



**Peer Global File Service
User Guide**

Copyright (c) 1993-2023 Peer Software, Inc. All Rights Reserved.

Updated Friday, March 31, 2023

Table of Contents

Peer Global File Service Help	1
Terminology	1
Installation and Configuration	8
Requirements and Prerequisites	9
Amazon FSxN Prerequisites	9
Dell EMC Prerequisites	9
NetApp Prerequisites	10
Nutanix Prerequisites	10
Installing Peer Management Center	10
Configuring and Managing the Web and API Services	16
Configuring the Web and API Services	16
Securing Access to the Web Client	18
Installing Peer Agents	18
Updating Peer Management Center and Peer Agents	22
Updating Peer Management Center	23
Updating Peer Agents	25
Peer Management Center User Interface	26
Accessing the Web Client	29
Peer Services Required for Web Client	31
Views	32
Agents View	33
Agents View Toolbar	35
Alerts View	35
Dashboard	37
Job Alerts View	38
Jobs View	39
Jobs View Toolbar	41
Runtime Views	42
Cloud Backup and Replication Job Runtime View	43
DFS-N Management Job Runtime View	44
File Collaboration Job Runtime View	45
Summary Tab	46
Session Tab	48
Event Log Tab	50
Quarantines Tab	52
Retries Tab	52
Alerts Tab	53
Participants Tab	54
Configuration Tab	56
File Replication Job Runtime View	57
File Synchronization Job Runtime View	58
Summary Views	59
Agent Summary View	60
Cloud Summary View	61
Collab, Sync, and Repl Summary View	62
Summary Tab	63
Dynamic Storage Utilization tab	65
Reports Tab	66

Namespace Summary View.....	70
Main Window Menus and Toolbar	70
File Menu	71
Help Menu	72
Window Menu	74
Toolbar	75
Tables	77
Basic Concepts	78
Email Alerts	78
File and Folder Filters	79
Creating and Applying File Filters.....	80
Predefined File Filters.....	81
Updating Predefined File Filters.....	81
Defining Filter Patterns.....	84
Using Wildcards in Filter Patterns.....	85
Automatically Excluded File Types.....	85
Excluding Temporary Files.....	86
Using Complex Regular Expressions in Filter Patterns.....	88
Filtering on Last Modified Date.....	88
Filtering on File Size	91
Filtering Folders	93
Folder Filter Examples	94
File Filter Usage Notes.....	95
List Filters	96
Creating Complex Filter Expressions.....	97
Saving and Managing List Filters.....	98
Removing List Filters	98
Logging and Alerts	98
Retrieving Log Files.....	100
Job Logs and Alerts.....	105
SNMP Notifications	106
Tags	107
Creating Tags and Categories.....	107
Assigning Tags	107
Using Tags to Filter Resources.....	110
Web Client Users	110
Internal Users	111
Active Directory Users and Groups.....	112
Overview of Web Roles.....	112
Standard Web Roles	113
Standard Web Role Permissions.....	113
Custom Web Roles	116
Custom Web Role Permissions.....	117
Advanced Topics	118
Analytics	119
Proactive Monitoring	120
Setting Up Proactive Monitoring.....	122
Step 1: General Configuration.....	123
Step 2: Telemetry Options.....	124
Step 3: Agent Locations.....	127
Step 4: Health Checker Setup.....	128
Set Up the Health Checker.....	130
Select Jobs	135

Schedule Task	136
Update Health Checker.....	137
Step 5: Confirmation	139
Disabling and Re-enabling Proactive Monitoring.....	141
Conflicts, Retries, and Quarantines	146
DFS Namespaces	147
Using DFS Namespaces with Jobs.....	149
DFS Namespace Failover and Failback.....	149
Dynamic Storage Utilization	150
DSU Glossary	151
File Metadata Synchronization	153
Network of Brokers	154
Managing Peer Agents	154
Peer Agent Connection Statuses.....	157
Re-enabling a Disabled Agent Within a Job.....	158
Editing an Agent Configuration.....	159
Broker	162
General	164
Logging	166
Performance	167
VM Options	169
Viewing Agent Properties.....	170
Editing Agent Properties.....	172
Updating a Peer Agent.....	174
PeerGFS API	174
Accessing the PeerGFS API.....	174
Testing the PeerGFS API.....	175
Integrating Your Own Tools and Scripts with the PeerGFS API.....	175
API Quick Reference.....	176
API Categories	176
Status Codes	177
Scheduled Replication	177
Smart Data Seeding	177
Storage Capacity	180
TLS Certificates	180
Creating New Certificates.....	180
Using Existing Certificates.....	187
Preferences	192
Configuring Preferences	193
Analytics Preferences	194
Proactive Monitoring Preferences	196
Cloud Backup and Replication Job Preferences	196
Cloud Backup and Replication.....	197
Database Connections.....	198
Destination Credentials.....	202
Email Alerts	205
File Retries and Source Snapshots.....	208
File and Folder Filters.....	211
Performance	214
Proxy Configuration.....	215
Replication and Retention Policies.....	219
SNMP Notifications.....	221
Scan Manager	223
Collaboration, Replication, and Synchronization Job Preferences	225

Collab, Sync, and Replication.....	226
Application Enhancements.....	227
DFS-N Management.....	230
Dynamic Storage Utilization.....	231
Dynamic Storage Utilization.....	231
Email Alerts.....	233
Master Data Service.....	236
Pinning Filters.....	238
SNMP Notifications.....	243
Utilization Policies.....	246
Volume Policies.....	249
Email Alerts.....	259
File Retries.....	265
File and Folder Filters.....	266
Locking.....	269
Performance.....	270
Real-time Event Detection.....	272
SNMP Notifications.....	274
Scan Manager.....	278
Scheduled Replication Filters.....	280
DFS-N Management Job Preferences.....	285
Email Alerts.....	287
SNMP Notifications.....	291
Email Configuration.....	294
General Configuration.....	297
General Configuration.....	298
Agent Connectivity.....	300
Broker Configuration.....	302
Email Alerts.....	303
Software Updates.....	306
Tags Configuration.....	308
Web and API Configuration.....	310
Licensing.....	311
MED Configuration.....	313
NAS Configuration.....	319
Amazon FSxN Configurations.....	319
Amazon FSxN Advanced Options.....	324
Dell EMC Configurations.....	325
Dell PowerScale EMC Isilon Credentials.....	328
Dell PowerScale EMC Isilon Advanced Options.....	329
Dell EMC Unity Credentials.....	333
Dell EMC Unity Advanced Options.....	334
Dell EMC VNX/Celerra Credentials.....	338
Dell EMC VNX/Celerra Advanced Options.....	339
NetApp 7-Mode Configurations.....	342
NetApp Data 7-Mode Advanced Options.....	346
NetApp cDOT Configurations.....	349
NetApp cDOT Advanced Options.....	353
Nutanix Files Configurations.....	354
Nutanix Files Advanced Options.....	358
Real-time Event Detection Preferences.....	360
SNMP Configuration.....	362
User Management.....	364
Managing Web Client Users.....	366

Managing Internal Users.....	366
Managing Active Directory Users.....	370
Configuring Active Directory Authentication.....	373
Managing Web Roles.....	376
Creating a Custom Web Role.....	377
Editing and Deleting Web Roles.....	381
Assigning Tags to Web Roles.....	382
Cloud Backup and Replication Jobs	382
Overview	383
Before You Create Your First Cloud Backup and Replication Job	383
Creating a Cloud Backup and Replication Job	383
Step 1: Job Type and Name.....	384
Step 2: Source Storage Platform.....	386
Step 3: Management Agent.....	387
Step 4: Proxy Configuration.....	388
Step 5: Storage Information.....	394
Amazon FSxN	395
Dell EMC Celerra VNX VNX 2.....	397
Dell EMC Unity	399
Dell PowerScale EMC Isilon.....	401
NetApp ONTAP Clustered Data ONTAP.....	403
NetApp Data ONTAP 7-Mode.....	405
Nutanix Files	407
Step 6: Source Paths.....	409
Step 7: File and Folder Filters.....	411
Step 8: Destination.....	412
Step 9: Destination Credentials.....	414
Azure Blob Storage Credentials.....	414
Amazon S3 Credentials.....	416
NetApp StorageGRID Credentials.....	418
Nutanix Objects Credentials.....	419
Step 10: Container or Bucket Details.....	420
Azure Blob Storage Container Details.....	421
Amazon S3 Bucket Details.....	423
NetApp StorageGRID Bucket Details.....	425
Nutanix Objects Bucket Details.....	427
Step 11: Replication and Retention Policy.....	429
Step 12: Replication Schedule.....	430
Scheduled Scans	431
Batched Real-Time	433
Continuous Data Protection.....	434
Step 13: Retention.....	435
Step 14: Source Snapshots.....	436
Step 15: Miscellaneous Options.....	437
Step 16: Email Alerts.....	440
Step 17: SNMP Notifications.....	442
Step 18: Confirmation.....	444
Editing a Cloud Backup and Replication Job	446
Running a Cloud Backup and Replication Job	446
Starting a Cloud Backup and Replication Job.....	446
Stopping a Cloud Backup and Replication Job.....	448
Monitoring Cloud Backup and Replication Jobs	449
Deleting a Cloud Backup and Replication Job	450
Recovering Data	451

Search Options	454
Search by Name	454
Search by Snapshot	457
Search by Point in Time.....	458
Search by Latest Replication.....	460
Recovery Options.....	460
DFS-N Management Jobs	464
Creating a DFS-N Management Job	465
Step 1: Job Type.....	466
Step 2: Management Agent.....	467
Step 3: Agent Verification.....	468
Step 4: Namespace Name.....	470
Step 5: Namespace Servers.....	471
Step 6: Namespace Settings.....	474
Step 7: Folders	475
Step 8: Email Alerts.....	481
Step 9: SNMP Notifications.....	484
Step 10: Review	486
Step 11: Results	487
Importing an Existing Namespace	490
Running a DFS-N Management Job	499
Starting a DFS-N Management Job.....	499
Stopping a DFS-N Management Job.....	501
Managing DFS Namespaces	501
Adding a Namespace Server.....	501
Adding a Namespace Folder.....	507
Adding a Namespace Folder Target.....	513
Linking a DFS Namespace to File Collaboration and File Synchronization Jobs	518
Creating a File Collaboration or File Synchronization Job from a Namespace Folder.....	519
Linking an Existing Namespace Folder to an Existing File Collaboration or File Synchronization Job.....	525
File Collaboration Jobs	530
Overview	530
Before You Create Your First File Collaboration Job	530
Creating a File Collaboration Job	531
Step 1: Job Type and Name.....	531
Step 2: Participants.....	533
Management Agent	535
Storage Platform	536
Storage Information	537
Amazon FSxN	538
Dell EMC Celerra VNX VNX 2.....	539
Dell EMC Unity	541
Dell PowerScale EMC Isilon.....	543
NetApp ONTAP 7-Mode.....	545
NetApp ONTAP Clustered Data ONTAP.....	547
Nutanix Files	548
Windows File Server	550
Windows File Server Advanced Options.....	551
Path	555
Dynamic Storage Utilization.....	556
Master Data Service	560
Volume Policy	563
Utilization Policy	566

Pinning Filter	568
Step 3: Master-Edge Assignment.....	572
Step 4: File Metadata.....	575
Step 5: Application Support.....	577
Step 6: Email Alerts.....	577
Step 7: DFS Namespace.....	580
Step 8: Save Job.....	584
Editing a File Collaboration Job	585
Participants	587
Adding and Deleting a Participant.....	588
Editing a Participant	595
Master-Edge Assignment.....	597
General	599
File and Folder Filters.....	601
Scheduled Replication Filters.....	602
Conflict Resolution.....	602
Delta Replication	604
File Metadata	606
File Locking	608
Application Support.....	613
Target Protection	613
Email Alerts	615
SNMP Notifications.....	617
Tags	618
DFS-N Link	619
Editing Multiple Jobs.....	620
Running and Managing a File Collaboration Job	622
Overview	622
Job Initialization Process.....	623
Initial Synchronization Process.....	623
Starting a File Collaboration Job.....	624
Stopping a File Collaboration Job.....	626
Auto-Restarting a File Collaboration Job.....	626
Host Connectivity Issues.....	628
Removing a File from Quarantine	629
Manual Retries	630
File Replication Jobs	630
Overview	631
Before You Create Your First File Replication Job	631
Creating a File Replication Job	631
Step 1: Job Type and Name.....	632
Step 2: Source Agent.....	633
Step 3: Storage Platform.....	634
Step 4: Storage Information.....	635
Amazon FSxN	636
Dell EMC Celerra VNX VNX 2.....	638
Dell EMC Unity	640
Dell PowerScale EMC Isilon.....	641
NetApp Data ONTAP 7-Mode.....	643
NetApp ONTAP Clustered Data ONTAP.....	645
Nutanix Files	646
Windows File Server	648
Windows File Server Advanced Options.....	649
Step 5: Source Path.....	653

Step 6: Destination Agent.....	654
Step 7: Destination Path.....	655
Step 8: File Metadata.....	656
Step 9: Email Alerts.....	658
Step 10: Save Job.....	660
File Synchronization Jobs	660
Overview	661
Before You Create Your First File Synchronization Job	661
Creating a File Synchronization Job	661
Step 1: Job Type and Name.....	662
Step 2: Participants.....	663
Management Agent	665
Storage Platform	666
Storage Information	667
Amazon FSxN	668
Dell EMC Celerra VNX VNX 2.....	670
Dell EMC Unity	672
Dell PowerScale EMC Isilon.....	674
NetApp Data ONTAP 7-Mode.....	675
NetApp ONTAP Clustered Data ONTAP	677
Nutanix Files	678
Windows File Server	680
Windows File Server Advanced Options.....	681
Path	684
Dynamic Storage Utilization.....	686
Master Data Service	689
Volume Policy	692
Utilization Policy	695
Pinning Filter	697
Step 3: Master-Edge Assignment.....	701
Step 4: File Metadata.....	704
Step 5: Email Alerts.....	706
Step 6: DFS Namespace.....	709
Step 7: Save Job.....	713
Editing a File Synchronization Job	713
Participants	716
Adding and Deleting a Participant.....	717
Editing a Participant	723
Master-Edge Assignment.....	727
General	729
File and Folder Filters.....	731
Scheduled Replication Filters.....	732
Conflict Resolution.....	734
Delta Replication	736
File Metadata	738
File Locking	740
Application Support.....	742
Target Protection	742
Email Alerts	744
SNMP Notifications.....	746
Tags	747
DFS-N Link	748
Editing Multiple Jobs.....	749
Running and Managing a File Synchronization Job	751

Overview	751
Job Initialization Process	752
Initial Synchronization Process	752
Starting a File Synchronization Job	753
Stopping a File Synchronization Job	755
Auto-Restarting a File Synchronization Job	755
Host Connectivity Issues	756
Removing a File from Quarantine	757
Manual Retries	758
PeerSync Management Jobs	759
Creating a PeerSync Management Job	759
Before You Create Your First PeerSync Management Job	760
Email Alerts	760
Integrating Existing PeerSync Instances	763
Requirements	763
How To	763
Deploying New PeerSync Instances	764
Requirements	764
How To	764
Step 1: General Information	765
Step 2: PeerSync Profile	766
Step 3: Jobs Configuration List	768
Step 4: Installation Settings	769
Logging and Alerts	772
Email Alerts	773
Running and Managing a PeerSync Management Job	774
Starting and Stopping	775
PeerSync Management Summary	776
PeerSync Management Dashboard Summary View	779
Managing the PeerSync Profile	780
Updating a Profile Configuration	781
Importing an Existing Profile	782
Editing and Configuring Jobs	783
Editing Global Settings	786
Distributing a Profile	787
Managing the PeerSync Service	788
Runtime Job Views	789
Summary View	790
PeerSync Jobs Stats	792
Added Files	792
Updated Files	793
Deleted Files	794
Messages	795
Failed Events View	796
Monitoring Log View	796
Alerts View	797
Participants View	798
Configuration View	800
Upgrade/Reprocess Installation	801

Peer Global File Service Help

Using This Help File

This help file is designed to be used online. It is cross-linked so that you can find more relevant information to any subject from any location. If you prefer reading printed manuals, a PDF version of the entire help is available from our website. This may be useful as a reference, but you will probably find that the active hyperlinks, cross-references, and active index make the on-screen electronic version of this document much more useful.

Trademark Information and Copyright

Copyright (c) 1993-2023 Peer Software, Inc. All Rights Reserved. Although we try to provide quality information, Peer Software makes no claims, promises, or guarantees about the accuracy, completeness, or adequacy of the information contained in this document. Peer Software, Peer Management Center, Peer Global File Service, PeerGFS, PeerSync, and their respective logos are trademarks or registered trademarks of Peer Software, Inc. Microsoft, Azure, Windows, Windows Server, and their respective logos are trademarks or registered trademarks of Microsoft Corporation in the United States and/or other countries. NetApp, the NetApp logo, Data ONTAP, and FPolicy are trademarks or registered trademarks of NetApp, Inc. in the United States and/or other countries. "Amazon Web Services", "AWS", "Amazon S3", "Amazon Simple Storage Service", "Amazon SNS", "Amazon Simple Notification Service", and their respective graphics, logos, and service names are trademarks, registered trademarks or trade dress of Amazon Web Services LLC and/or its affiliates in the U.S. and/or other countries. Dell, EMC, Celerra, Isilon, VNX, Unity and other trademarks are trademarks of Dell Inc. or its subsidiaries. Nutanix is a trademark of Nutanix, Inc., registered in the United States and other countries. All other trademarks are the property of their respective companies. Peer Software vigorously protects and defends its trade name, trademarks, patents, designs, copyrights, and other intellectual property rights. Unless otherwise specified, no person has permission to copy, redistribute, reproduce, or republish in any form the information in this document.

Last updated: Friday, March 31, 2023

PeerGFS Version 5.1.1

Terminology

Introduction

Before getting started, it is important to have a good understanding of key concepts and terminology used throughout this help system.

Terms

Term	Definition
Active-Active	Two or more file servers that hosts data sets that are in active use, as opposed to an active-passive environment where only one file server hosts active data. Made possible by real-time file synchronization to keep all file servers in sync.
Agent	See <i>Peer Agent</i> .
Cloud Backup and Replication job	A job type where a single participating host has a designated set of folders and files to be replicated to a cloud storage device.
DFS (Distributed File System)	A set of client and server services that allow an organization using Microsoft Windows servers to organize many distributed SMB file shares into a distributed file system.
DFS namespace (DFS-N)	A namespace that enables you to group shared folders located on different servers into one or more logically structured namespaces.
DFS Namespaces	A Windows Server feature that allows multiple SMB shares across different file servers (and even locations) to be combined into a single unified namespace. DFS Namespaces simplifies access to files, especially in large, distributed environments. When combined with Peer file synchronization technology, DFS Namespaces can provide redundancy to file shares across file servers and locations.
DFS-N Management job	A type of job that enables the creation and management of DFS namespaces.
Event	A single operation performed by a user on a file server.

Term	Definition
Failback	The process of redirecting previously displaced users from a secondary file server back to the primary after a failure state has been resolved.
Failover	The process of redirecting users from one file server to a secondary in the event of a failure.
File access event	An event that is triggered from the opening or closing of a file.
File change event	An event that causes a file to be changed in some way, for example, file modify, file delete, file rename, file attribute change.
File Collaboration job	A type of job that combines file synchronization with distributed file locking to prevent version conflicts across multiple active file servers.
File Collaboration session	A communication session made up of two or more hosts, each with a designated root of folders and files that are to be shared or collaborated on. A collaboration session coordinates the primary functions of file locking and synchronization.
File filter	A type of filter used to include or exclude specific files from replication and locking.
File lock conflict	A file collaboration condition that exists when two users open a file at the same time, and both hold exclusive locks on the file.
File Replication job	A type of job that involves real-time and/or scheduled copying of files and folders from one file server to another.

Term	Definition
File Synchronization job	A type of job that involves multi-directional real-time replication so that two or more file servers are always up to date with each other.
Filter	Three types of filters: file, folder, and list.
Filter expression	<i>See list filter.</i>
Folder filter	A type of filter used to include or exclude specific folders (and the files they contain) from replication and locking.
Heartbeat	A communication mechanism used between Peer Management Center and all connected Peer Agents to ensure that Peer Agents are alive and responsive. Heartbeats share information about the Peer Agent host server with Peer Management Center, aid in verifying when a Peer Agents is no longer available, and signal when a disconnected Peer Agent has reconnected. All heartbeat information is sent through the Peer Management Broker.
Host	A server that a Peer Agent is installed upon.
Initialization process	The steps executed whenever a job is started in Peer Management Center. The steps for an initialization process are different for each job type.
Initial synchronization process	The background process that occurs at the start of a file collaboration session, where the directory watch set is recursively scanned on all participating hosts, file conflict resolution is performed, and any files that require updating are synchronized with the most current copy of the file.

Term	Definition
List filter	A type of filter used to show or hide information from various views in Peer Management Center.
Management Agent	A server running the Peer Agent. Can manage storage devices or a DFS namespace.
Master host	In file synchronization and collaboration, the master host will always win in a split-brain scenario.
Malicious Event Detector (MED)	Leverages the same real-time event detection that powers all job types to detect and alert administrators to malicious user and application behavior. For more information, see: https://kb.peersoftware.com/tb/introduction-to-peer-med .
Participant	A participant consists of an Agent and the volume/share/folder to be replicated. Applies to File Collaboration, File Replication, and File Synchronization jobs.
Peer Agent (or Agent)	A lightweight piece of software that is installed on Windows Servers to perform the storage and file management functions used by the entire Peer Global File Service solution suite. Typically installed on or alongside the file servers that will be managed by Peer Management Center.
Peer Management Center (PMC)	The focal component of Peer Global File Service. Responsible for configuration, management, and monitoring of Peer Agents and the various solutions configured in Peer Global File Service. Peer Management Center runs as three parts: a Windows Service that is always running, along with a rich client application and a web server component, both used for configuration and monitoring.

Term	Definition
Peer Management Broker	The central messaging system of Peer Global File Service. The Peer Management Broker serves to connect Peer Management Center and Peer Agents, forming a Peer Management Center "network" that can be cast over local or wide-area networks via TCP/IP. One or more Peer Management Brokers are deployed in a Peer Management Center environment.
Quarantined file	A file that has been removed from a File Collaboration or File Synchronization job as a result of a lock or replication conflict that could not be automatically resolved. This file will not be deleted from any location but will be ignored while it remains in quarantine. An administrator or help desk user must manually remove files from quarantine.
Quorum	Requirement for a minimum of two participants must be available and connected. If that number dips to one or less, quorum will not be met. Applies to File Collaboration, File Replication, and File Synchronization jobs.
Real-time event detection	A key technology that backs all job types in Peer Management Center. Peer Management Center receives notifications as end users interact with the file servers that are being monitored. These notifications will usually result in replication or locking between file servers.
Scan	The initial process of comparing data sets on two or more file servers to ensure that they match. As differences are discovered, replication will occur to bring each file server "in sync" with one another.
Seeding target	Smart data seeding helps to efficiently integrate a host that has been disconnected for a long period of time or a new host into a File Collaboration job. Such existing hosts or new hosts with pre-seeded data (using

Term	Definition
	methods like shipping a drive or server) should be set as Seeding Targets within a collaboration job. When the scan starts, non-Seeding Targets will become the masters and bring the Seeding Targets up to date. Stale updates, deletes, and renames will NOT be brought back from the Seeding Targets. All local real-time activity will be quarantined. Once that initial scan is complete, the Seeding Targets will become full participants with real-time enabled. For more information on Smart Data Seeding and its potential options, see Smart Data Seeding or contact support@peersoftware.com .
SMB/CIFS	Server Message Block or Common Internet File System, an application-layer protocol used for providing shared access to file data and other networked resources.
Source host	The file server hosting a file from which file access or change event originated.
Target host	One or more Management Agents of file servers where file access and change events will be propagated to.
TLS	Transport Layer Security, a successor to Secure Socket Layer (SSL) that secures network traffic between a client and server.
UNC Path	A UNC path can be used to access network resources and must be in the format specified by the Universal Naming Convention. A UNC path always starts with two backslash characters (\\).
View	Individual sections of Peer Management Center's user interface, each providing unique information and control.

Term	Definition
	Examples: Main view, Jobs view, Agent Summary view, Alerts view, Job Alerts view.
Volume Shadow Copy Service (VSS)	Shadow Copy is a technology included in Microsoft Windows that allows taking manual or automatic snapshots of computer files or volumes, even when they are in use. It is implemented as a Windows service called the Volume Shadow Copy service.
Watch set	The root folder and all subfolders on a file server that are being scanned and/or monitored by a File Collaboration, File Replication, File Synchronization, or Cloud Backup and Replication job.

Installation and Configuration

This topics in this section provide information about:

[Requirements and Prerequisites](#)

[Installing Peer Management Center](#)

[Installing Peer Agents](#)

[Updating Peer Management Center and Peer Agents](#)

[Configuring and Managing the Web and API Services](#)

For information about Peer Global File System licensing, see [Licensing](#).

Requirements and Prerequisites

Before you get started, review the environmental requirements and platform prerequisites for using Peer Global File Service:

- [Peer Global File Service environmental requirements](#)
- [Amazon FSxN](#)
- [Dell EMC Prerequisites](#)
- [NetApp Prerequisites](#)
- [Nutanix Prerequisites](#)

Amazon FSxN Prerequisites

In addition to the standard [Peer Global File Service environmental requirements](#), the following prerequisites must be met:

- [Amazon FSx for NetApp ONTAP Prerequisites](#)

Dell EMC Prerequisites

In addition to the standard [Peer Global File Service environmental requirements](#), the following prerequisites must be met:

- [Dell PowerScale | EMC Isilon Prerequisites](#)
- [Dell EMC Unity Prerequisites](#)
- [Dell EMC Celerra | VNX | VNX 2 Prerequisites](#)

CEE Server Configuration

See the following guides for steps on setting up a CEE Server on which the Peer Agent will be running:

- [Dell PowerScale | EMC Isilon Configuration Guide](#)

- [Dell EMC Unity Configuration Guide](#)
- [Dell EMC Celerra | VNX | VNX 2 Configuration Guide](#)

NetApp Prerequisites

In addition to the standard [Peer Global File Service environmental requirements](#), the following prerequisites must be met:

- [NetApp Data ONTAP 7-Mode Prerequisites](#)
- [NetApp ONTAP | Clustered Data ONTAP Prerequisites](#)

Nutanix Prerequisites

In addition to the standard [Peer Global File Service environmental requirements](#), the following prerequisites must be met:

- [Nutanix Files prerequisites](#)

Installing Peer Management Center

Overview

Peer Management Center (PMC) can be installed in numerous ways based on your needs and environment. Peer Management Center installation consists of two separate installers, both of which are available for download from the Peer Software website:

- **Peer Management Center installer:** This installer installs both Peer Management Center and [Peer Management Broker](#) on the same server. Peer Management Broker handles the communication between Peer Management Center and Peer Agents. See [Installing and Launching Peer Management Center](#) for installation instructions.
- **Peer Agent installer:** This installer contains the Peer Agent installation files. You must install an Agent on each server you plan to include in any of your jobs. See [Installing Peer Agents](#) for installation instructions.

Before installing Peer Management Center, see [Requirements and Prerequisites](#) to verify that your environment satisfies the requirements and prerequisites.

Installing and Launching Peer Management Center


To install and launch Peer Management Center and Peer Management Broker:

1. Download the Peer Management Center installer (**PMC_Installer_win64.exe**) to the server you want to host Peer Management Center.
2. Run the installer and follow the installation wizard instructions.


During the installation, you will be prompted to configure access to the **Peer Management Center Web Service** and the **Peer Management API Service**. The web service allows users to access Peer Management Center via a web browser; the API service allows access to Peer Management Center through REST API calls. For detailed instructions on configuring access to these services, see [Configuring the Web and API Services](#).

3. On the final page of the installation wizard, you have several options; we recommend that, at minimum, you select the first option.

If you enabled the Peer Management Web Service and selected the **Launch the Peer Management Center Web Client**, on the final page of the installation wizard, the default username and password for accessing the web client is displayed. After [logging in to the web client](#), you should [change the password](#) immediately.




When the installation is complete, the Peer Management Center installation folder contains the following files and folders:



The **PL-Hub.exe** executable launches **Peer Management Center Client**, which is a Windows rich client application.

Four Windows services have been installed and are set to auto-start:




- If you didn't select the option to launch Peer Management Center Client on the last page of the installation wizard, launch it using one of the following methods:

- Select **Peer Management Center** from the Windows **Start** menu.
- Double-click the **PL-Hub.exe** executable in the Peer Management Center installation directory.


If both the **Peer Management Center Service** and the **Peer Management Broker Service** are up and running as background services, then Peer Management Center should successfully start. If not, open the Windows Service Panel (services.msc) and start both services.

5. When launching Peer Management Center Client for the first time, you are prompted to install your license. If you haven't already done so, copy the license to the desktop of the Peer Management Center server.




6. Click **Add/Update**.
7. Browse to where the License file is located and select the file.
8. Click **Open**.

The **License Information** tab displays your license information.



9. Click **Apply and Close**.



Now you are ready to [install the Peer Agents](#).

Uninstalling Peer Management Center

Peer Management Center ships with an uninstaller for the environment it is running in. Please use the standard platform-specific method for removing programs/applications to uninstall Peer Management Center.

Configuring and Managing the Web and API Services

As part of the [initial installation of Peer Management Center](#), you are prompted to configure access to the web and API services. The web service allows users to access Peer Management Center via a web browser; the API service allows access to Peer Management Center through REST API calls.

If you enable access to the web client, you will need to secure access to the web client and manage web client user accounts.

See the following topics for more information:

- [Configuring the Web and API Services](#)
- [Securing Access to the Web Client](#)
- [Accessing the Web Client](#)
- [Managing Web Client Users](#)

You can configure access to the web and API services during the [initial installation of Peer Management Center](#). If you do not enable access during the initial installation or want to modify settings at a later date, you can modify them through [Web and API Configuration in Preferences](#).

Configuration Options

To configure the web and API services during the initial installation of Peer Management Center:

1. Enter the requested values when the configuration page appears in the installation wizard.

Setup - Peer Management Center 5.0.0.20220601

Peer Management Center Web and REST API Configuration

Provide the name or IP address through which clients will connect to the Peer Management Center Web Service and Web REST API.

Hostname or IP:

Enable HTTPS Web Access using port:

Enable HTTPS REST API using port:

< Back Next > Cancel

Field	Description
Hostname or IP	Enter the hostname or IP address via which the services can be accessed: <ul style="list-style-type: none"> • Enter localhost or 127.0.0.1 if you want the services to be accessible only to users of the local server via the loopback interface. • Enter 0.0.0.0 to make the services accessible via all network interfaces. • Enter a specific IP address to restrict access to a specific network interface.
Enable HTTPS Web Access	Select this to enable secure access to the web service, and then enter a port number.
Enable HTTPS	Select this to enable secure access to the REST API service, and then enter a port number. The REST API port cannot be the same as the web

Field	Description
REST API	service port.

2. Click **Next** to continue with the rest of the installation wizard.

Access to Peer Management Center's web client is through HTTPS, which ensures that all communication between the browser and the service hosting the web client is encrypted. However, you may want to take additional actions to secure access to Peer Management Center's web client:

- You can limit users' access to the web client when you configure the hostname or IP address for web access. For example, enter **localhost** or **127.0.0.1** if you want the web client to be accessible only to users of the local server via the loopback interface. See [Configuring the Web and API Services](#) for more details.
- While HTTPS access to the web client is secured out of the box with a built-in Transport Layer Security (TLS) certificate, this certificate can be swapped for a custom one. See TLS Certificates in Advanced Topics for information on using existing certificates and creating new certificates.
- The default password for the admin account should be changed immediately. See Editing an Internal User for information about changing the password.

Installing Peer Agents

Overview

You will need to install a Peer Agent on each server you plan to include in any of your jobs. After installing the Peer Agent software, you should verify that the **Peer Agent Service** is running and can successfully connect to the [Peer Management Broker](#).

Note: For customers using clustered file server roles with Windows Failover Cluster, please review this Peer Software knowledge base article: [Windows Failover Cluster support for the Peer Agent](#).

Installing a Peer Agent


To install a Peer Agent and verify its connection to Peer Management Broker:

1. Download the Peer Agent installer (**P-Agent_Installer_win64.exe**) to the server you want to host the Agent.
2. Run the installer and follow the wizard instructions.

During installation, you will be prompted for:


- The Peer Management Broker hostname (computer name, fully qualified domain name, or IP address) of the server where Peer Management Broker is running.
- The TCP/IP port number of the server where Peer Management Broker is running. The default port for TLS communication is 61617.

Enter the same values that you entered when [installing Peer Management Center and Peer Management Broker](#).



The screenshot shows a Windows-style window titled "Setup - Peer Agent 4.6.0.20210316". The main heading is "Peer Management Broker Configuration". Below the heading, it says "Please provide the hostname, protocol and TCP/IP port of the Broker." There is a green arrow icon pointing right. The form has three fields: "Hostname:" with an empty text box and a green question mark icon; "Protocol:" with a dropdown menu showing "SSL" and a green question mark icon; and "Port:" with a text box containing "61617" and a green question mark icon. Below the fields, it says "Please note that enabling SSL/TLS may reduce performance." At the bottom, there are three buttons: "< Back", "Next >" (which is highlighted with a blue dashed border), and "Cancel".

You will also need to provide the account credentials under which the Peer Agent Service will run.



Setup - Peer Agent 4.6.0.20210316

Agent Service Account
Provide the account under which the Agent Service will run.

Enter Domain Credentials (Recommended)

Domain\UserName PEERTEST\debrag


Password

Re-enter Password


Use Local System account

< Back Next > Cancel

3. When the last page of the installation wizard appears, click **Finish**.



4. After the installation finishes, the Peer Agent is installed as a Windows service. You will need to verify that the **Peer Agent Service** is running, and that it was able to successfully connect to [Peer Management Broker](#). You can do this by opening the Windows Services Panel (services.msc) and verifying that the **Peer Agent Service** has started.



Secure Encrypted TLS Connections

By default, the Peer Agent is installed with Transport Layer Security (TLS) encryption enabled, where the Peer Agent connects to Peer Management Broker through a secure, encrypted connection. If you are running Peer Management Center on a secure LAN or via a corporate VPN, you might want to disable TLS to boost performance. For more details on disabling or enabling encryption for the Peer Agent, see [Broker Configuration](#).

Uninstalling a Peer Agent

Peer Agent ships with an uninstaller for the environment it is running in. Please use the standard platform-specific method for removing programs/applications to uninstall the Peer Agent.

Updating Peer Management Center and Peer Agents

You can easily check for updates to the Peer Management Center software. Minor releases can be automatically downloaded and installed. Major releases require a new license key and must be requested from Peer Software Support.

For details about updating, see:

- [Updating Peer Management Center](#)
- [Updating Peer Agents](#)

Updating Peer Management Center

Overview

There are two ways to check for software updates:

- You can manually check for software updates using the **Check for Updates** command on the **Help** menu. **Note:** This command is not available in the Peer Management Center Web Client.
- You can also configure Peer Management Center to automatically check for updates and download the updates. For more information, see the [Software Updates](#) setting in [Preferences](#).


Note: For customers running the PMC on a Windows Failover Cluster, please review this knowledge base article: <https://kb.peersoftware.com/tb/windows-failover-cluster-support-for-the-pmc>. The steps for upgrading the PMC on a Windows Failover Cluster are the same as installing the PMC for the first time.

Manually Checking for and Installing an Update

To manually check for an update:


1. From the **Help** menu, select **Check for Updates**.

The **Check for Updates** dialog appears. If a minor update is available, the dialog identifies the new version (and your current version) and provides a link to the release notes. If a major update is available, the dialog presents a link to an announcement page on the Peer Software website.



2. Click **Yes** to download the Peer Management Center installer.

As the update is downloaded, a progress bar appears in the lower right corner of the Peer Management Center window. After the download is complete, the **Check for Updates** dialog displays information about the upgrade process.



3. Click **Yes** to install the upgrade; click **No** to install the update at a later time.

If you clicked **No**, you can install the update later by going to the folder shown in the dialog.

If you clicked **Yes**, the **Setup** wizard appears.

4. Follow the prompts in the **Setup** wizard to install the update.

When updating a Peer Management Center installation, you will not be prompted to specify web and API access. The settings entered previously will be used. If you wish to change those settings, you can do so by modifying them in [Web and API Configuration in Preferences](#).

5. After the Peer Management Center upgrade is installed, update the Peer Agents. See [Updating Peer Agents](#) for details.


Updating Peer Agents

You can view the [status](#) of your Peer Agents in the [Agents](#) view. Whenever you [update Peer Management Center software](#), you need to update the Peer Agent software before you can start any jobs managed by that Agent. When **Update Required** appears next to an Agent's name, that indicates the software needs updating.


Note: For customers using clustered file server roles with Windows Failover Cluster, please review this knowledge base article: <https://kb.peersoftware.com/tb/windows-failover-cluster-support-for-the-peer-agent>. The steps for upgrading Agents tied to clustered file server roles is the same as installing these Agents for the first time.

To update Peer Agents:


1. Select the Agents in the **Agents** view.



2. Right-click and select **Install Software Updates**.




A confirmation dialog appears.



3. Click **Yes**.
4. Follow the prompts in the **Update Agent Software** dialog to complete the update.

After the Agents are updated, the Agents appear in green. The Agents automatically restart as part of the upgrade. Any jobs set to auto-start will restart once the Agents have reconnected.



Peer Management Center User Interface

Peer Management Center is a management interface for configuring and deploying jobs, as well as view summary and runtime information for jobs. It offers two graphical user interface options:

- A **rich client** installed and run on the server running Peer Management Center.
- A **web client** that, when configured, can be [accessed](#) from remote systems via a web browser. You can manage and monitor jobs via the robust Peer Management Center web client. Unlike many other web management consoles, Peer Management Center's web client is very responsive and is built to mirror the functionality of the rich client (which is included with the Peer Management Center installer for use by system administrators). When configured, the web client allows for the management of Peer Management Center from remote clients without the need to directly log into the Peer Management Center server.

The interface can be divided into four quadrants: each quadrant displays information in panels called [views](#). A view can contain one or more tabs. See [Views](#) for more information about the views.

The screenshot displays the Peer Management Center Client interface, which is divided into four quadrants:

- Jobs View:** Located on the left side, it shows a tree view of jobs categorized by type (e.g., Cloud Backup and Replication, DFS-N Management, File Collaboration, File Replication, File Synchronization).
- Summary and Runtime Views:** The central area, displaying a table of job details. The table includes columns for Name, Overall Status, Job Type, Failed Hosts, Quaran..., Retries, Errors, Warnings, Open Files, Pending Bytes, Pending Events, Queued Items, Background..., Scan Status, Elapsed Tl..., and Session Structure. A summary bar at the bottom indicates: "Active Jobs -> Failed Participants: 0 of 2 | Bytes Pending: 0 bytes | Bytes Transferred: 325.01 MB | Opens: 0 | Initial Scans Completed: 2 of 6 | Total Size: 713.23 MB | Total Files: 11920 | Total Directories: 116".
- Alerts and Task History Views:** Located at the bottom, it shows a list of alerts and task history. The table includes columns for Received Date, Severity, Type, Name, Host, Message, and Exception. Alerts include "Host Failure", "Auto Start Job", "Host Reconnect Startup Error", and "Host Reconnect Startup Error".
- Agents View:** Located at the bottom left, it shows a list of agents with columns for Agent, Version, and Status. Agents listed include DGAgent1 and DGAgent2, both connected.

Description of Quadrants

The quadrants are described in the following table.

Quadrant	Description
Upper right	Contains one view, the Jobs view , which displays a list of all jobs, grouped by job type. The toolbar in this view allows you to start and stop jobs.
Bottom right	Contains one view, the Agents view. The Agents view displays a list of known Peer Agents and connection status for each. Individual Peer Agents can be updated and restarted from this view as well by right-clicking on one or more items and selecting the appropriate item from the pop-up menu.
Upper right	<p>Several types of views are displayed in this area, including:</p> <ul style="list-style-type: none"> • A dashboard that provides metrics and key performance indicators. • Summaries of jobs by job type. • An Agent Summary view, which displays a list of all known Peer Agents deployed and detailed status information that can be used to assess the health of the environment. • Runtime statistics for individual jobs.
Lower left	<p>Contains a variety of views, including:</p> <ul style="list-style-type: none"> • The Alerts view, which displays a list of Peer Management Center alerts that have occurred with detailed information about each alert. Alerts relating to Peer Agent connection status changes are reported here. • The Jobs Alerts view, which displays a list of job-specific alerts that have occurred. Alerts relating to the automatic stopping and restarting of jobs are displayed here.

For information about other aspects of the user interface, see:

- [Accessing the Web Client](#)
- [Views](#)
- [Main Window Menus and Toolbar](#)
- [Tables](#)

Accessing the Web Client

Once Peer Management Center has been installed, the Peer Management Center Web Client Service has been configured, and the [necessary Peer services](#) have been started, users can access the Peer Management Center web client in various ways:

- Log in directly through a web browser on the local Peer Management Center server.
- Remote access from another system on a network that can reach the Peer Management Center server.
- Start the Peer Management Center Client (rich client application) and select **Peer Management Center Web Client** from the **Help** menu.

Logging into the Web Client

To access the Peer Management Center web client:

1. Open a web browser.
2. Enter one of the following URLs in the address field:


If this URL was entered in the Installation Wizard	Use this URL
A specific IP address	Enter https:// followed by that IP address and :8443/hub . You cannot use localhost even if you are directly logged into the Peer Management Center server. For example: https://10.0.0.1:8443/hub
localhost or 127.0.0.1	Enter https://localhost:8443/hub or https://127.0.0.1:8443/hub .
0.0.0.0	Enter https:// followed by the IP address of the Peer Management Center server and :8443/hub

If this URL was entered in the Installation Wizard	Use this URL
	For example: https://10.0.0.1:8443/hub

Notes:

- The URL will depend on how the web service was configured during the installation process; you may need to contact the administrator who installed Peer Management Center to determine the correct URL
- 8443 is the default HTTPS port and should be replaced with the port used in your environment if it is different.
- **/hub** is required after the port number to reach the PMC client UI.
- You can modify the web service configuration on the [General Configuration](#) page of [Preferences](#). For more information, see [Web and API Configuration](#).

The login page is displayed.




3. Enter a user name and password.

- The default user name is **admin**; the default password is **password**. For security reasons, we highly recommend that the user immediately changes the **admin** password. See [Editing an Internal User](#) for more information on changing account passwords.
- If logging in with an Active Directory account, enter the user name in this format: username@mydomain.local.

4. Click **Login**.

Peer Services Required for Web Client

To use the Peer Management Center web client, the following Peer services must be running on the Peer Management Center server:



If a required service is not running, open the Windows Service Panel (services.msc) on the applicable PMC server and start the service.

Views

The Peer Management Center interface can be divided into four quadrants; each quadrant displays information in panels called [views](#). A view can contain multiple tabs. There are various types of views. For example, some views display a combination of real-time file I/O activity, history, and configuration information for a specific job; others display a summary of information about all jobs of a specific type.

The screenshot displays the Peer Management Center Client interface with four distinct views highlighted by red boxes:

- Jobs View:** Located on the left side, it shows a tree view of jobs categorized by type (e.g., Cloud Backup and Replication, File Collaboration, File Replication, File Synchronization).
- Summary and Runtime Views:** The central area, featuring a table with columns for Name, Overall Status, Job Type, Failed Hosts, Quarantined, Retries, Errors, Warnings, Open Files, Pending Bytes, Pending Events, Queued Items, Background, Scan Status, Elapsed Time, and Session Structure. A filter bar is visible above the table.
- Alerts and Task History Views:** Located at the bottom, it displays a list of alerts with columns for Received Date, Severity, Type, Name, Host, Message, and Exception. The message column contains detailed error logs.
- Agents View:** Located at the bottom left, it shows a list of agents with columns for Agent, Version, and Status (e.g., Connected).

The primary views include:

- [Agents View](#)
- [Jobs View](#)
- [Dashboard](#)
- [Alerts View](#)
- [Job Alerts View](#)
- [Summary Views](#)
 - [Agent Summary View](#)
 - [Cloud Summary View](#)

- [Collab, Sync, and Repl Summary View](#)
- [Namespace Summary View](#)
- [Runtime Views](#)
 - [Cloud Backup and Replication Job Runtime View](#)
 - [DFS-N Management Job Runtime View](#)
 - [File Collaboration Job Runtime View](#)
 - [File Replication Job Runtime View](#)
 - [File Synchronization Job Runtime View](#)

Displaying Views

You can open views in a variety of ways:

- Selecting a command from the **Window** menu
- Right-clicking on an item to display a context menu.
- Clicking the **View** button in a toolbar and selecting an option from the View menu.

Resizing Views

You can resize views in a variety of ways:

- Drag the separator between views.
- Click the minimize or maximize button in the toolbar.
- Reset all views to the default size by selecting the **Reset Perspective** command on the **Window** menu.

Agents View

The **Agents** view is displayed in the lower left quadrant of the Peer Management Center interface and lists all known Peer Agents installed in your environment and displays the current

[connection status](#) for each. For more information, see [Agent Connection Statuses](#). This view is automatically displayed when Peer Management Center is started.

To filter a large list of Agents, use the **Filter** field located below the [Agents view toolbar](#). For more details on how to filter agents, see [List Filters](#).

The screenshot shows the Peer Management Center Client interface. The 'Agents' view is active, displaying a list of agents with columns for Agent, Version, and OS. The agents listed are DGWin16A, DGWin16B, DGWin16C, and DGWin16D, all connected and running on Windows Server 2016. The 'Host Participants' table above shows two hosts, DGWin16B and DGWin16C, both in a 'Not Participating' state. The 'Host Participant State Change Log' below the table shows a series of events including agent startups and connection status changes for DGWin16A, DGWin16B, DGWin16C, and DGWin16D.

Host	Root Path	Status	State	Message	DFS Namespace	DFS Target Status	DSU Role
DGWin16B	C:\Data\Projects	Not Participating	Inactive		N/A	N/A	None
DGWin16C	C:\Data\Projects	Not Participating	Inactive		N/A	N/A	None


Date	Host	Status	State	Message
06-03-2022 15:18:04	DGWin16C	Not Participating	Inactive	
06-02-2022 14:49:17	DGWin16B	Not Participating	Inactive	
06-02-2022 14:44:17	DGWin16B	Not Participating	Inactive	

Received Date	Severity	Type	Name	Host	Message
06-02-2022 04:51:51	Info	Connection	Startup	DGWin16A	Agent Started
06-02-2022 04:51:45	Info	Heartbeat	Reconnect	DGWin16A	Connection status changed from Disconnected to Connected
06-02-2022 04:51:26	Info	Connection	Startup	DGWin16B	Agent Started
06-02-2022 04:51:18	Info	Connection	Startup	DGWin16C	Agent Started
06-02-2022 04:51:18	Info	Heartbeat	Reconnect	DGWin16C	Connection status changed from Disconnected to Connected
06-02-2022 04:51:11	Info	Connection	Startup	DGWin16D	Agent Started

Updating Peer Agent Software

If the Peer Agent software running on a host is out of date, the host will be shown as having a pending update in this view. When right-clicking the Agent, the option to automatically update the Peer Agent software will also be available. You can update directly from the Peer Management Center; updating usually does not require any additional actions on the host server itself. See [Updating Peer Agents](#) for more information.

The following buttons are available on the toolbar in the Agents view:



Button	Description
Show Agent Summary	Opens the Agent Summary view , which provides details for all known Agents and their status.
Manage, Save and Load Filters	Allows for the selection of predefined or user-defined filters and to save and manage filters. Default Agent filters include Connected and Disconnected .
Assign Tags	Opens the Assign Tags dialog where resources can be viewed and assigned to tags or categories. Tagging resources helps when managing large number of resources.

Alerts View

The **Alerts** view is displayed in the lower right quadrant of the Peer Management Center interface and displays various system alerts. The **Alerts** view is automatically displayed when a critical system alert (Error or Fatal) is received. You can also [set the Alerts view to be automatically displayed](#) when Peer Management Center is started.

The screenshot displays the Peer Management Center Client interface. The main window shows a 'Summary Reports' section with a 'Runtime Summary (auto-update enabled)' table. The table lists various jobs with columns for Name, Overall Status, Job Type, Failed Hosts, Quorum, Retries, Errors, Warnings, Open Files, Pending Bytes, Pending Events, Queued Items, Background, Scan Status, Elapsed TL, and Session Structure. Below the table, there is a summary of active jobs: 'Failed Participants: 2 of 2 | Bytes Pending: 0 bytes | Bytes Transferred: 0 bytes | Opens: 0 | Initial Scans Completed: 2 of 6 | Total Size: 713.23 MB | Total Files: 1920 | Total Directories: 116'.

An 'Alerts' window is open at the bottom, showing a table of alerts with columns for Received Date, Severity, Type, Name, Host, Message, and Exception. The alerts include informational messages (Info), warnings (Warning), and errors (Error) related to agent connections and heartbeat status.

System alerts vary in their severity. The four categories of alerts are:

- Informational (containing Info, Debug, and Trace)
- Warning
- Error
- Fatal

An example of an Informational alert is when a [Peer Agent](#) connects to the [Peer Management Broker](#). If a Peer Agent's network connection is severed, then an Error alert will be logged. All alerts are also logged to the file **hub_alert.log**, available under the **Hub\logs** subdirectory within the Peer Management Center installation directory.

You can filter alerts based on host name, severity level, or type, and you can sort alerts by clicking on a specific column header. You can also clear all alerts in the table by clicking the **Clear Alerts** link.

Displaying the Alerts View

You can open the **Alerts** view at any time by clicking the **View Alerts** button located on the Peer Management Center toolbar or by selecting **View Alerts** from the **Show View** submenu of the **Window** menu. You can close the **Alerts** view at any time by clicking on the **X** (Close) button on the **Alerts** tab.

You can resize the Alerts view by dragging the separator between the upper view and the Alerts view, or you can double-click the **Alerts** tab to maximize the view. You can restore the view to its original, non-maximized size by double-clicking the **Alerts** tab again.

Dashboard

The Dashboard is divided into two sections:

- **Collab, Sync, and Repl** - This top section displays a table of metrics and key performance indicators for all running File Collaboration, File Synchronization, and File Replication jobs. It also contains a link that opens the [Collab, Sync, and Repl Summary view](#). Entries in the table's first column can be double-clicked to display a filtered runtime view of the selected item for additional details.
- **Agents** - The bottom section displays information about Agents. It also contains a link that opens the [Agent Summary view](#).

Click the triangle to the left of the section name to collapse and expand the section.

For performance reasons, the Dashboard is not updated in real-time. However, you can set the table to be automatically updated every few seconds by selecting the **Auto-Update** checkbox, and then choosing the update interval.

The screenshot displays the Peer Management Center Client interface. The main window is titled 'Dashboard' and features an 'Auto-Update' checkbox and a 'Refresh' button with a 10-second interval. The dashboard is divided into two main sections: 'Collab, Sync, and Repl' and 'Agents'.

The 'Collab, Sync, and Repl' section includes a 'Summary View' link and a table of metrics:

1 Running with Quarantines!		Active Statistics		Active Watch Set	
Running with Quarantines	1	Failed Participants	0 of 2	Total Size:	713.23 MB
Running with Disconnected Agents	0	Bytes Pending:	0 bytes	Total Files:	11920
Lost Quorum	0	Bytes Transferred:	0 bytes	Total Directories:	116
Not Running - Stopped	12	Opens:	0		
Running in Good State	1	Initial Scans Completed:	2 of 2		

The 'Agents' section includes an 'Agent Summary' link and a pie chart for 'Agent Memory Load' showing 0-49%, 50-74%, and 75-100% categories. Below the dashboard is an 'Alerts' section with a table of recent alerts:

Received Date	Severity	Type	Name	Host	Message	Exception
04-21-2021 01:51:43	Info	Connection	Startup	DGAgent2	Agent Started	
04-21-2021 01:51:37	Info	Connection	Restart Agent Service	DGAgent2	User attempting to restart disconnected Agent	
04-21-2021 01:00:00	Info	Agent	Scheduled Task Started	DGAgent1	Started Blob Tiering Maintenance on: DGAGENT1	
04-20-2021 23:59:00	Info	Agent	Scheduled Task Started	DGAgent1	Started Nightly Delete Shadow Copies Job on: DGAGENT1	
04-20-2021 23:29:59	Info	Agent	Scheduled Task Started	DGAgent1	Started Blob Tiering Database Maintenance on: DGAGENT1	
04-20-2021 22:37:00	Info	Agent	Scheduled Task Started	DGAgent1	Started Process Retention Policy on: DGAGENT1	
04-20-2021 22:09:59	Info	Agent	Scheduled Task Started	DGAgent1	Started Nightly Purge Destination Job on: DGAGENT1	
04-20-2021 16:02:20	Error	Heartbeat	Disconnect	DGAgent2	Connection status changed from Pending to Disconnected	
04-20-2021 16:02:20	Warning	Heartbeat	Peer Agent on DGAgent2 has disc...	DGAgent2	Peer Agent on DGAgent2 connect status has changed from Connected to Disconnected. PL...	
04-20-2021 16:02:00	Warning	Heartbeat	Missed Heartbeat	DGAgent2	Connection status changed from Connected to Pending	
04-20-2021 14:25:00	Info	Connection	Startup	DGAgent2	Agent Started	
04-20-2021 14:25:00	Info	Heartbeat	Reconnect	DGAgent2	Connection status changed from Disconnected to Connected	

To display the Dashboard, use one of the following methods:

- Select **Show Dashboard** from the **Window** menu.
- Click the **Show Dashboard** icon in the main [Peer Management Center toolbar](#).
- Set the Dashboard to launch automatically at start. See [General Configuration](#).

Job Alerts View

The **Alerts** view is displayed in the lower right quadrant of the Peer Management Center interface and displays various system alerts. The **Job Alerts** view is automatically displayed when a critical job-related (Error or Fatal) alert is received.

There are four categories of alerts, distinguished by the severity of the alert:

- Informational (containing Info, Debug, and Trace information)
- Warning
- Error
- Fatal

An example of an Informational alert is when a job is started or stopped manually by the user. If a job loses one of its participating hosts and as a result, cannot keep a quorum and shuts down, then a Fatal alert will be logged. All alerts are also logged to the file **job_alert.log**, available under the **Hub\logs** subdirectory within the Peer Management Center installation directory.

The screenshot displays the Peer Management Center Client interface. The top section shows the 'Jobs' view with a tree on the left and a table of job details. The bottom section shows the 'Job Alerts' view with a table of alerts and a 'Clear Alerts' link.

Name	Overall Status	Job Type	Failed Hosts	Quarant.	Retries	Errors	Warnings	Open Files	Pending Bytes	Pending Events	Queued Items	Background...	Scan Status	Elapsed Ti...	Session Structure
FC-4	Running	File Collaboration	0	0	0	1	0	0	0 bytes	0	0	0	Completed - 00:01:00	09:18:24	Size: 367.32 MB, ...
FR-4	Stopped	File Replication	0	0	0	0	0	0	0 bytes	0	0	0	Stopped	00:00:00	Size: 0 bytes, File...
FC-2	Running	File Collaboration	0	0	0	3	0	0	0 bytes	0	0	0	Completed - 00:00:27	09:18:24	Size: 345.92 MB, ...
FC-5	Stopped	File Collaboration	0	0	0	0	0	0	0 bytes	0	0	0	Stopped	00:00:00	Size: 0 bytes, File...
FS-1	Halted (Quorum Lost)	File Synchronization	DGAgent1	0	0	1	1	0	0 bytes	0	0	0	Stopped	00:00:00	Size: 0 bytes, File...
FS-3	Stopped	File Synchronization	0	0	0	0	0	0	0 bytes	0	0	0	Stopped	00:00:00	Size: 0 bytes, File...
FC-1	Stopped	File Collaboration	0	0	0	0	0	0	0 bytes	0	0	0	Stopped	00:00:00	Size: 0 bytes, File...
FR-2	Halted (Quorum Lost)	File Replication	DGAgent2	0	0	1	0	0	0 bytes	0	0	0	Stopped	00:00:00	Size: 0 bytes, File...
FS-4	Halted (Quorum Lost)	File Synchronization	DGAgent2	0	0	1	0	0	0 bytes	0	0	0	Stopped	00:00:00	Size: 0 bytes, File...
FS-5	Halted (Quorum Lost)	File Synchronization	DGAgent1	0	0	1	0	0	0 bytes	0	0	0	Stopped	00:00:00	Size: 0 bytes, File...
FR-1	Stopped	File Replication	0	0	0	0	0	0	0 bytes	0	0	0	Stopped	00:00:00	Size: 0 bytes, File...
FS-6	Stopped	File Synchronization	0	0	0	0	0	0	0 bytes	0	0	0	Stopped	00:00:00	Size: 0 bytes, File...
FS-2	Stopped	File Synchronization	0	0	0	0	0	0	0 bytes	0	0	0	Stopped	00:00:00	Size: 0 bytes, File...
FR-3	Stopped	File Replication	0	0	0	0	0	0	0 bytes	0	0	0	Stopped	00:00:00	Size: 0 bytes, File...

Received Date	Severity	Type	Name	Host	Message	Exception
04-21-2021 02:49:01	Error	Configuration	FS-5	DGAgent2,DG...	Disabled auto restart because maximum # (15) of restarts attempts was exceeded for hosts...	
04-21-2021 02:47:59	Error	Start Job	FS-5	DGAgent1	Host Reconnect Startup Error. Operations:Install Watch Directories: ERROR Registering job...	
04-21-2021 02:47:01	Info	Auto Start Job	FS-5	DGAgent1	Auto starting job, DGAgent1 host is now available.	
04-21-2021 02:46:00	Error	Start Job	FS-5	DGAgent1	Host Reconnect Startup Error. Operations:Install Watch Directories: ERROR Registering job...	
04-21-2021 02:45:01	Info	Auto Start Job	FS-5	DGAgent1	Auto starting job, DGAgent1 host is now available.	
04-21-2021 02:44:01	Error	Configuration	FS-1	DGAgent2,DG...	Disabled auto restart because maximum # (15) of restarts attempts was exceeded for hosts...	
04-21-2021 02:44:00	Error	Start Job	FS-5	DGAgent1	Host Reconnect Startup Error. Operations:Install Watch Directories: ERROR Registering job...	
04-21-2021 02:43:01	Info	Auto Start Job	FS-5	DGAgent1	Auto starting job, DGAgent1 host is now available.	
04-21-2021 02:42:56	Error	Start Job	FS-5	DGAgent1	Host Reconnect Startup Error. Operations:Install Watch Directories: ERROR Registering job...	
04-21-2021 02:42:01	Info	Auto Start Job	FS-1	DGAgent1	Auto starting job, DGAgent1 host is now available.	
04-21-2021 02:41:58	Error	Start Job	FS-5	DGAgent1	Host Reconnect Startup Error. Operations:Install Watch Directories: ERROR Registering job...	
04-21-2021 02:41:01	Info	Auto Start Job	FS-5	DGAgent1	Auto starting job, DGAgent1 host is now available.	

You can filter alerts based on host name, job name, severity level, or type, and you can sort alerts by clicking on a specific column header. You can also clear all alerts in the table by clicking the **Clear Alerts** link.

Displaying Job Alerts

You can open the Job Alerts view at any time by clicking the **View Job Alerts** button located on the Peer Management Center toolbar or by selecting the **Window** menu, then the **Show View** submenu, followed by the **View Job Alerts** menu item. You can close the view at any time by clicking on the **X** (Close) button on the Job Alerts tab.

You can resize the Job Alerts view by dragging the separator between the upper view and the Job Alerts view, or you can double-click the **Job Alerts** tab to maximize the view. You can restore the view to its original, non-maximized size by double-clicking the **Job Alerts** tab again.

Jobs View

The **Jobs** view is displayed in the upper left quadrant of the Peer Management Center interface and lists all the jobs, grouped by type. The number in the parentheses following the job type identifies the number of existing jobs of that type. This view is automatically displayed when Peer Management Center is started.

The screenshot displays the Peer Management Center Client interface. The main window shows the 'Jobs' view, which includes a sidebar on the left with a tree view of jobs, a main table of job details, and an Alerts section at the bottom.

Jobs View Table:

Name	Overall Status	Job Type	Failed Hosts	Quaran...	Retries	Errors	Warnings	Open Files	Pending Bytes	Pending Events	Queued Items	Background...	Scan Status	Elapsed Ti...	Session Structure
FC-4	Running	File Collaboration	8	0	0	1	0	0	12 KB	0	0	0	Scanning Directories...	00:44:05	Size: 367.32 MB, ...
FR-4	Stopped	File Replication	0	0	0	0	0	0	0 bytes	0	0	0	Stopped	00:00:00	Size: 0 bytes, File...
FC-2	Running	File Collaboration	0	0	0	0	0	0	0 bytes	0	0	0	Completed - 00:00:41	00:44:23	Size: 345.92 MB, ...
FC-5	Stopped	File Collaboration	0	0	0	0	0	0	0 bytes	0	0	0	Stopped	00:00:00	Size: 0 bytes, File...
FS-1	Contacting participants ...	File Synchronization	0	0	0	0	0	0	0 bytes	0	0	0	Stopped	00:00:04	Size: 0 bytes, File...
FS-3	Stopped	File Synchronization	0	0	0	0	0	0	0 bytes	0	0	0	Stopped	00:00:00	Size: 0 bytes, File...
FC-1	Stopped	File Collaboration	0	0	0	0	0	0	0 bytes	0	0	0	Stopped	00:00:00	Size: 0 bytes, File...
FR-2	Contacting participants ...	File Replication	0	0	0	0	0	0	0 bytes	0	0	0	Stopped	00:00:07	Size: 0 bytes, File...
FS-4	Contacting participants ...	File Synchronization	0	0	0	0	0	0	0 bytes	0	0	0	Stopped	00:00:01	Size: 0 bytes, File...
FS-5	Installing Directory Watchers ...	File Synchronization	0	0	0	0	0	0	0 bytes	0	0	0	Stopped	00:00:20	Size: 0 bytes, File...
FR-1	Stopped	File Replication	0	0	0	0	0	0	0 bytes	0	0	0	Stopped	00:00:00	Size: 0 bytes, File...
FS-6	Stopped	File Synchronization	0	0	0	0	0	0	0 bytes	0	0	0	Stopped	00:00:00	Size: 0 bytes, File...
FS-2	Stopped	File Synchronization	0	0	0	0	0	0	0 bytes	0	0	0	Stopped	00:00:00	Size: 0 bytes, File...
FR-3	Stopped	File Replication	0	0	0	0	0	0	0 bytes	0	0	0	Stopped	00:00:00	Size: 0 bytes, File...

Alerts Section:


Received Date	Severity	Type	Name	Host	Message	Exception
04-20-2021 14:25:00	Info	Connection	Startup	DGAgent2	Agent Started	
04-20-2021 14:25:00	Info	Heartbeat	Reconnect	DGAgent2	Connection status changed from Disconnected to Connected	
04-20-2021 14:24:37	Warning	Connection	Shutdown	DGAgent2	Agent Shutdown	
04-20-2021 13:47:45	Warning	Agent	Connection	DGAgent2	Connection to Broker DGPAC1 was lost for 1 minute 13 seconds	
04-20-2021 13:47:45	Warning	Agent	Connection	DGAgent1	Connection to Broker DGPAC1 was lost for 1 minute 13 seconds	

You can easily display more information about a job or job type by double-clicking a job name or job type name:


- Double-clicking any job name in the list will display a [runtime view](#) of that job.
- Double-clicking any job type name in the list will display a [summary view](#) of that job type.

To filter a large list of jobs, use the **Filter** field located below the [Jobs view toolbar](#). For more details on how to filter jobs, see [List Filters](#).

You can expand all or collapse all jobs by clicking the **View** button in the [Jobs view toolbar](#) and selecting an option from the **View** menu:



The following buttons are available on the toolbar within the **Jobs** view:




Button	Description
Manage, Save and Load Filters	Enables selection of predefined or user-defined filters and to save/manage filters. Default filters include Failed Jobs, Jobs with Backlog, and Running Scans.
Assign Tags	Opens the Assign Tags dialog where resources can be viewed, tagged, and assigned to categories. Tagging resources helps when managing large number of resources.
Start	Starts one or more selected and currently stopped jobs.
Stop	Stops one or more selected and currently running jobs.
Restart	Restart one or more selected jobs.
View	Presents options for displaying views and collapsing and expanding jobs in the Jobs view.

Runtime Views

Each job has a **runtime view** that show a combination of real-time file I/O activity, history, and configuration information. The job name appears as the title of the view. The **runtime** views are displayed in the upper right quadrant of the Peer Management Center interface.

A runtime view typically has several tabs. For example, in the following figure, the Cloud Backup and Replication job **CB-1** is displayed; this view contains six tabs.



The runtime views include:

- [Cloud Backup and Replication job](#)
- [DFS-N Management job](#)
- [File Collaboration job](#)
- [File Replication job](#)
- [File Synchronization job](#)

To monitor a specific Cloud Backup and Replication job, open its runtime view.

Each Cloud Backup and Replication job has a runtime view that show a combination of real-time file I/O activity, history, and configuration. This runtime view has six tabs:

- **Summary** – Displays the status of the job, the number of and size of files uploaded in the last replication, and the size of replicated files.

- **Snapshots** – Displays a log of the snapshots taken since the job was created.
- **Failed Events** – Displays information about events that failed to successfully complete.
- **Event Log** – Displays a log of events that have occurred for the jobs – It displays the last 2500 actions that Cloud Backup and Replication has taken.
- **Alerts** – Displays a log of alerts that were issued for the job.
- **Participants** – Displays Agents that are participants in this Cloud Backup and Replication job (Currently a job can have only one participating agent.)
- **Configuration** – Displays a summary of the job configuration.

The screenshot displays the Peer Management Center Client interface. The main window shows the configuration view for a job. The left pane shows a tree view of jobs and agents. The main area has tabs for Summary, Snapshots, Failed Events, Event Log, Participants, and Configuration. The Configuration tab is selected, showing a summary of the job session (Stopped), workstation stats, and destination stats. Below this is a table with columns for Volume, Job, Management, Storage Device, Storage Type, Destination Type, Destination, Status, Mode, Scan Status, Next Scan, Scan pending, Real-time pen, Retry pending, and VSS pending. The bottom section shows an Alerts tab with a table of 107 errors, 3 warnings, and 107 others, including details like Received Date, Severity, Type, Name, Host, Message, and Exception.


Volume	Job	Management ...	Storage Device	Storage Type	Destination Type	Destinatio...	Status	Mode	Scan Status	Next Scan ...	Scan pending ...	Real-time pen...	Retry pending ...	VSS pending
C:\	CB-1	DGAgent1	DGAgent1	Windows	Nutnix Objects		Stopped							

Received Date	Severity	Type	Name	Host	Message	Exception
04-20-2021 14:45:46	Info	Start Job	FS-5		User Started Peerlet - Restart Action	
04-20-2021 14:45:45	Fatal	Error Running ...	CB-1		Uncaught Exception running job CB-1: java.lang.Exception: Reply not received from DGAg...	java.lang.Exception: Reply not received from DGAg...
04-20-2021 14:45:42	Info	Start Job	FS-4		User Started Peerlet - Restart Action	
04-20-2021 14:45:39	Info	Start Job	FS-1		User Started Peerlet - Restart Action	
04-20-2021 14:45:31	Info	Auto Start Job	FR-2	DGAgent2	Auto starting job, DGAgent2 host is now available.	
04-20-2021 14:45:06	Error	Host Failure	FS-5	DGAgent2	Host Reconnect Startup Error. Operation=StartSession Command : Host Reply Timeout (C...	
04-20-2021 14:45:06	Error	Host Failure	FS-1	DGAgent2	Host Reconnect Startup Error. Operation=StartSession Command : Host Reply Timeout (C...	
04-20-2021 14:45:06	Error	Host Failure	FS-4	DGAgent2	Host Reconnect Startup Error. Operation=StartSession Command : Host Reply Timeout (C...	
04-20-2021 14:44:36	Error	Host Failure	FR-2	DGAgent2	Host Reconnect Startup Error. Operation=StartSession Command : Host Reply Timeout (C...	
04-20-2021 14:44:01	Info	Auto Start Job	FS-1	DGAgent2	Auto starting job, DGAgent2 host is now available.	
04-20-2021 14:44:01	Info	Auto Start Job	FS-5	DGAgent2	Auto starting job, DGAgent2 host is now available.	
04-20-2021 14:44:01	Info	Auto Start Job	FS-4	DGAgent2	Auto starting job, DGAgent2 host is now available.	

To monitor a specific DFS-N Management job, open its runtime view.

Each DFS-N Management job has a runtime view that show a combination of real-time file I/O activity, history, and configuration. This runtime view has four tabs:

- **Namespace** – The top panel of the tab displays the namespace folders in a tree structure. The namespace path is shown at the top of the tree. The bottom panel displays the folder targets linked to the selected namespace folder.
- **Namespace Servers** – Displays a list of the namespace servers and folder targets for the namespace selected in the top panel.
- **Alerts** – Displays a log of alerts that were issued for the job.
- **Configuration** – Displays a summary of the job configuration.



To monitor a specific File Collaboration job, open its runtime view.

Each File Collaboration job has a runtime view that shows a combination of real-time file I/O activity, history, and configuration. This runtime view has eight tabs:

The view contains the following eight tabs:

- [Summary](#) - Displays overall statistics for the selected job.
- [Session](#) - Displays active open files and files that are currently in transit between [participating hosts](#).
- [Event Log](#) - Displays a list of all runtime activity that has occurred within the selected job.


- [Quarantines](#) - Displays a list of all files that are quarantined for the session or are in conflict between two or more participating hosts.
- [Retries](#) - Displays a list of files that are currently in the Retries list.
- [Alerts tab](#) - Displays a list of all job alerts specifically tied to the selected job.
- [Participants tab](#) - Displays a list of all hosts participating in the selected job.
- [Configuration tab](#) - Displays a summary of all configurable options for the selected job.

The screenshot displays the Peer Management Center Client interface. The main window shows the 'Summary' tab for a job. The job status is 'Running', started on 4/20/21 at 2:23 PM, and has elapsed 4 minutes and 17 seconds. The watch set includes 6000 total files and 345.9 MB total bytes, with 60 total folders. Activity statistics show 0 active opens, 0 files pending, 0 bytes pending, and 0 metadata pending. Replication status shows 0 bytes transferred, 0 added, 0 updated, and 0 metadata updates. A timeline graph at the bottom shows the job's progress from 03:00 PM to 02:00 PM. The alerts table at the bottom shows 73 errors, 3 warnings, and 73 others, with a filter by host and severity.

Received Date	Severity	Type	Name	Host	Message	Exception
04-20-2021 14:29:11	Error	Start Job	FS-1	DGAgent1	Host Reconnect Startup Error. Operations Install Watch Directories : ERROR Registering job...	
04-20-2021 14:28:31	Info	Auto Start Job	FS-5	DGAgent1	Auto starting job, DGAgent1 host is now available.	
04-20-2021 14:28:20	Error	Start Job	FS-5	DGAgent1	Host Reconnect Startup Error. Operations Install Watch Directories : ERROR Registering job...	
04-20-2021 14:27:31	Info	Auto Start Job	FR-2	DGAgent1	Auto starting job, DGAgent1 host is now available.	
04-20-2021 14:27:18	Error	Start Job	FR-2	DGAgent1	Host Reconnect Startup Error. Operations Install Watch Directories : ERROR Registering job...	
04-20-2021 14:27:01	Info	Auto Start Job	FS-1	DGAgent1	Auto starting job, host is now available.	
04-20-2021 14:26:59	Info	Start Job	CB-1		User Started Peerlet	
04-20-2021 14:26:24	Error	Start Job	FS-1	DGAgent1	Host Reconnect Startup Error. Operations Install Watch Directories : ERROR Registering job...	
04-20-2021 14:25:38	Info	Start Job	FS-5		User Started Peerlet - Restart Action	
04-20-2021 14:25:35	Info	Start Job	FS-4		User Started Peerlet - Restart Action	
04-20-2021 14:25:32	Info	Start Job	FR-2		User Started Peerlet - Restart Action	
04-20-2021 14:25:28	Info	Start Job	FS-1		User Started Peerlet	

Summary Tab

The **Summary** runtime tab allows you to view current and cumulative file collaboration and synchronization statistics, as well background synchronization status. For performance reasons, this tab is not updated in real-time. However, it can be set to automatically update every few seconds. Select the **Auto-Update** checkbox to enable this functionality; set the refresh interval (in seconds) in the **Refresh** checkbox. Each refresh cycle will update the totals across all active jobs listed at the bottom of the view.



Key statistics in this view are presented in the [Activity](#), [Replication Status](#), and [Background Scan](#) sections. Notice that this tab is scrollable.

Activity

This section presents statistics on pending activity:

- **Files Pending** – Number of files pending synchronization, this includes queued initial scan items, bulk add files, single file adds and real-time modifies. This does not include Deletes, renames or security changes. Move your cursor over the field to see the breakdown from Adds, Updates, and Scan.
- **Bytes Pending** – Matches the Pending Bytes from the [Collab, Sync, and Repl Summary](#) view, which includes all Queued Transfers including scan works, as well as bulk adds. Note this does not track Files Pending exactly but does provide a good indication of the number of bytes currently still needing to be synchronized.
- **Metadata Pending** – Number of pending metadata changes from real-time and from initial and folder scans.
- **Renames Pending** – Total number of files and folders pending rename. Move your cursor over the field to see the breakdown for folders and files.
- **Deletes Pending** – Total number of files and folders pending delete.

Replication Status

This section presents statistics on all completed synchronization from real-time and the initial scan:

- **Bytes Transferred** – Total number of bytes transferred for all real-time Add, Bulk Add, Modify, and Scan synchronization. This does not include bulk delete, security or renames.
- **Added** – Total number of files and folders added in real-time. Move your cursor over the field to see the breakdown for folders and files.
- **Updated** – Total number of files synchronized by initial scan or real-time.
- **Deleted** – Total number of files and folders deleted.
- **Renamed** – Total number of files and folders renamed. Move your cursor over the field to see the breakdown for folders and files.
- **File Metadata Updates** – Total number of real-time and scan metadata updates for folders and files.

Background Scan

This section presents pending and completed synchronization statistics from the initial full scan.

- **Files to Replicate** – Total number of pending files synchronization queued up by initial scan.
- **Bytes to Replicate** – Total number of pending files bytes needing synchronization and queued up by initial scan.
- **Metadata to Replicate** – Total number of file and folder metadata queued up by scan.
- **Files Replicated** – Total number of completed file synchronization from the full initial scan.
- **Bytes Replicated** – Total number of bytes transferred by full initial scan.
- **Metadata Replicated** – Total number of file and folder metadata synchronized by full initial scan.

Session Tab

The **Session** tab allows you to view real-time file collaboration activity and the current session status. You can see which files are currently open in the running session, as well as any file that is currently being synchronized between hosts.

The screenshot shows a web interface for Peer Global File Service. At the top, there are tabs for 'Collab, Sync, and Repl Summary' and 'FC-1'. Below this is a navigation bar with tabs: 'Summary', 'Session', 'Event Log', 'Quarantines (0)', 'Retries (0)', 'Alerts (0)', 'Participants (2)', and 'Configuration'. The 'Session' tab is active. Underneath, it says 'Open Files (0)'. There are controls for 'Session Status: Running', 'Filter by Host', 'Filter by', 'Actions', 'Auto-Update' (checked), and 'Refresh 10 seconds'. A table with the following columns is shown: File Path, Host, Is Source, User Name, Sync. Status, File Size, Last Modified, Date Opened, Message, and Attributes. The table is currently empty. At the bottom left, there is a status indicator: 'Status: Running'.

The **Session** tab has the following components:

Component	Description
Open Files table	<p>A table showing all currently open files on the source host, any internal file locks being held by the running File Collaboration job on the target host(s), and file summary information. This table also shows all file transfers currently in progress along with file summary information, status, and overall progress. Clicking any column headers sorts by that column in ascending or descending order.</p> <p>All items listed in this table are grouped by file path. Each associated lock and/or transfer for each participating host will be available as a hidden child item of a root row. The root row represents the file on the source host. Pressing the + next to the root will show all associated file transfers and/or locks.</p>
Session Status field	<p>Field indicating the current status of the session. Valid values are:</p> <ul style="list-style-type: none"> • Stopped: Session is stopped. • Starting: Session is starting up. • Collaborating: Real-time event detection is enabled.
Filter by Host list	<p>A drop-down list of participating hosts to filter on. Selecting a specific host will filter the open files to show files on that host only.</p>
Filter By Combo list	<p>A drop-down list of additional filters that can be applied to the Open Files table, including filtering by user name (associated with the opening, adding, deleting, or modification of a file) and by file name.</p>
Actions menu	<p>Refresh View: Refreshes the entire Open Files table to show the latest list of file transfers and locks.</p>

Event Log Tab

The **Event Log** tab allows you to view recent file event history for the currently running File Collaboration job based on your Logging and Alerts settings. You can specify the maximum number of events to store in the table by adjusting the Display Events spinner located in the top right corner of the panel. The maximum number of events that can be viewed is 3,000.

If you need to view more events or events from a prior session, then you can use the log files saved in the **Hub\logs** directory located in the installation directory. The event log files will start with **fc_event.log** and are written in a tab-delimited format. Microsoft Excel is a good tool to use to view and analyze a log file.

You can click any column header to sort by the column. For example, clicking the **File** column will sort by file name and you will be able to view all file events for that file in chronological order. Warnings are displayed in light gray, errors are displayed in red, and fatal errors are displayed in orange. Error records will also contain an error message in the **Message** column.


Date	Severity	Type	Host	Is Source	File	Comments	Message	Username	File Size	Modified Time	Remote IP
03-14-2023 04:27:01	INFO	Scan Complete		true			Scan completed for path "\", Scan Type: Full Directory, ...				
03-14-2023 04:26:56	INFO	Scan Start		true			Scan Type: Full Directory				
03-14-2023 04:26:42	INFO	Watch Directory	DGAgent1	true							
03-14-2023 04:26:42	INFO	Watch Directory	DGAgent2	true							
03-14-2023 04:26:29	INFO	Install File Disposer	DGAgent2	true							
03-14-2023 04:26:29	INFO	Install File Disposer	DGAgent1	true							
03-14-2023 04:26:28	INFO	Job Started	DGAgent2	true							
03-14-2023 04:26:28	INFO	Job Started	DGAgent1	true							

The **Actions** menu provides the following options:

Option	Description
Refresh View	Refresh all information provided in the table. This can also be done from the right-click context menu of the table.
Clear Events	Remove all items from the table. This can also be done from the right-click context menu of the table.

Quarantines Tab

The **Quarantines** tab displays a list of files (a) for which file conflicts could not be automatically resolved or (b) retries have failed after the maximum number of attempts. Files in this list will no longer be synchronized or protected with file locks until a winning file is picked through the PeerGFS user interface.




The context menu for the table contains the following actions:

Refresh View	Refresh all information provided in the table.
Purge All Quarantines	Clears all files from the quarantines list.
Copy Details	Copies the quarantine information for the selected file to your clipboard.

Retries Tab

The **Retries** tab displays the files currently in the **Retries** list. Files are put into the retry list if certain errors are thrown when trying to synchronize a file between locations. Synchronization of a file in this list will be retried every minute for a maximum of 60 attempts. The frequency of attempts and the maximum number of attempts are configurable.



The context menu for the table contains the following actions:

Action	Description
Refresh View	Refresh all information provided in the table.
Purge All Quarantines	Clears all files from the Quarantines tab.
Copy Details	Copies the quarantine information for the selected file to your clipboard.

Alerts Tab

The **Alerts** tab allows you to view any alerts relevant to the running File Collaboration job. Items shown here are based on the configured Alerts Severity setting on the Logging and Alerts configuration page. You can specify the maximum number of alerts to store in the table by adjusting the Display Alerts spinner located in the top right corner of the panel. The alerts are also written to a tab delimited file named **fc_alert.log** within the subdirectory 'Hub/logs' within the installation directory of Peer Management Center.

You can click on any column header to sort by that column. For example, clicking on the Severity column will sort by alert severity. Warnings are displayed in light gray, while errors and fatal alerts are displayed in red. In general, you should not see any alerts, but if an error

or fatal alert occurs, it usually means something is wrong with the collaboration session. It may need to be restarted or a configuration setting may need to be changed. You should consult the text in the message field for details on what occurred.

Received Date	Severity	Type	Host	Message
04-20-2021 14:26:20	WARNING	Application	DGAgent1	Recursive reparse point folder detected during scan, excluding folder path=C:\Users\Public\Documents\...
04-20-2021 14:26:20	WARNING	Application	DGAgent1	Recursive reparse point folder detected during scan, excluding folder path=C:\Users\Public\Documents\...
04-20-2021 14:26:20	WARNING	Application	DGAgent1	Recursive reparse point folder detected during scan, excluding folder path=C:\Users\Public\Documents\...
04-20-2021 14:24:41	ERROR	Application	DGAgent2	Agent service on host DGAgent2 was shutdown while job was running.
04-20-2021 13:58:33	WARNING	Application	DGAgent1	Recursive reparse point folder detected during scan, excluding folder path=C:\Users\Public\Documents\...
04-20-2021 13:58:33	WARNING	Application	DGAgent1	Recursive reparse point folder detected during scan, excluding folder path=C:\Users\Public\Documents\...
04-20-2021 13:58:33	WARNING	Application	DGAgent1	Recursive reparse point folder detected during scan, excluding folder path=C:\Users\Public\Documents\...
04-20-2021 13:56:17	WARNING	Application	DGAgent1	Unsupported Host Configuration: 8.3 short file name is enabled for Host DGAgent1
04-20-2021 13:52:37	ERROR	Application	DGAgent2	Host Reconnect Startup Error. Operation=StartSession Command : Host Reply Timeout (Connected)
04-20-2021 13:49:30	ERROR	Application	DGAgent2	Host Reconnect Startup Error. Operation=StartSession Command : Host Reply Timeout (Connected)

The context menu for the table contains the following actions:

Action	Description
Refresh View	Refresh all information provided in the table. This can also be done from the right-click context menu of the table.
Clear Events	Remove all items from the table. This can also be done from the right-click context menu of the table.

Participants Tab

The **Participants** tab is divided into two sections:

- [Host Participants](#)
- [Host Participant State Change Log](#)

Action	Description
	job from automatically restarting. If quorum has not been lost, canceling auto-restart will simply prevent a host from automatically re-joining collaboration.

Host Participant State Change Log

The **Host Participant State Change Log** section contains a table that displays the most recent host participant state changes, e.g., when a host was removed from collaboration session, or when a host came back online.

The **Host Participant State Change Log** is a log of all host participant status changes (e.g., Collaborating, Not Collaborating) and/or state changes (e.g., Active, Pending Restart) of a host participant. This table is limited to 250 rows and can be filtered by host, by status, and by state.

The following options are available in the right-click context menu for this section:

Action	Description
Refresh View	Refresh all information provided in the table.
Clear Events	Remove all items from the table.

Configuration Tab

The **Configuration** tab displays a quick summary of all configurable items for the selected job. Each page of the File Collaboration Configuration edit wizard is represented in its own part of the view and can be collapsed if desired. Clicking **Edit this Configuration** opens the [Edit Job wizard](#), where you can edit the current configuration.

Configuration Summary

[Edit this Configuration](#)

Selected Participants and Configurations

- DGWin16B C:\Installs\PMC (Storage Platform: Windows)
- DGWin16C C:\Installs\PMC (Storage Platform: Windows)

DSU Configuration

- Agent: DGWin16C
- Role: Master
- Agent: DGWin16B
- Role: Edge
- Volume Policy: [DGWin16B - C:](#)
- Utilization Policy: [Default Utilization Policy](#)
- Dynamic Rules: Enabled
- Pinning Filter: None
- Masters: [DGWin16C]

General Settings

- Job Name: FC-3
- Job ID: 185
- Job Type: File Collaboration
- Transfer Block Size: 2048 KB
- Verify Checksum: true
- Use Multipart Transfers: false
- Global Real-Time Expedited Threads: 20
- Global Real-Time Background Threads: 20
- Synchronization Priority: 2
- Timeout: 180 Seconds
- Scan Delay: 10
- Remove Filtered Files On Folder Delete: true
- Require All Hosts At Start: false
- Auto Start: true

Locking

- Allow Write Access During Synchronization: true
- Exclusive Target Lock: false
- Include MS Office User Lock Information: true
- Include AutoCAD User Lock Information: false
- Source Snapshot Synchronization: false
- Source Vss Snapshot Synchronization: false
- Snapshot File Extensions: mdb,accdb,zip,psd,ai,indd
- Max File Size (MB): 512
- Sync. On Save Extensions:
- Sync. On Save Delay: 20

Conflict Resolution

- Latest Modified Time (Truncate Milliseconds=true)
- Quarantine Multi-edit Conflicts: true
- Offline Folder Rename Detection Detection: false
- Offline Delete Detection During Scan: true
- Delete Detection Master Host: none

Delta Replication Settings

- Enable Block/Byte Synchronization: true
- Disable on Session Startup: false
- Checksum Transfer Size: 256 KB
- Delta Block Transfer Size: 1024 KB
- Minimum File Size: 2048 KB
- Minimum File Size Percentage Target/Source: 0.3
- Excluded File Extensions:
- Excluded File Name Patterns: None

File Metadata Settings

- Enable attribute synchronization in real-time: false
- Enable attribute synchronization with master host during initial scan: false

Status: Stopped

To monitor a specific File Replication job, open its runtime view.

Each File Replication job has a runtime view that show a combination of real-time file I/O activity, history, and configuration. This runtime view has six tabs:

- Summary
- Session
- Event Log
- Quarantines
- Retries
- Alerts
- Participants

- Configuration

The screenshot displays the Peer Management Center Client interface. The main window shows the configuration for a File Synchronization job, which is currently stopped. The configuration includes details for the Job Status (Stopped), Watch Set (0 files, 0 bytes), Activity (0 active opens, 0 files pending, 0 bytes pending, 0 metadata pending), and Replication Status (0 bytes transferred, 0 added, 0 updated, 0 metadata updates). A graph below the configuration shows the Priority Queue, Replication Queue, and Active Opens over time. The Alerts section shows 111 errors and 3 warnings, with a table of alerts including Received Date, Severity, Type, Name, Host, Message, and Exception.

Received Date	Severity	Type	Name	Host	Message	Exception
04-20-2021 14:47:25	Info	Start Job	FS-1		User Started Peetlet - Restart Action	
04-20-2021 14:47:07	Info	Stop Job	FS-1		User Stopped Peetlet - Restart Action	
04-20-2021 14:47:02	Info	Auto-Start Job	FS-1	DGAgent2	Auto-starting job, DGAgent2 host is now available.	
04-20-2021 14:47:01	Info	Start Job	FS-1		User Started Peetlet - Restart Action	
04-20-2021 14:46:58	Info	Start Job	FS-4		User Started Peetlet - Restart Action	
04-20-2021 14:46:54	Info	Start Job	FR-2		User Started Peetlet - Restart Action	
04-20-2021 14:46:50	Error	Host Failure	FS-5	DGAgent2	Host Reconnect Startup Error. Operations StartSession Command : Host Reply Timeout (C...	
04-20-2021 14:46:47	Error	Host Failure	FS-4	DGAgent2	Host Reconnect Startup Error. Operations StartSession Command : Host Reply Timeout (C...	
04-20-2021 14:46:44	Error	Host Failure	FS-1	DGAgent2	Host Reconnect Startup Error. Operations StartSession Command : Host Reply Timeout (C...	
04-20-2021 14:46:36	Error	Host Failure	FR-2	DGAgent2	Host Reconnect Startup Error. Operations StartSession Command : Host Reply Timeout (C...	
04-20-2021 14:45:46	Info	Start Job	FS-5		User Started Peetlet - Restart Action	
04-20-2021 14:45:45	Fatal	Error Running	CB-1		Uncaught Exception running job CB-1: java.lang.Exception: Reply not received from DGAg...	java.lang.Exception: Reply not received from DGAg...

To monitor a specific File Synchronization job, open its runtime view.

Each File Synchronization job has a runtime view that show a combination of real-time file I/O activity, history, and configuration. This runtime view has six tabs:

- Summary
- Session
- Event Log
- Quarantines
- Retries
- Alerts
- Participants

- Configuration

The screenshot displays the Peer Management Center Client interface. The main window shows a summary view for File Replication jobs. The interface includes a navigation tree on the left, a main summary view with tabs for Summary, Session, Event Log, Quarantines, Retries, Alerts, Participants, and Configuration. The Summary View shows job status as 'Stopped', watch set statistics, activity metrics, and replication status. A timeline graph at the bottom shows Priority Queue, Replication Queue, and Active Opens. An Alerts section at the bottom displays a table of 118 errors, 3 warnings, and 120 others.

Received Date	Severity	Type	Name	Host	Message	Exception
04-20-2021 14:50:11	Info	Start Job	FS-5	DGAgent2	User Started Peerlet - Restart Action	
04-20-2021 14:50:06	Error	Host Failure	FS-5	DGAgent2	Host Reconnect Startup Error. Operations-StartSession Command : Host Reply Timeout (C...	
04-20-2021 14:50:05	Info	Start Job	FS-1	DGAgent2	User Started Peerlet - Restart Action	
04-20-2021 14:50:02	Info	Start Job	FS-4	DGAgent2	User Started Peerlet - Restart Action	
04-20-2021 14:49:58	Info	Start Job	FR-2	DGAgent2	User Started Peerlet - Restart Action	
04-20-2021 14:49:36	Error	Host Failure	FS-4	DGAgent2	Host Reconnect Startup Error. Operations-StartSession Command : Host Reply Timeout (C...	
04-20-2021 14:49:06	Error	Host Failure	FR-2	DGAgent2	Host Reconnect Startup Error. Operations-StartSession Command : Host Reply Timeout (C...	
04-20-2021 14:49:02	Info	Auto Start Job	FS-5	DGAgent2	Auto starting job. DGAgent2 host is now available.	
04-20-2021 14:48:32	Info	Auto Start Job	FS-4	DGAgent2	Auto starting job. DGAgent2 host is now available.	
04-20-2021 14:48:29	Error	Host Failure	FS-1	DGAgent2	Host Reconnect Startup Error. Operations-StartSession Command : Host Reply Timeout (C...	
04-20-2021 14:48:06	Error	Host Failure	FS-5	DGAgent2	Host Reconnect Startup Error. Operations-StartSession Command : Host Reply Timeout (C...	
04-20-2021 14:48:02	Error	Host Failure	FS-4	DGAgent2	Host Reconnect Startup Error. Operations-StartSession Command : Host Reply Timeout (C...	

Summary Views

You can use the summary views to monitor the overall health of your jobs and Agents. You can [set summary views to be automatically displayed](#) when Peer Management Center is started. The **summary** views are displayed in the upper right quadrant of the Peer Management Center interface.

A summary view typically has several tabs. For example, in the following figure, the summary view for File Collaboration, File Synchronization, and File Replication jobs is displayed; this view contains three tabs.

The screenshot displays the Peer Management Center Client interface. The main window is titled "Peer Management Center Client" and contains several panes. The left pane shows a tree view of the environment, including "Cloud Backup and Replication (0)", "DFS-N Management (4)", "File Collaboration (3)", "File Replication (0)", and "File Synchronization (1)". The right pane is divided into two sections: "Runtime Summary (auto-update enabled)" and "Alerts".

The "Runtime Summary" section displays a table of jobs with the following columns: Name, Overall Status, Job Type, Failed Hosts, Quara..., Retries, Errors, Warnin..., Open Files, Pending B..., Queued It..., Background S..., Scan St..., Elapsed T..., Session Structure, and Synchr. The table contains three rows of data:

Name	Overall Status	Job Type	Failed Hosts	Quara...	Retries	Errors	Warnin...	Open Files	Pending B...	Queued It...	Background S...	Scan St...	Elapsed T...	Session Structure	Synchr
Development Projects	Running	File Collaboration	0	0	0	2	0	0	0 bytes	0	0	Compl...	00:12:25	Size: 0 bytes, File...	2
FC-1	Running	File Collaboration	0	0	0	2	0	0	0 bytes	0	0	Compl...	00:12:32	Size: 198.29 KB, F...	2
FC-2	Stopped	File Collaboration	0	0	0	0	0	0	0 bytes	0	0	Stopped	00:00:00	Size: 0 bytes, File...	2


The "Alerts" section shows a summary of 16 errors, 5 warnings, and 6 others. Below this, a table lists individual alerts with columns: Received Date, Severity, Type, Name, Host, Message, and Exception. The alerts include configuration warnings for unsupported host configurations and information about start jobs.

The summary views include:

- [Agent Summary](#) - Displays summary information about the Agents.
- [Cloud Summary](#) - Displays summary information about running Cloud Backup and Replication jobs.
- [Collab, Sync, and Repl Summary](#) - Displays summary information about running File Collaboration, File Synchronization, and File Replication jobs
- [Namespace Summary view](#) - Displays summary information about namespaces and DFS-N Management jobs.

The **Agent Summary** view displays a list of all known Agents deployed and their detailed status information, which can be used to assess the health of the environment. This summary view has a single tab.

The **Agent Summary** view is updated in real-time and can be filtered by using an expression or by built-in categories such as **Connected**, **Disconnected**, and **Needing Upgrade**.



To display the Agent Summary view, use one of the following methods:

- Select **Show Agent Summary** from the **Window** menu.
- Click the **Show Agent Summary** icon in the main [PMC toolbar](#) or in the [Agents view toolbar](#).

Use the **Cloud Summary** view to monitor the overall health of your Cloud Backup and Replication jobs. This view is the first place to check to see the status of your Cloud Backup and Replication jobs.

This view can be [set to be automatically displayed](#) when Peer Management Center is started and can be opened at any other time by double-clicking the job type name **Cloud Backup and Replication** in the [Jobs view](#) or by selecting **View Cloud Summary** from the toolbar in the **Jobs** view.

This view has four tabs:

- **Volume Summary** – Displays the volumes associated with jobs. The color of the icon next to a volume name quickly indicates the status of the job associated with that volume—a green icon indicates an active job; a gray icon indicates an inactive job, and a red icon indicates a problem with a job.

- **Job Summary** – Displays the status of all Cloud Backup and Replication jobs.
- **Destination Statistics** – Displays the total number of files that have been replicated since the first run of the jobs and other statistics.
- **Tasks** – Displays a high-level view of activities such as snapshots, and recovery processes, and background events for all Cloud Backup and Replication jobs.

The screenshot shows the Peer Management Center Client interface. The main window is titled 'Collab, Sync, and Repl Summary' and displays a table with the following columns: Volume, Job, Management, Storage Device, Storage Type, Destination Type, Destination, Status, Mode, Scan Status, Next Scan, Scan pending, Real-time pen., Retry pending, and VSS pending. The table contains one row of data: Volume C:\, Job CB-2, Management DGAgent1, Storage Device SVM6X-1, Storage Type Windows, Destination Type Nutanix Objects, Destination Amazon S3, and Status Stopped.

Below the table is an 'Alerts' section with a filter by Host and a list of alerts. The alerts table has columns for Received Date, Severity, Type, Name, Host, Message, and Exception. The alerts include:

Received Date	Severity	Type	Name	Host	Message	Exception
04-20-2021 14:45:06	Error	Host Failure	FS-5	DGAgent2	Host Reconnect Startup Error. Operations-StartSession Command: Host Reply Timeout (C...	
04-20-2021 14:45:06	Error	Host Failure	FS-1	DGAgent2	Host Reconnect Startup Error. Operations-StartSession Command: Host Reply Timeout (C...	
04-20-2021 14:45:06	Error	Host Failure	FS-4	DGAgent2	Host Reconnect Startup Error. Operations-StartSession Command: Host Reply Timeout (C...	
04-20-2021 14:44:36	Error	Host Failure	FR-2	DGAgent2	Host Reconnect Startup Error. Operations-StartSession Command: Host Reply Timeout (C...	
04-20-2021 14:44:01	Info	Auto Start Job	FS-1	DGAgent2	Auto starting job, DGAgent2 host is now available.	
04-20-2021 14:44:01	Info	Auto Start Job	FS-5	DGAgent2	Auto starting job, DGAgent2 host is now available.	
04-20-2021 14:44:01	Info	Auto Start Job	FS-4	DGAgent2	Auto starting job, DGAgent2 host is now available.	
04-20-2021 14:43:31	Info	Auto Start Job	FR-2	DGAgent2	Auto starting job, DGAgent2 host is now available.	
04-20-2021 14:43:28	Error	Host Failure	FR-2	DGAgent2	Host Reconnect Startup Error. Operations-StartSession Command: Host Reply Timeout (C...	
04-20-2021 14:43:25	Error	Host Failure	FS-5	DGAgent2	Host Reconnect Startup Error. Operations-StartSession Command: Host Reply Timeout (C...	
04-20-2021 14:43:22	Error	Host Failure	FS-1	DGAgent2	Host Reconnect Startup Error. Operations-StartSession Command: Host Reply Timeout (C...	
04-20-2021 14:43:06	Error	Host Failure	FS-4	DGAgent2	Host Reconnect Startup Error. Operations-StartSession Command: Host Reply Timeout (C...	

Use the **Collab, Sync, and Repl Summary** view to monitor the overall health of your File Collaboration, File Replication, and File Synchronization jobs. This view is the first place to check to see the status of your File these job types.

This view can be [set to be automatically displayed](#) when Peer Management Center is started and can be opened at any other time by double-clicking one of the job type names (**File Collaboration**, **File Replication**, or **File Synchronization**) in the [Jobs view](#) or by selecting **View Collab, Sync, and Repl Summary** from the **Jobs** view toolbar.

This view has three tabs:

- [Summary](#)

- [Dynamic Storage Utilization](#)
- [Reports](#)

Peer Management Center Client

File Window Help

Jobs

type filter text

- Cloud Backup and Replication (0)
- DFS-N Management (3)
 - \\PeerTest.local\DG
 - \\PeerTest.local\Documentation
 - User Guides
 - \\PeerTest.local\Technical Support
 - QA
- File Collaboration (2)
 - FC-1
 - FC-2
- File Replication (0)
- File Synchronization (0)

Agents

type filter text

Agent	Version	OS
DGWin16A (Connected)	5.0.0.20220504	Windows Serve
DGWin16B (Connected)	5.0.0.20220504	Windows Serve
DGWin16C (Connected)	5.0.0.20220504	Windows Serve
DGWin16D (Connected)	5.0.0.20220504	Windows Serve

Summary Dynamic Storage Utilization Reports

Runtime Summary (auto-update disabled)

Filter by: Expression Actions Auto-Update Refresh 10 seconds

Name	Overall Status	Job Type	Failed H.	Quar.	Retries	Errors	Warnin...	Open Files	Pending B.	Queued It.	Background S.	Scan St.	Elapsed T.	Session Structure	Synchronization P
FC-1	Stopped	File Collaborat...	0	0	0	0	0	0	0 bytes	0	0	Stopped	00:00:00	Size: 0 bytes, File...	2
FC-2	Stopped	File Collaborat...	0	0	0	0	0	0	0 bytes	0	0	Stopped	00:00:00	Size: 0 bytes, File...	2

Active Jobs -> Failed Participants: 0 of 0 | Bytes Pending: 0 bytes | Bytes Transferred: 0 bytes | Opens: 0 | Initial Scans Completed: 0 of 0 | Total Size: 0 bytes | Total Files: 0 | Total Directories: 0

Alerts Job Alerts

0 errors, 8 warnings, 17 others Filter by: Host: Severity: Type: Clear Alerts

Summary Tab

The **Summary** tab aggregates critical status and statistical information from all File Collaboration, File Synchronization, and File Replication jobs in a single table. It presents overall job status, basic pending, and bytes transferred statistics. See the [Reports tab](#) for more detailed pending activity information.

Information in this view can be sorted and filtered. Operations such as starting, stopping, and editing multiple job at once are available, in addition to the ability to clear [job alerts](#) and purge [quarantines](#) from stopped jobs. Scroll the view horizontally to see all of its columns.

For performance reasons, this tab is not updated in real-time. However, it can be set to automatically update every few seconds. Select the **Auto-Update** checkbox to enable this functionality; set the refresh interval (in seconds) in the **Refresh** spinner. Each refresh cycle will update the details across all jobs, as well as the active jobs totals listed at the bottom of the view.

Actions Menu

The **Actions** menu provides the following options:

Option	Description
Filters	Allows you to select predefined or user-defined filters and to save/manage list filters . Default job filters include Failed Jobs, Jobs with Backlog, and Running Scans.
Scheduler	Opens the Task Scheduler.
Custom Sort...	Enables you to define multi-level sort criteria for the table. This is useful for keeping important items visible at the top. For example, you may choose to create a sort level where the Overall Status column is sorted in ascending order by default.
Refresh View	Refreshes all information displayed in the table.
Copy All Filtered Statistics	Copies detailed information to the system clipboard for all items current displayed in the table, taking any filters into account. This information can then be pasted into a text editor.
Export Table Data to File	Dumps the entire contents of the table to a text file that can be viewed in any text editor.

Dynamic Storage Utilization tab

The **Dynamic Storage Utilization** tab presents about jobs using Dynamic Storage Utilization in a single table.

The screenshot shows the Peer Management Center Client interface. The main window is titled "Collab, Sync, and Repl Summa..." and has tabs for Summary, Dynamic Storage Utilization, and Reports. The Reports tab is active, displaying a table with the following data:

Agent/Volumes	Last Update	Temporary Storage Path	Edge Service Status	Volume Utilization (Total/Free)	Cache Utilization (Total/Free)	Local Files	Pinned Local Files	Stubbed Files	Pinned Stubbed Files	Scan Status
DGWin168	05-31-2022 09:58...	C:\Users\PeerTempPath	Unknown	59.45 GB / 44.82 GB	44.58 GB / 34.46 GB	114110 (10.1...)	0 (0 bytes)	0 (0 bytes)	0 (0 bytes)	Scan Co
DGWin16C	N/A	C:\PeerTempPath	Unknown	N/A	N/A	N/A	N/A	N/A	N/A	Not Sca

Below the table, the "Job Details (DGWin168 - C:\)" section shows:

Job	Status	Items In Cache	Stubbed Files	Pinned Local Files
FC-3	Stopped	1 (62.1 MB)	0 (0 bytes)	0 (0 bytes)

The "Alerts" section at the bottom shows a list of events:

Received Date	Severity	Type	Name	Host	Message	Exception
06-02-2022 04:51:51	Info	Connection	Startup	DGWin16A	Agent Started	
06-02-2022 04:51:45	Info	Heartbeat	Reconnect	DGWin16A	Connection status changed from Disconnected to Connected	
06-02-2022 04:51:26	Info	Connection	Startup	DGWin16B	Agent Started	
06-02-2022 04:51:18	Info	Connection	Startup	DGWin16C	Agent Started	
06-02-2022 04:51:18	Info	Heartbeat	Reconnect	DGWin16C	Connection status changed from Disconnected to Connected	
06-02-2022 04:51:11	Info	Connection	Startup	DGWin16D	Agent Started	

Reports Tab

The **Reports** tab presents critical statistical information from all File Collaboration, File Synchronization, and File Replication jobs in a single table. The **Reports** tab is visible when the **Enable Advanced Reporting Tab** option on the [Collab, Sync, and Repl Summary](#) page in [Preferences](#) is selected.

The **Reports** tab is especially useful to view the number of files that are in the queue waiting to be synchronized (shown in the **File Sync Queue** column). Scroll the view horizontally to see all of its columns.

For performance reasons, this tab is not updated in real-time. However, it can be set to automatically update every few seconds. Select the **Auto-Update** checkbox to enable this functionality; set the refresh interval (in seconds) in the **Refresh** checkbox. Each refresh cycle will update the totals across all active jobs listed at the bottom of the view.

The screenshot shows the Peer Management Center Client interface. The main window displays a table of pending activity for various jobs. The table has the following columns: Name, File Sync Queue, Real-Time Queue, Queued Bytes, Mods, Adds, Metadata, Scan Queue, Deletes, Renames, Event Queue, and Scheduled Replication. The table is filtered by 'Expression'. Below the table, there is an Alerts section with a table of recent events. The Alerts table has columns: Received Date, Severity, Type, Name, Host, Message, and Exception.

Name	File Sync Queue	Real-Time Queue	Queued Bytes	Mods	Adds	Metadata	Scan Queue	Deletes	Renames	Event Queue	Scheduled Replication
FS-1	0	0	0 bytes	0	0	0	0	0	0	0	0
FC-4	0	0	0 bytes	0	0	0	0	0	0	0	0
Development Projects	0	0	0 bytes	0	0	0	0	0	0	0	0
FR-1	0	0	0 bytes	0	0	0	0	0	0	0	0
FC-1	0	0	0 bytes	0	0	0	0	0	0	0	0
FC-3	0	0	0 bytes	0	0	0	0	0	0	0	0
FC-2	0	0	0 bytes	0	0	0	0	0	0	0	0

Received Date	Severity	Type	Name	Host	Message	Exception
06-02-2022 04:51:51	Info	Connection	Startup	DGWin16A	Agent Started	
06-02-2022 04:51:45	Info	Heartbeat	Reconnect	DGWin16A	Connection status changed from Disconnected to Connected	
06-02-2022 04:51:26	Info	Connection	Startup	DGWin16B	Agent Started	
06-02-2022 04:51:18	Info	Connection	Startup	DGWin16C	Agent Started	
06-02-2022 04:51:18	Info	Heartbeat	Reconnect	DGWin16C	Connection status changed from Disconnected to Connected	
06-02-2022 04:51:11	Info	Connection	Startup	DGWin16D	Agent Started	

Items in the table can be filtered by a [filter expression](#), job name, [Participant](#), Session Status, or by [tags](#). Select the desired filter or enter your own expression in the text field to the right of the **Filter** drop-down list. Check the **Auto-Hide** button to hide all jobs which have no pending activity.

Column Descriptions

Column	Description
Name	The name of the job.
File Sync Queue	The number of files that are in queue waiting to be processed. The number of threads available for this queue is set by the Real-Time Background Threads field in the Performance preferences for Collaboration, Synchronization, and Replication jobs.
Real-Time Queue	The number of open/close events that are in queue waiting to be processed. The number of threads available to process this queue is set by the Real-Time Expedited Threads field in the Performance preferences for Collaboration, Synchronization, and Replication jobs.
Queued Bytes	The number of bytes that are in queue waiting to be processed.

Column	Description
Mods	The number of file update events waiting to be processed for each job.
Adds	The number of file add events waiting to be processed for each job.
Metadata	The number of metadata updates waiting to be processed for each job.
Deletes	The number of files deleted on a source host that are waiting to be processed.
Renames	The number of files renamed on a source host that are waiting to be processed.
Event Queue	The number of events that are queued up to run for each job.
Slow Expedited Queue	The number of events that are queued in the Slow Expedited Queue for each job.
Fast Expedited Queue	The number of events that are queued in the Fast Expedited Queue for each job.
Scheduled Replication Pending	The number of events that are queued awaiting replication at a scheduled time or interval.
Scheduled Replication Processing	The number of events that are queued awaiting a validation scan to make sure that the source version is correct before being released for replication.
Scheduled Replication Transfers	The number of events that are queued awaiting an available replication slot.

Actions Menu

The **Actions** menu provides the following options:

Option	Description
Filters	Allows you to select predefined or user-defined filters and to save/manage list filters . Default job filters include Failed Jobs, Jobs with Backlog, and Running Scans.
Scheduler	Opens the Task Scheduler.
Custom Sort...	Enables you to define multi-level sort criteria for the table. This is useful for keeping important items visible at the top. For example, you may choose to create a sort level where the Overall Status column is sorted in ascending order by default.
Refresh View	Refreshes all information displayed in the table.
Copy All Filtered Statistics	Copies detailed information to the system clipboard for all items current displayed in the table, taking any filters into account. This information can then be pasted into a text editor.
Export Table Data to File	Dumps the entire contents of the table to a file that can be viewed in any text editor.
Move Totals Row To Top	Moves the Totals row to the top of the table.
Move Totals Row To Bottom	Moves the Totals row to the bottom of the table.

Use the **Namespace** view to monitor the overall health of your DFS-N Management jobs and namespaces. This view is the first place to check to see the status of your DFS-N Management jobs. This view has a single tab.

This view can be [set to be automatically displayed](#) when Peer Management Center is started and can be opened at any other time by double-clicking the **DFS-N Management** job type name in the [Jobs view](#) or by selecting **View Namespace Summary** from the toolbar in the **Jobs** view.


The **Management Status** column shows the status of the DFS-N Management job. The **State** column shows the state of the namespace, which can be **Online**, **Offline**, **Unknown**, and **Not Found**. **Unknown** is not a common state--it typically reflects when an unexpected error has occurred or during initialization.

Namespace Path/Folders	Management Status	State	Errors	Servers	Total Folders/Targets
\\PeerTest.local\Documentation	Monitoring	Online	0	peertestdc1, peertestdc2	1
User Guides					3
\\PeerTest.local\DG	Monitoring	Online	0	peertestdc2, peertestdc1	1
DGNFS					2
\\PeerTest.local\Technical Support	Monitoring	Online	0	peertestdc1	1
QA					0

Main Window Menus and Toolbar

The main window of Peer Management Center has three menus and a toolbar:

- [File](#)
- [Window](#)
- [Help](#)



File Menu

The **File** menu in the Peer Management Center main window has the following commands:

Command	Description
New Job	Starts the Create New Job wizard.
Close	Closes the selected view.
Close All	Closes all views.
Exit	(Rich client only) Closes the Peer Management Center Client. Note that as long as the Peer Management Center Service remains running, all running jobs will continue to operate.

Command	Description
Logout	(Web client only) Logs the user out of the Peer Management Center Web client.

Help Menu

The **Help** menu in the Peer Management Center main window has the following commands:

Command	Description
User Guide	Opens the User Guide.
Support Portal	Opens the Support Portal on the Peer Software website.
Download Peer Agent Installer	Opens the Peer Software website where you can download the Peer Agent installer compatible with this version of Peer Management Center.
Download Broker Installer	Opens the Peer Software website where you can download the Broker installer compatible with this version of Peer Management Center.
Peer Management Center Web Client	Opens the Peer Management Center Web Client in a web browser.
Peer Management Center API	Opens the Peer Global File Service API in a web browser.
Analytics	Opens the Analytics page in Preferences, which allows you to modify Analytics and Proactive Monitoring settings.

Command	Description
Run Event Detection Analytics	Runs event detection analytics immediately. PeerGFS can perform event detection analysis every night; however, this option allows you to receive the most up-to-date analytics.
Retrieve PMC/Agent Logs	Collects and retrieve all useful log files for specified Peer Agents, Peer Management Center, and all jobs. This information is assembled into a single encrypted zip file that can optionally be uploaded to the Peer Software Technical Support. The collection and retrieval of the log and support files is performed in the background, which might take a while, depending on content size and network speed. Upon completion, you are notified and can view the zip file.
Retrieve Broker Statistics	Displays detailed statistical information about all messaging that has transpired for all connections (Peer Agents and Peer Management Center) to Peer Management Broker . Peer Technical Support can use these statistics to aid in diagnosing problems.
Generate Thread Dump File	Gives options to generate a thread dump of the running Peer Management Center Client and Service, as well as the running Peer Management Broker service. Both can be used by Peer Software technical support to debug certain issues.
Generate PMC Memory Dump File	Generates a memory dump of the running Peer Management Center Client and Service, which can be used by Peer Software Technical Support to debug certain issues.
Compress DB on Restart	(Rich client only) Compresses the database upon restart of the Peer Management Center Service. Select this option in cases where the database consumes a large amount of disk space.
Check for Updates	(Rich client only) Checks for updates to Peer Management Center. Minor releases can be automatically downloaded and installed. Major releases require a new license key and must be requested from Peer Software Technical Support.
Licenses	Displays the Licensing page in Preferences .
About Peer Management	Displays version information and installation details.

Command	Description
Center	

Window Menu


The **Window** menu in the Peer Management Center main window has the following commands:

Command	Description
Reset Perspective	Resets all current windows, views, and editors to their default size and layout.
Show Dashboard	Displays the Dashboard, which displays metrics and key performance indicators from all running File Collaboration, File Replication, and File Synchronization jobs, and Peer Agents.
Show Agent Summary	Displays the Agent Summary view, which displays a list of all known Peer Agents deployed and their detailed status information, which can be used to assess the health of the environment.
Show Summary View	Displays a submenu with the following options: <ul style="list-style-type: none"> • Cloud Summary - Displays the summary view for Cloud Back and Replication jobs. • Namespace Summary - Displays the summary view for DFS-N Management jobs. • Collab, Sync, and Repl Summary - Displays the summary view for File Collaboration, File Replication, and File Synchronization jobs.
Show View	Displays a submenu with the following options: <ul style="list-style-type: none"> • Alerts - Displays the Alerts view, which displays Peer Management Center alerts such as Peer Agent connection status changes.

Command	Description
	<ul style="list-style-type: none"> • Job Alerts - Displays the Job Alerts view, which displays alerts such as job restarts. • Task History - Displays the Task History view, which displays the status of tasks such as Daily Cleanup. • Progress - Displays the Progress view, which displays information pertaining to any running background tasks within Peer Management Center.
Preferences	Displays the Preferences page, which enables the user to configure global settings for Peer Management Center, as well as settings for individual job types.
Assign Tags	Displays the Assign Tags dialog where resources can be viewed, tagged, and assigned to categories. Tagging resources helps when managing large number of resources.
Refresh	Refreshes all open views and tabs.

Toolbar

Use the toolbar in the main Peer Management Center window to quickly launch commonly performed actions.



The toolbar has the following buttons:

Button	Description
New Job	Opens the New Job wizard.
Preferences	Displays the Preferences page, which enables the user to configure global settings for Peer Management Center, as well as settings for individual job types.
View Dashboard	Displays the Dashboard, which displays metrics and key performance indicators from all running File Collaboration, File Replication, and File Synchronization jobs, and Peer Agents.
Show Agent Summary	Displays the Agent Summary view, which displays a list of all known Peer Agents deployed and their detailed status information, which can be used to assess the health of the environment.
Task Scheduler	Opens the Task Scheduler, which enables a user to schedule tasks that can be carried out by the Peer Management Center at scheduled times or intervals.
Assign Tags	Displays the Assign Tags dialog where resources can be viewed, tagged, and assigned to categories. Tagging resources helps when managing large number of resources.
View Alerts	Displays the Alerts view , which displays Peer Management Center alerts such as Peer Agent connection status changes.
View Job Alerts	Displays the Job Alerts view , which displays job-related alerts such as job restarts.
View Task History	Displays the Task History view, which displays the status of tasks such as Daily Cleanup.
Refresh	Refreshes all current views and tabs.

Tables

Tables are used throughout the Peer Management Center interface to present information. For example, the Job Alerts view contains a table displaying job-specific alerts:

Received Date	Severity	Type	Name	Host	Message
04-16-2021 15:37:23	Error	Configuration	FS-5	DGAgent2,DGAgent1	Disabled auto restart because maximum # (15) of restarts attempts was exceeded for host(s) DGAgent2,DGAgent1
04-16-2021 15:36:27	Error	Host Failure	FS-5	DGAgent2	Host Reconnect Startup Error. Operation=StartSession Command : Host Reply Timeout (Connected)
04-16-2021 15:36:23	Error	Configuration	FS-1	DGAgent2,DGAgent1	Disabled auto restart because maximum # (15) of restarts attempts was exceeded for host(s) DGAgent2,DGAgent1
04-16-2021 15:35:27	Error	Host Failure	FS-1	DGAgent2	Host Reconnect Startup Error. Operation=StartSession Command : Host Reply Timeout (Connected)
04-16-2021 15:35:23	Info	Auto Start Job	FS-5	DGAgent2	Auto starting job, DGAgent2 host is now available.
04-16-2021 15:34:27	Error	Host Failure	FS-5	DGAgent2	Host Reconnect Startup Error. Operation=StartSession Command : Host Reply Timeout (Connected)
04-16-2021 15:34:23	Info	Auto Start Job	FS-1	DGAgent2	Auto starting job, DGAgent2 host is now available.
04-16-2021 15:33:47	Error	Host Failure	FS-1	DGAgent2	Host Reconnect Startup Error. Operation=StartSession Command : Host Reply Timeout (Connected)
04-16-2021 15:33:23	Info	Auto Start Job	FS-5	DGAgent2	Auto starting job, DGAgent2 host is now available.
04-16-2021 15:32:53	Error	Configuration	FS-4	DGAgent2	Disabled auto restart because maximum # (15) of restarts attempts was exceeded for host(s) DGAgent2
04-16-2021 15:32:47	Error	Host Failure	FS-5	DGAgent2	Host Reconnect Startup Error. Operation=StartSession Command : Host Reply Timeout (Connected)
04-16-2021 15:32:23	Info	Auto Start Job	FS-1	DGAgent2	Auto starting job, DGAgent2 host is now available.
04-16-2021 15:32:17	Error	Host Failure	FS-4	DGAgent2	Host Reconnect Startup Error. Operation=StartSession Command : Host Reply Timeout (Connected)

Most tables allow you to sort them by clicking on a column header.

Most tables support double-clicking on any row to display a dialog containing details pertaining to that row. For example, clicking a row in the Job Alerts table displays detailed information for that particular alert:

Received at	04-16-2021 15:36:27
Severity	Error
Category	Host Failure
Host Name	DGAgent2
Locally Generated at	04-16-2021 15:36:27
Name	FS-5
Message	Host Reconnect Startup Error. Operation=StartSession Command : Host Reply Timeout (Connected)
Ref ID	243

Click outside of popup to close

Right-clicking in a table displays a **context menu**. A context menu allows you to perform additional operations on the table. For example, you can choose which columns to hide and to display in the table. One very useful option available in many context menus is the ability to copy detailed information for one or more rows all at the same time. This information can then be pasted into any text editor.

Received Date	Severity	Type	Name	Host	Message
04-16-2021 15:33			FS-5	DGAgent2,DGAgent1	Disabled auto restart because maximum # (15) of restarts attempts was exceeded for host(s) DGAgent2,DGAgent1
04-16-2021 15:33			FS-5	DGAgent2	Host Reconnect Startup Error. Operation=StartSession Command : Host Reply Timeout (Connected)
04-16-2021 15:33			FS-1	DGAgent2,DGAgent1	Disabled auto restart because maximum # (15) of restarts attempts was exceeded for host(s) DGAgent2,DGAgent1
04-16-2021 15:33			FS-1	DGAgent2	Host Reconnect Startup Error. Operation=StartSession Command : Host Reply Timeout (Connected)
04-16-2021 15:33			FS-5	DGAgent2	Auto starting job, DGAgent2 host is now available.
04-16-2021 15:33			FS-5	DGAgent2	Host Reconnect Startup Error. Operation=StartSession Command : Host Reply Timeout (Connected)
04-16-2021 15:33			FS-1	DGAgent2	Auto starting job, DGAgent2 host is now available.
04-16-2021 15:33			FS-1	DGAgent2	Host Reconnect Startup Error. Operation=StartSession Command : Host Reply Timeout (Connected)
04-16-2021 15:33			FS-5	DGAgent2	Auto starting job, DGAgent2 host is now available.
04-16-2021 15:33			FS-4	DGAgent2	Disabled auto restart because maximum # (15) of restarts attempts was exceeded for host(s) DGAgent2
04-16-2021 15:33			FS-5	DGAgent2	Host Reconnect Startup Error. Operation=StartSession Command : Host Reply Timeout (Connected)
04-16-2021 15:33			FS-1	DGAgent2	Auto starting job, DGAgent2 host is now available.
04-16-2021 15:33			FS-4	DGAgent2	Host Reconnect Startup Error. Operation=StartSession Command : Host Reply Timeout (Connected)

Basic Concepts

The topics in this section provide information on advanced functionality and configuration options available in Peer Management Center.

- [Email Alerts](#)
- [File and Folder Filters](#)
- [List Filters](#)
- [Logging and Alerts](#)
- [SNMP Notifications](#)
- [Tags](#)
- [Web Client Users](#)

Email Alerts

Overview

An email alert notifies recipients when a certain type of event occurs, for example, file quarantined, session aborted, host failure, system alert. When an email alert is applied to a

job, an alert is sent to all listed recipients whenever a selected event type is triggered by the job.

An email alert consists of a unique name, a selection of event types, and a list of email addresses. The available event types depend on the job type.

When you create a job, you can select an existing email alert to apply to the job or you can create a new alert and apply it to the job. Multiple email alerts can be applied to a job. You cannot modify an email alert while it is applied to a running job. You cannot delete an email alert while it is applied to any job. An alert can be applied to multiple jobs of the same type. Email alerts are defined in the [preferences](#) for a job type.

See [Email Configuration](#) for configuring an SMTP email connection. This must be configured before email alerts can be sent.

Managing Email Alerts

You can create, edit, copy, and delete alerts.

To manage email alerts:

1. Select **Preferences** from the **Window** menu.

The **Preferences** dialog appears.

2. Select the job type from the navigation tree and expand it.
3. Select **Email Alerts** from the navigation tree.

The **Email Alerts** page lists existing email alerts for that job type.

File and Folder Filters

Overview

A file filter enables you to specify which files (and folders) should be included and/or excluded from a job's [watch set](#). Included files are subject to scan(s) and real-time event detection, while excluded files are not. Initially, all files are included and no files are excluded from a job, except for files matching the [predefined file filters](#) and [automatically excluded file types](#).

Filters can also operate on folders, allowing you to include and exclude folders from a job's watch set. For more information on folder filters, see [Folder Filters](#).

A file filter consists of a unique name and one or more [filter patterns](#). A filter can also be based on a file's [last modified time](#) and [file size](#). For more information on defining a filter pattern, see [Defining Filter Patterns](#). For more information on defining a filter pattern that can be used to filter folders, see [Filtering Folders](#).

Types of File Filters

There are three types of file filters:

- **General** - Can be applied to any job type.
- **Synchronization Only** - Can be applied to File Collaboration jobs only. Select this filter type to exclude file types from being locked when a file open is detected on a participant in a File Collaboration job.
- **Locking Only** - Can be applied to File Collaboration jobs only. Select this filter type to exclude synchronization across the entire File Collaboration job so that only opens and closes are detected and acted on without any synchronization being performed.

For more information, see [Creating and Applying File Filters](#).

Creating and Applying File Filters

You create a file filter in the **File and Folders** page of [Preferences](#) for a job type; the filter can then be applied to individual jobs of the same type. For example, a file filter created in [Cloud Backup and Replication Preferences](#) can be applied to any Cloud Backup and Replication job; a file filter created in [Collab, Sync, and Replication Preferences](#) can be applied to any File Collaboration, File Synchronization, or File Replication job. Multiple file filters can be applied to a single job.

In addition, there are also [predefined filters](#) that are applied to jobs; some of these predefined filters are automatically applied to certain job types.

For more information about creating a file filter, see:

- [Creating File Filters for a Cloud Backup and Replication Job](#)
- [Creating File Filters for File Collaboration, File Locking File Replication, and File Synchronization Jobs](#)

Predefined File Filters

In addition to defining your own file filters, there are predefined file filters that can be applied to jobs. The predefined filters vary per job type.

File and Folder Filters					
Name	Type	Exclusions	Inclusions	Date Filter	Size Filter
Default	General	~*.*, *.BAK, *.BCK, *.WBK, *.ASD...	None Selected	Include all dates	None
File Collaboration Sync Only	Synchronization Only	None Selected	*.LOG, *.EXE, *.DLL, *.OTF,...	Include all dates	None
Invalid Characters	General	<<.*[.]\$>>	None Selected	Include all dates	None
Locking Only	Locking Only	None Selected	*	Include all dates	None
MacOS Exclusions	General	*__MACOSX, *\TemporaryItem...	None Selected	Include all dates	None
PEER_Autodesk AutoCAD [General]	General	*.BAK, *.DWL	None Selected	Include all dates	None
Synchronizing Only	Synchronization Only	None Selected	*	Include all dates	None
User Profile Exclusions	General	*\AppData\Roaming\Microsoft\...	None Selected	Include all dates	None


Two of the predefined filters, **Default** and **Invalid Characters**, are applied to all jobs by default. However, you can deselect a predefined filter for a specific job. Only the **Default** filter can be modified; none of the predefined file filters can be deleted.

In addition to these predefined filters, there are [file types that are automatically excluded](#) from a watch set for all job types.


To upgrade a predefined filter:

1. Select **Preferences** from the **Window** menu.
2. Expand **Cloud Backup and Replication** or **Collab, Sync, and Repl Summary** in the navigation tree, and then select **File and Folder Filters**.


Existing file filters are listed in the **File and Folder Filters** table.



3. Select the filter to upgrade, and then click **Upgrade**.
4. If no changes are available, click **OK** to close the message that appears.



If an updated filter definition is available, a confirmation message lists the changes to the filter definition; click **OK** to install the updated definition.



Defining Filter Patterns

A **filter pattern** is a character string that defines a logical expression that is evaluated to determine which files and folders match the pattern. A file filter pattern can contain [complex regular expressions](#) and [wildcards](#). See [Folder Filters](#) for more information about what a folder filter pattern can contain.

Files and folders that match an **exclusion pattern** are excluded from the [watch set](#); files and folders that match an **inclusion pattern** are included the watch set. For example, in the following file filter definition, files with names ending in *.dotx are excluded and files with names ending with *.docx are included:

The screenshot shows the "Create File Filter" dialog box. It features a title bar with a close button. The main area is divided into several sections:

- Name:** An empty text input field.
- Filter Type:** A dropdown menu currently set to "General".
- Auto Excluded:** A section with a link that says "View file types that are automatically excluded".
- Excluded Patterns:** A large empty text area for listing patterns to be excluded, with "Add", "Edit", and "Delete" buttons below it.
- Included Patterns:** A large empty text area for listing patterns to be included, with "Add", "Edit", and "Delete" buttons below it.
- Included Last Modified Dates:** A dropdown menu set to "Include all dates" and a text box containing "0 days".
- Excluded File Sizes:** A dropdown menu set to "None" and a text box containing "0 bytes".

At the bottom of the dialog are "OK" and "Cancel" buttons.

You can use the following wildcards in a file filter pattern to more easily cover well-known file extensions or names that follow established patterns.

*	Matches zero or more characters of any value
?	Matches one character of any value

The following examples show the use of a wildcard:

- *.ext** Filter files that end with the **.ext** extension
- ext*** Filter files that begin with the string **ext**
- ext** Filter files that contain the string **ext**

The following expressions are automatically applied as exclusion patterns and cannot be modified.

File Type	Exclusion Pattern
Temporary files generated by common applications	~\$*. *.tmp *.\$\$\$ Any file without a file extension, e.g., abcdefg
Explorer System Files	desktop.ini, thumbs.db, and Windows shortcut file, e.g., *.lnk

You will generally want to exclude all temporary files created by the applications you use so they are not propagated to the target hosts. For example, if your [watch set](#) contains files created by AutoCAD applications, you should create a file filter to exclude the temporary files created by these applications.

Typically, AutoCAD files have the following extensions:

.AC\$

.SV\$


.DWL

.BAK

To create a file filter that excludes these temporary AutoCAD files, you would add these extensions (with [wildcards](#)) to the **Excluded Patterns** field:

1. Click the **Add** button under the **Excluded Patterns** field.

The **Add Exclusion Pattern** dialog appears.



2. Enter ***.AC\$**, and then click **OK**.
3. Repeat Step 2 to add ***.BAK**, ***.DWL*** and ***.SV\$**.

The patterns are listed in the **Excluded Patterns** field.

Create File Filter

Name:

Filter Type:

Auto Excluded
[View file types that are automatically excluded](#)

Excluded Patterns

- *.ACS
- *.BAK
- *.DWL*
- *.SVS

Included Patterns

Included Last Modified Dates
 days

Excluded File Sizes
 bytes

You have now created a file filter that excludes temporary AutoCAD files—all files ending in *.AC\$, *.BAK, *.DWL*, or *.SV\$ will be excluded from any running job that uses this filter.

Using Complex Regular Expressions in Filter Patterns

You can use complex regular expressions in filter patterns. Use the following format for a regular expression:

```
<<regEx>>
```

For example, the following filter pattern contains a regular expression that finds AutoCAD temporary files (atmp files):

```
<<^.*\\atmp[0-9]{4,}$>>
```

Using the following regular expression in an exclusion pattern excludes any path containing a folder **XX** that also contains a child folder **YY**:

```
<<^.*\\XX\\YY(\\. *$|)$>>
```

The following files and folders **MATCH** the above expression:

```
\\projects\\xx\\yy  
\\accounting\\projects\\xx\\yy\\file.txt  
\\accounting\\projects\\xx\\yy\\zz\\file.txt
```

The following files and folders **DO NOT MATCH** the above expression:

```
\\projects\\accounting\\file.txt  
\\projects\\xx\\y  
\\projects\\xx\\yyy\\file.txt  
\\accounting\\projects\\xx\\file.txt  
\\accounting\\projects\\yy\\xx\\zz\\file.txt
```

For a good reference on regular expressions, see <http://www.regular-expressions.info/reference.html>

In addition to filtering on file names, file extensions, folder paths, or partial path wildcard pattern matching, you can filter based on a file's last modified date:

- Peer Management Center supports filtering on a file's last modified date but does not support filtering on a folder's last modified date.

-
- If you have a folder hierarchy that contains files that are all being filtered based on last modified date, then all folders will still be created during the initial scan process on all hosts.
 - If a file is excluded from collaboration based on its last modified date, then the initial scanning process will not synchronize the file even if the file's last modified time and size do not match, or the file does not exist on all hosts. However, the file will be synchronized, if and when the file is modified in the future, and if a user deletes or renames the file on any host, the file will be deleted or renamed from all other hosts where the file exists.
 - A file filter cannot combine filtering on last modified date with inclusion or exclusion patterns or [file size](#). The last modified date is the sole criteria used to identify matching files.

Options for Included Last Modified Date Filter

The screenshot shows a 'Create File Filter' dialog box with the following fields and options:

- Name:** An empty text input field.
- Filter Type:** A dropdown menu set to 'General'.
- Auto Excluded:** A section with a link: [View file types that are automatically excluded](#).
- Excluded Patterns:** An empty list box with 'Add', 'Edit', and 'Delete' buttons below it.
- Included Patterns:** An empty list box with 'Add', 'Edit', and 'Delete' buttons below it.
- Included Last Modified Dates:** A dropdown menu set to 'Include older than' with a value of '0' days. This section is highlighted with a red box.
- Excluded File Sizes:** A dropdown menu set to 'None' with a value of '0' bytes.
- Buttons:** 'OK' and 'Cancel' buttons at the bottom right.

Field	Description
Include all dates	This is the default option and will include all files regardless of last modified date.
Include today and past	Includes all files whose last modified date are more recent than the specified number days. For example, you can exclude all files that have not been modified within the last year (365 days).
Include older than	Includes all files whose last modified date are older than the specified number days.

In addition to filtering on file names, file extensions, folder paths, or partial path wildcard pattern matching, you can filter based on the size of an individual file, excluding files that are greater or less than a specified size:

- Peer Management Center does not support filtering on a folder's total size.
- If you have a folder hierarchy that contains files that are all being filtered based on size, then all folders will still be created during the initial scan process on all hosts.
- If a file is excluded from collaboration based on size, then the initial scanning process will not synchronize the file even if the file's last modified time and size do not match, or the file does not exist on all hosts. However, if a user deletes or renames the file on any host, the file will be deleted or renamed from all other hosts where the file exists.
- You cannot define a file filter that combines filtering on file size with inclusion or exclusion patterns or [last modified date](#). The file size is the sole criteria used to identify matching files.

Options for Excluded File Sizes

The screenshot shows the 'Create File Filter' dialog box with the following sections:

- Name:** An empty text input field.
- Filter Type:** A dropdown menu set to 'General'.
- Auto Excluded:** A section with a link: [View file types that are automatically excluded](#).
- Excluded Patterns:** An empty list box with 'Add', 'Edit', and 'Delete' buttons below it.
- Included Patterns:** An empty list box with 'Add', 'Edit', and 'Delete' buttons below it.
- Included Last Modified Dates:** A dropdown menu set to 'Include all dates' and a text input field containing '0' followed by 'days'.
- Excluded File Sizes:** A dropdown menu set to 'None' and a text input field containing '0' followed by 'bytes'. This section is highlighted with a red box.

At the bottom of the dialog are 'OK' and 'Cancel' buttons.

Field	Description
None	Default option. Select this option to include all files regardless of file size.
Exclude files greater than or equal to	Select this option to exclude all files whose size is greater than or equal to the specified number of bytes. For example, you can configure a job to exclude all files greater than 1 GB.
Exclude files less than	Select this option to exclude files whose size is less than the specified number of bytes.

Filtering Folders

In addition to creating file filters, you can create folder filters. Folder filters allow you to include and exclude folders from a job's watch set. See [Folder Filter Examples](#) for examples of folder filters. Folder filters are created in the same way as file filters.

Reduce the Number of Jobs Using Folder Filtering

For management purposes, we recommend keeping the total number of jobs as low as possible. Using folder filters, you can reduce the total number of jobs without sacrificing efficiency. This process involves analyzing all existing jobs, identifying all the folders and hosts that will be collaborating, and consolidating them into fewer jobs by watching a few root folders at a higher level. Filters will then be added to include or exclude only the folders of interest.

Folder Filter Syntax

When defining a filter pattern to use on folders, use the following syntax:

\Folder or **\Folder*** or **\Folder***

Presently, Peer Management Center supports included expressions for a full folder path only and does not support wildcard matching on parent paths. For example, the following expression is not valid:

\Folder*\Folder

Example of a Simple Folder Filter

The following example reduce the number of existing jobs from four to two:

		Server 1		Server 2	
		Drive D	Drive E	Drive D	Drive F
Old Jobs	Job 1	D:\General		D:\General	
	Job 2		E:\Common		F:\Common
	Job 3	D:\Projects		D:\Projects	
	Job 4		E:\Documents		F:\Documents

After consolidation:

				Filter Option 1	Filter Option 2
		Server 1	Server 2	INCLUDE	EXCLUDE
New Jobs	Job 1	D:\	D:\	\General*	All other files
				\Projects*	
	Job 2	E:\	F:\	\Common*	All other files
				\Documents*	

Jobs 1 and 3 were merged into a single job watching the root D drive on both servers while using Filter Option 1 or 2.

Jobs 2 and 4 were merged into a single job watching the root E drive on Server 1 and the root F drive on Server 2 while using Filter Option 1 or 2.

Please note the following regarding regular expressions:

- Peer Management Center does not support the ability to use regular expressions for multi-level folder inclusions such as `\Level1\Level2\FolderName`.
- Peer Management Center does not currently support the ability to filter on certain parts of a path, like `\Folder*\Folder` and `\Folder*`.

Additional Examples of Folder Filters

To exclude a specific folder from anywhere within the watch set:	*\FolderName *\FolderName\FolderName
To exclude a specific folder from the ROOT of the watch set:	\FolderName \FolderName\FolderName
To exclude folders that end with a specific name from anywhere within the watch set:	*FolderName\
To include a specific folder from the root of the watch set:	\FolderName \FolderName\FolderName

File Filter Usage Notes

Conflicting Patterns

Since inclusions and exclusions patterns are expressed separately, it is possible to submit conflicting patterns. The pattern evaluator addresses this by exiting when a file is determined to be excluded. Therefore, exclusions patterns override inclusion patterns.

Rename Operations

Rename operations may subject files to an inclusion status change. Renaming a file out of the watch set will trigger a target deletion, while renaming into the Rename operations may subject files to an inclusion status change. Renaming a file out of the [watch set](#) triggers a target addition.

Folder Deletions

Folder deletions only affect included files, possibly leading to folder structure inconsistencies. When a session participant deletes a folder, the target outcome will vary depending on whether excluded files are present. Folder deletions are propagated in detail to the targets as to the exact files that have been affected.

List Filters

Peer Management Center provides the ability to filter lists throughout the Peer Management Center interface. List filters can help you quickly find jobs, Agents, and sort through summary reports

To use a list filter, enter a filter expression in the filter expression box. The search results of your filter are displayed in the window below the expression.

You can save the list filters and reuse them. For more information, see [Saving and Managing List Filters](#). This is useful when you frequently use the same list filter or when you create complex list filters.

Use the **Ctrl + Space** keyboard shortcut to list all possible list filters and predefined labels, which can be selected to refine your search quickly.

Basic Filter Expressions

The simplest filter expressions contain words you are looking for. For example, to find all items related to sales, simply type the word *sales* in the filter expression box. All items from the list that contain the word *sales* in their name, tag names, or tag categories will be displayed, and all other items will be hidden. The agent attribute fields (see [attr](#) below) are not included in generic searches.

If you want an exact word match or the words contain a space, enclose the terms in double quotes. For example, if you want to search for the words *North America*, the two words must be contained in double quotes. If you want to search for the word *agent* only without showing *USAgent* or *Agent2015* in results, the word *agent* must be contained in double quotes.

For information about creating more complex filter expressions using operators and labels, see [Creating Complex Filter Expressions](#).

Predefined List Filters

- Default job filters include **Failed Jobs**, **Jobs with Backlog**, and **Running Scans**.
- Default Agent filters include **Connected** and **Disconnected** (e.g., filter:"Running Scans").

Creating Complex Filter Expressions

You can create more sophisticated list filters by using operators and labels.

Using Operators

Operators allow you to combine multiple simple expressions into a single compound expression. Supported operators are: **OR**, **AND**, and **NOT**. For example, typing `tag:Americas AND sales` in the Filter Expression will show only Agents with the word *Americas* in their tag(s) **AND** the word *sales* in their name, tags, or tag categories. Parentheses can be used to build more complex expressions by grouping simple expressions.

Using Labels

Use predefined labels to specify in which field your filter word should appear. Use the following format to take advantage of labels in your filter expression:

`<label>:<search string>`.

List of possible labels include:

- name** List only items that match the string (e.g., `name:"Design Data"`)
- tag** Show only items with the word specified in their tag(s) (e.g., `tag:Americas`)
- cat** Search for items that have been assigned a specific category (e.g., search for Jobs that were categorized as Design - `cat:Design`)
- host** Filter through Jobs and list only those that contain the host in the list of job participants (e.g., `host:WIN12R2A`)
- attr** Search for the specified string in the following Agent fields: Connection Status, Operating System, JVM Architecture, and Agent Version (e.g., `attr:x86`)
- filter** List items that have been assigned a default or user-created filter.

Examples

Example 1: Show all Agents with the word *Sales* in their name, tag name, or tag category:

`Sales`

Example 2: Show all Agents with a tag that has *North America* in the tag name and *Location* in the tag category:

`cat:Location AND tag:"North America"`

Example 3: Show all Agents with the word *Sales* in their name, tag name, and tag category and with a tag that has *North America* in the tag name and *Location* in the tag category.

Sales AND (cat:Location AND tag:"North America")

Saving and Managing List Filters

Throughout the Peer Management Center interface, you will have the opportunity to save your filter expression by clicking the **Manage, Save, and Load filters** button, usually located above the **Filter Expression** field or in the **Actions** drop-down menu. The **Manage, Save, and Load filters** button is available in the [Jobs view](#) panel, the [Agent Summary](#) view, the and the [Collaboration Summary](#) panel.


To remove a list filter and show all items in the list, click the pencil icon to the right of the filter expression.

Logging and Alerts

Logging

PeerGFS performs an extensive amount of logging to track events and activities processed by PeerGFS. The results are stored in log files that are useful for troubleshooting and [analytics](#). PeerGFS tracks and logs many types of information and activities, including file events, preferences, job-specific configuration files, and analytics files.

Many of the log files have an .log extension; these are text files that can be opened in a text editing application. Other log files are stored in other file formats such as .xml, .csv, and .prefs. Log files are stored in the **workspace** folder in the Peer Management Center and Agent installation directories:



If you want to review log files for troubleshooting or analytical purposes, you can retrieve them as a single, compressed file, which is then stored in the **support** folder in the Peer Management Center installation directory. The [retrieval process](#) compiles the various log files into a single zip file that is easy to review and send to others for review. When retrieving log files, you have various options, such as choosing which log files are included, whether to encrypt log files (which may contain sensitive information), and whether to have the zip file automatically sent to Peer Software Support.

Job Alerts

Various types of alerts will be logged to a log file and to the **Alerts** table located within the job's runtime summary view for the selected job. Each job will log to the **fc_alert.log** file located in the **Hub\logs** subdirectory within the Peer Management Center installation directory.

The default log level is WARNING, which will show any warning or error alerts that occur during a running session. Depending on the severity of the alert, the job may need to be restarted.

Retrieving Log Files

To retrieve log files:

1. Open Peer Management Center.
2. From the **Help** menu, choose **Retrieve PMC/Agent Logs**.

The **Retrieve PMC/Agent Log Files** dialog is displayed.

Retrieve PMC/Agent Log Files

Log Collection Options

Include logs newer than days

Run Event Detection Analytics before log file collection

Exclude detailed log files

Collect system event logs

Include topology statistics

Agent Log Options

Exclude all Agent log files

Include all connected Agent log files

Include log files from the following connected Agents:

Agent
<input type="checkbox"/> DGAgent1
<input type="checkbox"/> DGAgent2
<input type="checkbox"/> DGAgent3

[Select All](#) [Clear Selected](#)

Encryption and Support Options

Encrypt log files

Upload log files and telemetry to Peer Software Support

Log retrieval can take a while based on network speed and log file sizes.
You will be notified when this operation completes.


Are you sure you want to proceed with this operation?

3. Select the logging options.

There are three sets of options:

- [Log Collection Options](#)
- [Agent Log Options](#)
- [Encryption and Support Options](#)

4. Enter your contact information and a description of the problem. All fields are required.




The image shows a dialog box titled "Contact Information" with a close button (X) in the top right corner. Inside the dialog, there is a question mark icon and the text "Please enter your contact information and a description of the problem below:". Below this text are several input fields: "Name:", "Phone:", "Email address:", "Case number:", "Service number:", and "Description:". The "Description:" field is a larger text area with a vertical scrollbar. At the bottom right of the dialog, there are two buttons: "OK" and "Cancel".

This information will be sent to Peer Software Support.

5. Click **Yes** to start the log retrieval process.

It may take some time for the log files to be collected and compiled into a single, compressed file. When the retrieval is finished, a message is displayed.



The image shows a dialog box titled "Log Files Gathering Status" with a close button (X) in the top right corner. Inside the dialog, there is an information icon (i) and the text "Retrieve PMC/Agent Logs task completed successfully. The zip file is located on host DGPMC1 at the following location:". Below this text is the file path: "C:\Program Files\Peer Software\Peer Management Center\Hub\workspace\support\PL-Hub-Logs-DGPMC1-04-10-2021.01.04.27.zip". At the bottom right of the dialog, there is an "OK" button.

6. Click **OK**.

The retrieved log file is stored as a zip file in the **workspace/support** subfolder in the Peer Management Center installation directory.

Log Collection Options

Option	Description
Include logs newer than X days	Use this option to restrict the logs retrieved to a certain time period.
Run Event Detection Analytics before log file collection	Select this option to run event detections analytics immediately before the log files collected. PeerGFS can perform event detection analysis every night; however, this option ensures that the log bundle contains the most up-to-date analytics.
Exclude detailed log files	Select this option to reduce size of log uploads. By default, log collection includes all Peer-generated log files (for example, event log files, activity log files, and Agent output logs if Agents are selected in the Agent Log Options section). If this option is selected, detailed log files will not be uploaded, thus reducing Peer Technical Support's ability to troubleshoot using log files.
Collect system event logs	Select this option to retrieve Windows event logs.
Include topology statistics	Select this option to include topology statistics. This option appears only for users with a subscription license.

Agent Log Options

Option	Description
Do not include any agent log files	Select this option if you do not want to retrieve log files for any Agent.
Include all connected agent log files	Select this option if you want to retrieve log files for all connected Agents.
Include the log files from the connected agents selected below	Select this option if you want to retrieve log files for selected connected Agents.

Encryption and Support Options

Option	Description
Encrypt log files	Select this option if you want to encrypt the log files in the zip file. We suggest checking this option if you are uploading the log bundle to Peer Software Support.
Automatically upload log files and telemetry to Peer Software Support	Select this option if you want to automatically upload the zip file containing the log files and telemetry information to Peer Software Support. No file data will be uploaded—only Peer-specific configuration, logs, etc.

Job Logs and Alerts

You can configure the logging and alert settings for a job when you edit a job. By default, all file collaboration and synchronization activity are logged for all severity levels. You can enable or disable file event logging, as well as select the level of granularity.

The screenshot shows the 'Edit File Collaboration Job' dialog box. The sidebar on the left lists the following categories: Participants, General, File Filters, Conflict Resolution, Delta Replication, File Metadata, File Locking, Application Support, Logging and Alerts (highlighted), Target Protection, Email Alerts, SNMP Notifications, Tags, and DFS-N. The main area is titled 'Logging and Alerts' and contains the following settings:

- Enabled:
- Severity: All (dropdown menu)
- Alerts: Severity: INFO (dropdown menu)

At the bottom right of the dialog are 'OK' and 'Cancel' buttons.

Log Entry Severity Levels

Level	Description
Informational	Informational log entry, e.g., a file was opened.
Warning	Some sort of warning occurred that did not produce an error but was unexpected or may need further investigation.
Error	An error occurred performing some type of file activity.
Fatal	A fatal error occurred that caused a host to be taken out of the session, a file to be quarantined, or a session to become invalid.

Job Alerts

Various types of alerts will be logged to a log file and to the **Alerts** table located within the job's runtime summary view for the selected job. Each job will log to the **fc_alert.log** file located in the **Hub\logs** subdirectory within the Peer Management Center installation directory.

The default log level is **WARNING**, which will show any warning or error alerts that occur during a running session. Depending on the severity of the alert, the job may need to be restarted.

SNMP Notifications

Overview

Peer Management Center provides support for SNMP v1 messaging. A SNMP notification notifies recipients when a certain type of event occurs, for example, session abort, host failure, system alert. When an SNMP notification is applied to a job, a SNMP trap is sent to the destination IP address or hostname whenever a selected notification type is triggered by the job. The available notification types depend on the job type.

When you create a job, you can select an existing SNMP notification to apply to the job or you can create a new notification and apply it to the job. You cannot modify or delete a notification while it is applied to a job. An SMNP notification can be applied to multiple jobs of the same type. SNMP notifications are defined in the [preferences](#) for a job type. An SNMP notification can be applied to all job types except File Replication.

Note that before Peer Management Center can send SMNP notifications on behalf of any job, you must [configure some SNMP settings](#).

Managing SMNP Notifications

To manage SMNP notifications:

1. Select **Preferences** from the **Window** menu.

The **Preferences** dialog appears.

2. Select the job type from the navigation tree and expand it.
3. Select **SMNP Notifications** from the navigation tree.

The **SMNP Notifications** page lists existing SMNP notifications for that job type. You can create, edit, copy, and delete notifications.

Tags

Tags can be used to categorize resources and customize a user's workspace or perspective. Tagging helps when managing large number of resources.

You can assign tags to:

- Jobs
- Resources
- Web roles
- Agents

You can also assign resources to tags. See [Using Tags to Filter Resources](#).

Creating Tags and Categories

Tags and categories are created in [Tags Configuration](#) in **Preferences**. The **Assign Tags** dialog also offers the option to create tags and categories.

Assigning Tags

You can:

- Assign tags during job creation
- Assign tags while editing an existing job
- Assign tags to one or more resources
- Assign tags to web roles
- Assign resources to one or more tags

Assigning Tags to Jobs

- During job creation - You can assign tags during the creation of a job from the [Tags](#) page of the job creation wizard.
- During job editing - You can assign tags to individual jobs by right-clicking on the job, selecting **Edit Job(s)**, and navigating to the **Tags** page of the job editing wizard.

Assigning Tags to Resources

To assign tags to one or more resources:

1. Click the **Assign Tags** button from the main view, [Jobs view](#), or [Agent Summary view](#) toolbars.
2. In the **Assign Tags** dialog, click the **Tags** radio button.
3. Select the tag that needs to be assigned to one or more resources.
4. Click the **Edit** button.

The **Assign/Unassign resources** dialog appears.

5. In the **Unassigned Resources** table, select the resources to be assigned the selected tag, and then click the right-arrow button (Add One) to move it to the table on the right side.

Tip: To select multiple resources, press the Shift key on the keyboard when selecting resources.

6. Click **Save**.
7. Repeat the preceding steps for all the tags that need to be assigned to one or more resources.

Assigning Tags to Web Roles

Web roles can be assigned tags that customize a user's Jobs view when they log in via the [web client](#). For example, in a very large deployment scenario, a user that is part of the Help Desk role can be assigned tags that limit their view to only jobs that are part of their region.

To assign tags to user roles:

1. Create tags and categories as outlined in Step 1 above.
2. Assign tags to one or more jobs as outlined in Step 2 above.

3. Go to [User Management](#) in the [Preferences](#) page.
4. Select the desired role to which you wish to assign specific job tags.
5. Click the **Edit** button.
6. In the **Tags** window, from the **Unassigned Tags** table on the left side, select the tags that need to be assigned the selected role, and then click the right-arrow button (Add one) to move it to the table on the right side (hold down the Shift key on the keyboard when selecting tags to select more than one).
7. Click **OK** to commit your changes and close the dialog, and then close the **Preferences** page.

The user will see only the jobs that were tagged in the user's role.

Assigning Resources to One or More Tags

To assign resources to one or more tags:

1. Click the **Assign Tags** button from a summary view, [Jobs view](#), or [Agent Summary view](#) toolbar.
2. In the **Assign Tags** dialog, click the **Resources** radio button.
3. On the left-hand side, click inside the **Resource Name Filter** or **Type Filter** fields and press the CTRL + Space keys on the keyboard to list all possible filters and predefined labels, which can be selected to refine your search quickly.
4. Select the resource that needs to be assigned to one or more tags.
5. Click the **Edit** button to the right.
6. From the **Unassigned Tags** table on the left side, select the tags that need to be assigned the selected Resource, and then click the right-arrow button (Add one) to move it to the table on the right side (hold down the Shift key on the keyboard when selecting tags to select more than one).
7. Click the **Save** button to commit your changes, and then close the dialog.
8. Repeat the preceding steps for all the resources that need to be assigned to one or more tags.

Using Tags to Filter Resources

You can use tags to filter resources:

- Filter jobs
- Filter agents

To filter resources using tags, use the tag label in any list filter field throughout the Peer Management Center interface.

Filter Jobs

To filter through a large list of jobs, use the filter field located below the toolbar buttons in the **Jobs** view. For more details on how to filter through resources, see [List Filters](#).

Example:

Show all jobs with a tag that has "North America" in the tag name and "Location" in the tag category:

```
tag:"North America" AND cat:Location
```

Filter Agents

To filter through a large list of Agents, use the **Filter** field located below the toolbar buttons in the [Agent Summary View](#) panel. For more details on how to filter through resources, see [Filter Expressions](#).

Web Client Users

Peer Management Center offers two [interfaces](#):

- A rich client interface: Rich client users have access to all Peer Management Center functionality. The rich client is accessible only on the server where Peer Management Center is installed
- A web client interface: Web client users access to Peer Management Center functionality is controlled by their [web role](#).

Web client users can be divided into two categories based on how their access to the web client is authenticated:

- [Internal users](#)

- [Active Directory users and groups](#)

For information about managing web client users, see [Managing Web Client Users](#).

Internal Users

An **internal user** is one whose access to the Peer Management Center web client is authenticated by an internal Peer Management Center database rather than through Active Directory.

For information about managing internal users, see [Managing Internal Users](#).

Internal Users and Web Roles

When you add internal users to Peer Management Center, you need to specify their access to Peer Management Center functionality by assigning them a [standard web role](#) or a [custom web role](#). A **web role** is a set of [permissions](#) that specifies the appropriate level of access to Peer Management Center functionality. For example, some users will need the ability to create and edit jobs, while other users may need only to view job summaries. Assign the most suitable role to each user, giving them the most appropriate level of control and not more.

For more information about web roles, see [Overview of Web Roles](#).

Default Internal User: The admin User

There is a default internal user who has access to all Peer Management Center functionality available in the web client: the **admin** user. This user does not need to be created. This internal user has the following properties:

Username	admin
Password	password This should be changed immediately upon first log-in.
Web Role	Administrator

Unlike other internal users, the admin user cannot be renamed or deleted, nor can its role be changed. However, for security reasons, [the password should be changed immediately](#).

Active Directory Users and Groups

An Active Directory (AD) user or group is one whose access to Peer Management Center is authenticated through Active Directory. Adding an Active AD user or group authenticates and authorizes that user or group members to use Peer Management Center. The AD user or group must already exist in Active Directory prior to adding the user or group to Peer Management Center.

Active Directory users won't be able to access the web client until [Active Directory authentication is configured](#) in Peer Management Center.

For information about managing Active Directory users and groups, see [Managing Active Directory Users](#).

Active Directory Users and Web Roles

When you add Active Directory users and groups to Peer Management Center, you need to specify their access to Peer Management Center functionality by assigning them a [standard web role](#) or a [custom web role](#). A **web role** is a set of [permissions](#) that specifies the appropriate level of access to Peer Management Center functionality. For example, some users will need to the ability to create and edit jobs, while other users may need only to view job summaries. Assign the most suitable role to each user, giving them the most appropriate level of control and not more.

For more information about web roles, see [Overview of Web Roles](#).

Overview of Web Roles

All users that access Peer Management Center through the web client must have an assigned **web role**. A web role is a set of [permissions](#) that specifies the appropriate level of access to Peer Management Center functionality. For example, some users will need to the ability to create and edit jobs, while other users may need only to view job summaries.

Web client users can have a [standard web role](#) or a [custom web role](#). In contrast, a user who accesses Peer Management Center through the rich client does not have a web role. All Peer Management Center functionality is accessible to a rich client user.

For more information about web roles, see [Managing Web Roles](#).

There are three standard web roles, each with a predefined set of permissions:

- **Administrator** - This role has complete access to all functionality found in the Peer Management Center's rich client.
- **Power User** - This role has view-only access to jobs and the **Agent Summary** view; this role cannot create, edit, or delete jobs, access settings in Preferences, or assign tags.
- **Help Desk** - This role has view-only access to jobs. Specifically, Help Desk users are limited to view-only access to the following:
 - The [Jobs view](#)
 - The [runtime views](#)
 - The **Summary** and **Session** tabs of each job.

In addition, Help Desk users have read-write access to the **Quarantines** tab of each job, with the ability to release conflicts for any running jobs.

Standard web roles cannot be modified or deleted, with one exception: tags can be assigned to standard roles. For a list of the permissions associated with standard web roles, see [Standard Web Role Permissions](#).

Standard Web Role Permissions

Each of the three standard web roles (Administrator, Power User, and Help Desk) has permission to access the resources shown in the following table.

Functionality	Administrator	Power User	Help Desk
Advisory Alert View	Edit	Edit	
Broker Statistics Action	Edit	Edit	
Collaboration Summary View	Edit	Edit	

Functionality	Administra tor	Power User	Help Desk
Configuration Interface	Edit	Edit	
Event Analyzer Configuration Interface	Edit	Edit	
Event Analyzer Log View	Edit	Edit	View-only
Event Analyzer Participant view	Edit	Edit	
Event Analyzer Runtime Summary Interface	Edit	Edit	View-only
Event Log View	Edit	Edit	
Expression List Dialog	Edit	Edit	
File Conflict View	Edit	Edit	Edit
File Sync Advisory Alert View	Edit	Edit	
Folder Analyzer View	Edit	Edit	View-only
Job Alert View	Edit	Edit	
Job View	Edit	Edit	View-only
Log Dump Action	Edit	Edit	
Memory Dump Action	Edit	Edit	
New Job Action	Edit		

Functionality	Administrator	Power User	Help Desk
Participant View	Edit	Edit	
Permission Mode	Edit	Edit	
PMC Alert View	Edit	Edit	
PMC Download Agent	Edit	Edit	
PMC Refresh Perspective	Edit	Edit	
PMC View Progress	Edit	Edit	
Preferences	Edit		
Runtime Summary Interface	Edit	Edit	View-only
Session View	Edit	Edit	View-only
Status Agent Tree View	Edit	View-only	
Tag Resources Dialog	Edit		
Thread Dump Action	Edit	Edit	

PeerSync Management Job Permissions

The following table outlines the permissions for PeerSync Management jobs.

Functionality	Administrator	Power User	Help Desk
PeerSync Summary View	Edit	Edit	Edit

Functionality	Administrator	Power User	Help Desk
PeerSync Job Stats View Part View	Edit	Edit	
PeerSync Configuration Interface	Edit	Edit	View-only
PeerSync Job Stats View	Edit	Edit	Edit
PeerSync Update Log View	Edit	Edit	Edit
PeerSync Add Log View	Edit	Edit	Edit
PeerSync File Conflict View	Edit	Edit	Edit
PeerSync Runtime Summary Interface	Edit	Edit	View-only
PeerSync Participant View	Edit	Edit	
PeerSync Advisory Alert View	Edit	Edit	
PeerSync Messages Log View	Edit	Edit	Edit
PeerSync Delete Log View	Edit	Edit	Edit
PeerSync Event Log View	Edit	Edit	

A custom web role allows you to customize and fine-tune the access that a user has to Peer Management Center resources. This is useful if you have multiple types or levels of users that need different types of access. For example, if you have multiple tiers of help desk staff,

creating custom roles based on the standard Help Desk role allows you to provide them varying levels of access to Peer Management Center.

A custom role is based on one of the three [standard web roles](#) (Administrator, Power User, and Help Desk); the custom role starts with the same set of permissions as the role it is based on. However, during the process of creating the custom role, you modify the permissions associated with the new role.


For more information, see [Creating a Custom Web Role](#).

Custom Web Role Permissions

You can [create custom web roles](#) in User Management and specify the permissions you want associated with the role.

When creating a custom web role, you select the permissions for the web role in the **Permissions** table, which has three columns:

- **Category** - Identifies the general area of the user interface that the permission applies:
 - **Cloud Backup and Replication UI** - Applies to Cloud Backup and Replication jobs.
 - **Collab/Sync/Repl UI** - File Collaboration, File Synchronization, and File Replication jobs.
 - **DFS-N UI** - Applies to DFS-N Management jobs.
 - **PMC UI** - Applies to Agent Summary view, statistics, task scheduling and task history, logs, memory dumps, and thread dumps.
- **Name** - Identifies the specific area of the user interface.
- **Access** - Identifies the level of access:
 - **Full access** - Has complete access.
 - **View-only access** - Can view but not create, edit, or delete.
 - **No access** - No access.



Advanced Topics

This section discusses the following topics:

- [Analytics](#)

- [Proactive Monitoring](#)
- [Conflicts, Retries, and Quarantines](#)
- [DFS Namespaces](#)
- [Dynamic Storage Utilization](#)
- [File Metadata Synchronization](#)
- [Managing Peer Agents](#)
- [PeerGFS API](#)
- [Scheduled Replication Filters](#)
- [Smart Data Seeding](#)
- [Storage Capacity](#)
- [TLS Certificates](#)

Analytics

Starting in PeerGFS v5.1.1, there are three flavors of analytics capabilities. Some are for internal Peer Software use only, while others are controlled by your license and the level of support that you have purchased. The three capabilities are:

- A new virtual machine (VM)-based analytics system called **PeerIQ**. PeerIQ replaces the Microsoft Power BI-based dashboard for monitoring the health and performance of PeerGFS and the replication environment. Moreover, it also serves as the platform for our future analytics capabilities.
- Anonymous diagnostic information that is sent to Peer Software to help us improve PeerGFS. This can be disabled on the [Analytics](#) preferences page.
- A [Proactive Monitoring](#) option for PeerGFS customers with dedicated Technical Account Managers.

PeerIQ Overview

Peer Software provides a new virtual appliance to our subscription customers that contains a self-hosted dashboard and analytics environment named PeerIQ. PeerIQ offers tools to system

administrators for monitoring the health and performance of PeerGFS and the replication environment. PeerIQ provides intelligent insights into how PeerGFS and your storage environment are performing.

PeerIQ is hosted by you, either on-premises or in a public cloud provider. It is available as a VMware OVA, Hyper-V vhd, and a Nutanix AHV qcow2. Once the appliance is deployed, set up of PeerIQ is quick and easy with a simple configuration on the PeerIQ side, followed by the enabling of a single option on the [Analytics](#) preference page. Its dashboards are viewable in a web browser and provide a visual and interactive interface that displays telemetry that is updated automatically every few seconds by default.

PeerIQ is currently geared to provide information such as:

- Agent information, including disk space and memory utilization of all Agents.
- Job information, including watch set growth and overall performance.
- Overall PMC information, including disk space and memory utilization, queue backlogs, and quarantine counts.

Some of the information displayed in PeerIQ is available in the Peer Management Center client interface; however, PeerIQ brings the information together for easy access and provides historical data not found in the PMC client.

PeerIQ in the Future

In the future, the PeerIQ will provide even more information and in greater detail. For example:

- Proactive information about your PeerGFS environment, how well it is performing, and details about what it is replicating.
- Trends and insights around what is stored on the file servers across your storage infrastructure.
- Trends and insights around how your users and applications are using the data on the file servers across your storage infrastructure.

Proactive Monitoring

Proactive Monitoring is a new option available to PeerGFS customers with dedicated Technical Account Managers (TAMs). Once enabled, the various data points are uploaded to a Peer Software-owned storage account in Microsoft Azure. Data collected includes:

- Agent information, including disk space and memory utilization of all Agents.
- Job information, including watch set growth and overall performance.
- Overall PMC information, including disk space and memory utilization, queue backlogs, and quarantine counts.

This data is available only to Peer Software employees and is used to provide regular reviews of the status of your PeerGFS environment.

Health Checker

Proactive Monitoring can also integrate information from Peer Software's Health Checker tool. The Health Checker is a standalone service designed to alert on outages and backlog spikes, as well as track overall performance of the replication environment. To provide replication performance details to your Peer Software TAM, the Health Checker must be installed on either a standalone server in the environment (if both alerting and performance monitoring are desired) or on the PMC server itself (if only performance monitoring is desired).

Health Checker Prerequisites

While Peer Software's Health Checker is a lightweight application, there are some minimum requirements that must be met to use the tool:


- Windows Server 2012 operating system or later is required.
- Virtual servers running on enterprise-class hypervisors are sufficient if they have a minimum of 2 processor cores, 2 GB of RAM, and 20 GB of free disk space.
- SMB network access is required from the Health Checker server to all participating file servers and shares.
- The Health Checker service must be run under a domain user account with the ability to create folders and files on all participating file servers and shares.
- To provide failure and backlog alerting, the Health Checker should not be installed on any server that is already running the Peer Management Center or the Peer Agent. The Health Checker may be run on servers hosting other infrastructure (such as Active Directory Domain Controllers), provided that the requirements above are met.

Setting Up Proactive Monitoring

To set up Proactive Monitoring:

1. From the **Window** menu, select **Preferences**.
2. Select **Analytics** in the navigation tree, and then select **Proactive Monitoring**.

The **Proactive Monitoring** page is displayed.




3. Click the **Enable Proactive Monitoring** button.

The [General Configuration](#) page appears.

The **General Configuration** page is where you enter your Subscription ID and other basic information.

1. Enter your Subscription ID if the field is not auto-filled.

Contact Peer Software if you do not know your Subscription ID. Once you enter a value, it cannot be changed.



The screenshot shows a window titled "Set Up Proactive Monitoring" with a "General Configuration" tab selected. The window contains the following fields and controls:

- Subscription ID:** A text input field with a blurred value. Below it is a blue link: [What is my Subscription ID?](#)
- Environment Name:** A text input field containing the value "DGPMC1".
- Upload Interval:** A spinner control set to "30" with the label "minutes".

At the bottom of the window, there are four buttons: "< Back", "Next >" (highlighted with a blue border), "Finish", and "Cancel".

2. Enter a name in the **Environment Name** field if the auto-filled value doesn't match the name of the server or environment where the PMC server is installed.

Note: Changing the name here will also change the name in the **Environment Name** field in the [General Configuration](#) preferences page.

3. In the **Upload Interval** field, enter the number of minutes to wait between uploads of data to Proactive Monitoring.

The default upload interval is 30 minutes. The minimum interval is 15 minutes; the maximum interval is 180 minutes.

4. Click **Next**.

The [Telemetry Options](#) page appears.

The **Telemetry Options** page allows you to select detailed telemetry data to upload to be used by the Peer Software Technical Account Management Team if you signed up for Proactive Monitoring.

The detailed telemetry data is divided into three categories:

- PMC Details
- Agent Details
- Job Details

1. Select the data to be uploaded:

The screenshot shows a window titled "Set Up Proactive Monitoring" with a standard Windows title bar (minimize, maximize, close). The main heading is "Telemetry Options" with a subtitle "Review and select the types of information to upload for Proactive Monitoring." On the left is a navigation pane with the following items: "General Configuration", "Telemetry Options" (highlighted), "Agent Locations", "Health Checker Setup", and "Confirmation". The main content area has a blue link: "What types of data are uploaded to Proactive Monitoring?". Below this are three sections of checkboxes, all of which are checked:

- PMC Details:**
 - Include IP Information
 - Include Statistical Information
- Agent Details:**
 - Include IP Information
 - Include Agent Names
 - Include Agent Locations
 - Include Storage Information
- Job Details:**
 - Include Job Names
 - Include MED Alerts

At the bottom of the window are four buttons: "< Back", "Next >" (highlighted with a blue border), "Finish", and "Cancel".

The table below describes what data is included in each category. Data in the **Standard Data Upload** column is uploaded when Proactive Monitoring is enabled. Data in the **Include Optional Data** column is uploaded only if you select that option.

Category	Standard Data Upload	Include Options
PMC Details	Includes details about this PMC deployment. Details include service memory consumption, replication backlog, quarantines, license consumption, and watch set size.	<ul style="list-style-type: none"> • IP Information - The IP address of the server that this PMC is installed on. • Statistical information - In-depth statistics about the queues and performance of PeerGFS's replication engine.
Agent Details	Includes the details about the Agents that are connected to this PMC. Details include service and server memory consumption, replication throughput, uptime, operating system, and disconnect counts.	<ul style="list-style-type: none"> • IP information - The IP addresses of the servers that the Agents are installed on. • Agent Names - The names assigned to the Agents (typically the name of each Agent's Windows Server). If this option is not checked, random strings will be used in the Proactive Monitoring system to represent each Agent. • Agent Locations - The locations (the latitude, longitude, city, state, and country) of the Agents. You can enter the locations while running this wizard or in the Agent Configuration dialog later. If you choose to include Agent location data, you will be prompted to enter Agent location information on the next page of this wizard (the Agent Locations page of this wizard). No location information is automatically determined—it must be manually entered. • Storage Information - Information specific to the storage platforms that each Agent is managing, including available and used disk space.
Job Details	Includes the details about the file collaboration, synchronization and/or replication jobs configured within this PMC. Per-job details include	<ul style="list-style-type: none"> • Job Names - The names of the file collaboration, synchronization, and replication jobs configured in this PMC. If this option is not checked, random strings will be used in the Proactive Monitoring system to represent each job.
		<ul style="list-style-type: none"> • MED Alerts - If MED alerts are enabled in this PMC, this option will include any alerts for use in the Proactive Monitoring system.

2. Click **Next**.

If you selected the **Include Agent Locations** option, the [Agent Locations](#) page appears; otherwise the [Set up Health Checkup](#) page appears.

This step is optional.

The **Agent Locations** page allows you to set location details for each Agent. The **Agent Locations** page appears only if you selected the **Include Agent Locations** option on the previous wizard page. If an Agent's location has already been set through its [Agent Configuration](#), those values will automatically appear on this page.

Tip

Agents do not automatically self-detect their locations. You can look up location coordinates using free online geographic tools such as <https://www.latlong.net/> or Google Maps.

To use Google Maps to look up coordinates:

- (a) Open Google Maps, navigate to the Agent server's location and right-click this location.
- (b) On the menu that appears, click the coordinates (the first item in the menu). The coordinates are automatically copied to the Clipboard.
- (c) Paste the coordinates into a text editor window (such as Notepad).
- (d) Paste each coordinate into the proper coordinate field.

1. For each Agent that you want to set location details, enter the following information in the appropriate fields:

- **Location** - Enter the city, state, and country of where the Agent server is installed.
- **Longitude** - Enter the longitude of where the Agent server is installed.
- **Latitude** - Enter the longitude of where the Agent server is installed.

Note: The **Computer Description** column is read-only. Its value is set through Microsoft Windows.

Set Up Proactive Monitoring

Agent Locations
(Optional) Set location details for each Agent for use with dashboard maps.

General Configuration
Telemetry Options
Agent Locations
Health Checker Setup
Confirmation

Only running Agents are listed below.

Agent	Computer Description	Location*	Longitude	Latitude
DGAgent1		Centreville, VA, US	-77.428879	38.840389
DGAgent2		Vienna, VA, US	-77.262817	38.903481
DGAgent3		Washington, DC US		

*Location identifies the city, state, and country of the Agent (for example: Centreville, VA, US)

< Back **Next >** Finish Cancel

2. Click **Next**.

The [Health Checkup Setup](#) page appears.

The **Health Checker Setup** page is where you decide whether you want to set up the Health Checker, which is a standalone monitoring and reporting tool. The Health Checker is used by the Peer Software Technical Account Management team to monitor for replication issues and track the **Real-Time Delta (RTD)**. The RTD represents how many minutes out of sync the replication is between participants. It is similar to a **Recovery Point Objective (RPO)** but focuses only on the real-time replication engine and not the scan engine.

You can install the Health Checker **locally** (on the same server that Peer Management Center is installed on) or **externally** (on a server that neither Peer Management Center nor Agents are running on). To receive the full benefit of the Health Checker, we recommend that you install it externally. If you install it locally, you will not get failure alerts if the PMC server goes down.

To set up Health Checker:

1. Select a setup option.

Option	Description
Configure the Health Checker already installed on a remote server.	Recommended option for receiving the full benefit of Health Checker. If installed on remote server, Health Checker does both failure as well as performance monitoring. The remote server can be a domain controller or some other infrastructure server. It should not be running PMC or Agent software.
Set up Health Checker on this PMC server.	Select this option if you want performance statistics but not full failure monitoring. If the PMC server fails or is shut down, replication will stop but no failure alerts will be sent.
Do not install or configure the Health Checker.	Select this option if you do not want performance statistics or failure monitoring.

2. Click **Next**.

Your next step depends on the option you selected in Step 1:


If you selected this option	Continue on this wizard page
Configure the Health Checker already installed on a remote server.	Select Jobs
Set up Health Checker on this PMC server.	Set up the Health Checker
Do not install or configure the Health Checker.	Confirmation

Set Up the Health Checker

The **Set up the Health Checker** page appears only if you selected the option **Set up Health Checker on this PMC server** on the previous wizard page.


From this page, you install Health Checker. If you have previously installed Health Checker on the PMC server, it will verify that Health Checker was successfully installed and initialized and is currently running.

1. Click the **Start** button.




As the wizard performs the setup process, it communicates results via colored dots. A green dot indicates that successful completion of that setup stage. A red dot indicates that action is needed.


2. The wizard first checks to see the Health Checker has already been installed. If the dot next to **Verify Health Checker is installed** turns red, Health Checker has not yet been installed. Click the **Install** button that appears. It runs a silent packaged installer for the Health Checker. Click **OK** in the **Success** message that appears.



3. The wizard next checks to see if the Health Checker service has been initialized. If the dot next to **Verify Health Checker service is initialized** turns red, the Health Checker service has not yet been initialized. Click the **Initialize** button that appears.




In the **Service Account Info dialog**, enter the user name and password for the service, and then click **OK**.




Click **OK** in the **Success** message that appears.

4. The wizard next checks to see if the Health Checker Service is running. If the dot next to **Verify Health Checker service is running** turns red, click the **Start** button that appears. Click **OK** in the **Success** message that appears



5. Once all dots are green, click **Next**.




The [Select Jobs](#) page appears.

Select Jobs

The **Select Jobs** page allows you to specify which jobs are monitored by Health Checker. By default, all jobs are selected.

To select jobs:

1. Keep the default for the **Apply for all jobs** checkbox to monitor all current and future jobs. Otherwise, use the **Add** and **Remove** buttons to move jobs from between the **Selected** and **Available** lists.



2. Click **Next**.

The [Update Health Checker](#) page appears.

Schedule Task

The **Schedule Task** page allows you to specify when and how often Health Checker configuration information is updated.

By default, the task is set to run every day at 4-hour intervals.

1. In **Settings**, select a frequency as well as the start date and time.

The screenshot shows a window titled "Set Up Proactive Monitoring" with a "Schedule Task" section. The instruction reads: "Specify the conditions that will trigger the task." On the left is a navigation pane with options: General Configuration, Telemetry Options, Agent Locations, Health Checker Setup (expanded), Set up the Health Checker, Select Jobs, Schedule Task (highlighted), Update Health Checker, and Confirmation. The main area is divided into "Settings" and "Advanced Settings". In "Settings", "One Time" is selected. The "Start" field is set to 3/31/2023 at 12:30:25 PM. In "Advanced Settings", "Repeat task every: 4 Hours" is checked. The "Expire" field is set to 3/31/2024 at 12:30:25 PM. At the bottom are buttons for "< Back", "Next >" (highlighted), "Finish", and "Cancel".

2. In **Advanced Settings**, select whether you want the task repeated and the frequency of the repetition. We recommend repeating this task every 1 to 4 hours.

3. In **Advanced Settings**, select when you want the task to expire.

If you don't select an expiration date, the task will run indefinitely.

4. Click **Next**.

The [Configure External Health Checker](#) page appears.

Update Health Checker

The **Update Health Checker** page allows you to specify the criteria for the files that Health Checker should monitor.

To configure the Health Checker:

1. If you installed Health Checker on an external server, enter the path in UNC format to Health Checker **workspace** folder in the **Path to Health Checker Configuration** field.

The Health Checker **workspace** is a subfolder of the Health Checker installation folder. If Health Checker is installed on the PMC server, the path is automatically detected and filled in.

The screenshot shows a Windows-style dialog box titled "Set Up Proactive Monitoring" with a sub-header "Update Health Checker" and the instruction "Configure Health Checker settings." On the left is a tree view with the following items: "General Configuration", "Telemetry Options", "Agent Locations", "Health Checker Setup" (expanded), "Set up the Health Checker", "Select Jobs", "Schedule Task", "Update Health Checker" (highlighted), and "Confirmation". The main area contains the following fields and options:

- "Path to Health Checker configuration:" with a text box containing "D:\Program Files\Peer Software\Health Checker\Workspace".
- "SMB username:" with an empty text box.
- "SMB password:" with an empty text box.
- "Extensions to test:" with a text box containing ".txt".
- An unchecked checkbox labeled "Include participants that are inactive".
- A section titled "Monitor jobs that are:" containing five checkboxes:
 - Running
 - Starting
 - Stopping
 - Stopped
 - Stopped due to lost quorum

At the bottom of the dialog are four buttons: "< Back", "Next >" (highlighted with a blue border), "Finish", and "Cancel".

2. In the **SMB Username** field, enter the user name if the server hosting the Health Checker requires account credentials. In most cases, a locally installed Health Checker will not need a user name.
3. In the **SMB Password** field, enter the password if the server hosting the Health Checker requires account credentials. In most cases, a locally installed Health Checker will not need a password.
4. In the **Extensions to Test** field, enter the extensions for the file types that you want Health Checker to monitor. Separate the extensions with a semicolon.
5. Select the **Include Participants that are inactive** checkbox if you want the Health Checker to monitor inactive participants.
6. In the **Monitor jobs that are** section, select which job states should be included in Health Checker monitoring.

We recommend checking all but the **Stopped** category. The **Stopped** category includes jobs that are stopped for any reason other than a quorum lost. For example, if you have manually stopped a job, you may not want Health Checker monitoring it.

7. Click **Next**.

The [Confirmation](#) page appears.

The **Confirmation** page displays a summary of the settings you have selected.

1. Review the configuration.

The screenshot shows a window titled "Set Up Proactive Monitoring" with a "Confirmation" header. Below the header, it says "Review your configuration. Click Finish to complete the Proactive Monitoring setup process." The main area is divided into a left sidebar and a main content area. The sidebar lists the following steps: General Configuration, Telemetry Options, Agent Locations, Health Checker Setup (expanded), Set up the Health Checker, Select Jobs, Schedule Task, Update Health Checker, and Confirmation (highlighted). The main content area displays the following configuration details:


- General Configuration**
 - Subscription ID: [REDACTED]
 - Environment Name: DGPMC1
 - Upload Interval: 30 minutes
- Telemetry Options**
 - PMC Details**
 - Include PMC IP: Yes
 - Include Statistical Information: Yes
 - Agent Details**
 - Include Agent IP Info: Yes
 - Include Agent Names: Yes
 - Include Agent Locations: Yes
 - Include Agent Storage Information: Yes
 - Job Details**
 - Include Job Names: Yes
 - Include MED Alerts: Yes

Note: After clicking Finish, the settings specified in this wizard will be enabled immediately. Information will be uploaded to the Proactive Monitoring dashboard within 30 minutes. You can change these settings or disable the upload of this information by selecting Proactive Monitoring from the Help menu, and then clicking the Disable button in the Proactive Monitoring preference page.

At the bottom of the dialog, there are four buttons: "< Back" (highlighted), "Next >", "Finish", and "Cancel".

2. Click **Finish** to complete the setup.

The settings are displayed in the Proactive Monitoring preferences page.



Note: If you modified the location of an Agent, you will be prompted to restart the Agent. Click **Restart Later** if you do not want to restart the Agent services because you have other jobs running; otherwise, click **Restart Now**.

3. Click **Apply and Close**.
4. Notify your Peer Software Technical Account Manager that the setup of Proactive Monitoring is complete.

The effects of disabling Proactive Monitoring are:


- Your Peer Software Technical Account Manager will no longer be able to check on the status of your PeerGFS environment.
- Data will no longer be uploaded to Peer Software. If you disable Proactive Monitoring, you have the option of having your data deleted by Peer Software.

To disable Proactive Monitoring:


1. Select **Preferences** from the **Window** menu.

The **Preferences** dialog appears.

2. Select **Analytics** in the navigation tree, and then select **Proactive Monitoring**.




3. Click the **Disable Proactive Monitoring** button.
4. Click **Yes** to confirm that you want to disable Proactive Monitoring.




5. Click **Yes** if you want your data deleted.

Peer Software will be notified to delete your data from Microsoft Azure. This process will remove all of your current and historical information. Once deleted, this data will not be recoverable.




6. If Health Checker was installed locally, select an option in **Health Checker** dialog that appears:




- Click **Disable** if you want Health Checker disabled but not uninstalled. The Health Checker Service will be stopped and prevented from starting automatically.
- Click **Uninstall** if you want Health Checker uninstalled. An uninstaller will start automatically to remove the Health Checker service and all installed files.
- Click **Do Nothing** if you want the Health Checker to remain installed and running.

7. Click **OK** in the dialog that appears if you chose to remove Proactive Monitoring data.



The **Preferences** page reappears.



8. Click **Apply and Close** or **Apply**.

Re-enabling Proactive Monitoring

To re-enable Proactive Monitoring, you must rerun the Set up Proactive Monitoring wizard.

You can access the wizard by clicking the **Enable Proactive Monitoring** button in the [Proactive Monitoring preferences](#) page.

Conflicts, Retries, and Quarantines

Making unstructured data active at multiple locations introduces the chance of users making conflicting changes to different copies of the same file. The real-time synchronization and locking engines built into Peer Global File Service are designed to prevent these conflicts by ensuring that only one user can modify a file at a time while also making sure that all locations always have the most up to date version of a file. There are scenarios, however, where the synchronization and locking engines may not be able to prevent version conflicts. Such scenarios include network outages and file system issues.

The conflict resolution engine in Peer Global File Service is designed to handle these circumstances with a three-tiered approach backed by a combination of scans and real-time activity:

- **File Conflicts** – The initial state of detection of a potential version conflict. Depending on user activity, these can often be resolved automatically.
- **File Retries** – If certain errors are thrown when trying to synchronize a file between locations, this file will be automatically put into a retry list. Synchronization of this file will be retried every minute for a maximum of 60 attempts. The frequency of attempts and the maximum number of attempts are configurable.
- **File Quarantines** – These are file conflicts that could not be automatically resolved, as well as file retries that have failed after the maximum number of attempts. Files in the quarantine list will no longer be synchronized or protected with file locks until a winning file is picked through the PeerGFS user interface.

File conflicts (and potentially quarantines) can occur for any of the following reasons:

- Two users open a file at the same time or in-and-around the same time.
- A file is open at the start of a job and has been modified on a host where the configured conflict resolution strategy selects a different host as the winner.
- Two or more users have the same file open on different hosts when a collaboration job is started.
- A file was modified on two or more hosts between job restarts or network outages.
- Peer Management Center is unable to obtain a lock on a target host file for various reasons.
- Peer Management Center may conflict a file when an unexpected error occurs, or a file is in an unexpected state.

File retries can occur for any of the following reasons:

- The transfer of a file between locations is interrupted for any reason.
- The renaming of a temp file after a successful file transfer is blocked for any reason.

An example of a file conflict versus a file quarantine is as follows:

Two users have the same file open at two different locations prior to a Peer Global File Service job being enabled. When starting the job, PeerGFS will track this file as a potential conflict. If only one or no users make a change to the file, this conflict will automatically be resolved. If both users make a change, the conflict will become a quarantine.

DFS Namespaces

Debra

Overview

A [DFS namespace](#) enables you to group shared folders that are located on different servers into one or more logically structured namespaces. Each namespace appears to users as a single shared folder with a series of subfolders. However, the underlying structure of the namespace can consist of numerous file shares that are located on different servers and in multiple sites.

The elements that make up a DFS namespace are:

- **Namespace server** - A namespace server hosts a namespace. The namespace server can be a member server or a domain controller.
- **Namespace root** - The namespace root is the starting point of the namespace. For example, if you have a namespace path of `\\Domain.local\MyNamespace`, the root is `MyNamespace`. This is a domain-integrated namespace, meaning that its metadata is stored in Active Directory Domain Services.
- **Folders** (also referred to as **namespace folders**)- Namespace folders without folder targets add structure and hierarchy to the namespace, while folders with folder targets provide users with actual content. When users browse a folder that has folder targets, the client computer receives a referral that transparently redirects the client computer to one of the folder targets.
- **Folder targets** - A folder target is the UNC path of a shared folder or another namespace that is associated with a folder in a namespace. The folder target is where data and content are stored. For example, if a user navigates to `\Domain.local\MyNamespace\MyFolder`, the user is transparently redirected to `\NYC-FS.Domain.local\MyFolder` or `\\LA-FS.Domain.local\MyFolder`, depending on which site the user is currently accessing. Adding multiple folder targets increases the availability of the folder in the namespace.

For more information about DFS namespaces, see [DFS Namespaces overview](#) on Microsoft's website.

Managing DFS Namespaces through PeerGFS

PeerGFS enables you to create a namespace and manage various activities related to it, such as creating namespace folders, adding folder targets, and linking the namespace to a File Collaboration or File Synchronization job. You could manage DFS namespace using Microsoft tools; however, you can manage [DFS namespaces](#) through a dedicated job type in Peer Management Center, the DFS-N Management job.

The benefits of creating and managing a DFS namespace within Peer Management Center are:

- **Ease of managing a namespace** - You can [create](#) and [manage](#) a namespace within the same interface that manages PeerGFS synchronization and replication technologies. This removes the need to use two different tools to manage the key elements of multi-site and multi-vendor file services.
- **Integration with PeerGFS collaboration and synchronization** - [When linked to file collaboration and synchronization jobs](#), DFS namespaces can provide redundancy to file shares across file servers and locations.
- **Automating failover and fallback** - If a file server goes offline, Peer Management Center can disable the associated folder target in the DFS namespace. This automatically redirects users to another available file server. When the original file server comes back, Peer Management Center will automatically make sure it is brought back in sync, and then enable the associated folder target so users can once again connect to it. See [DFS Namespace Failover and Fallback](#) for more information.

Note: Although Microsoft provides two types of namespaces, a stand-alone namespace or a domain-based namespace, you can manage only a domain-based namespace in PeerGFS.

For more information about using DFS namespaces in PeerGFS, see:

- [Using DFS Namespaces with Jobs](#)
- [DFS Namespace Failover and Fallback](#)
- DFS-N Management Jobs
 - [Creating a DFS-N Management Job](#)
 - [Managing DFS Namespaces](#)
 - [Linking a DFS Namespace to File Collaboration or File Synchronization Job](#)

Using DFS Namespaces with Jobs

Debra

If you want to use a DFS namespace with a File Collaboration or File Synchronization job, you can [create a DFS-N Management job](#) to manage the namespace from within PeerGFS.

PeerGFS is very flexible and lets you proceed in various ways. For example:

- You can create a new namespace or import an existing one by first creating a DFS-N Management job and then later [linking the namespace to a File Collaboration or File Synchronization job](#).
- You can create a new namespace or import an existing one when creating a File Collaboration or File Synchronization job, thus automatically linking namespace folder targets to the watchsets of the collaboration or synchronization participants. A DFS-N Management job is automatically created during this process.
- You can also import an existing namespace by right-clicking on the Namespace Summary view which will guide you through the import of a namespace into PeerGFS. [Importing an existing namespace](#) will automatically create a DFS-N Management job which can then be linked to a File Collaboration or File Synchronization job.

Before creating jobs that use namespaces, you may want to [configure DFS preferences](#).

See [Managing DFS Namespaces](#) for information about adding namespace servers, namespace folders, or folder targets to a DFS namespace.

DFS Namespace Failover and Failback

Debra

One of the primary benefits of using DFS Namespaces with PeerGFS is that Peer Management Center can control [failover](#) and [failback](#) by automatically disabling and enabling DFS namespace folder targets.

Failover

Peer Management Center and Agents are constantly looking for connectivity issues and other failures across linked file servers, the Peer Agents themselves, and entire sites. If Peer Management Center detects a failure, Peer Management Center can be set to automatically disable a linked DFS namespace folder target from a namespace folder. This will prevent end users from accessing the associated folder target. For details about enabling and disabling automatic failover to another folder target, see [DFS-N Management](#) in [Collaboration, Replication, and Synchronization Job Preferences](#).

Failback

When Peer Management Center determines that a file server, Peer Agent, or entire site is back online, it automatically runs the following process to re-integrate that file server:

1. Kicks off a rescan to ensure the disconnected site or file server is brought back in sync with the others.
2. Re-enables the associated folder target once the re-scan is complete. Once this is done, DFS Namespaces begins to direct end users back to this file server.

For details about enabling and disabling automatic failback to another folder target, see [DFS-N Management](#) in [Collaboration, Replication, and Synchronization Job Preferences](#). Automatic failback is enabled by default.

Dynamic Storage Utilization

Overview

Dynamic Storage Utilization (DSU) allows you to save storage space on edge storage devices (for example, storage devices used in branch offices) where only a small subset of files are used on a frequent basis. Files that are used less frequently are replaced with stub files on the edge storage device so that it appears to have a complete set of files. When a user accesses a stub file, DSU retrieves the full version of the file from a master storage device. The benefit of using DSU is that it allows you to efficiently utilize storage capacity on edge devices while preserving fast access performance on files that are used most often.

DSU offers flexible edge storage management with:

- The ability to assign an amount or percentage of available storage to be used on the edge storage device.

- Dynamic adjustments of the time periods used to determine whether to stub or rehydrate a file, allowing DSU to keep the assigned storage space as full as possible (best experience for the end user).
- Direct integration with our file collaboration and file synchronization job types.
- Point-to-point data transfer capability between one edge and one or more masters.
- The flexibility to mix and match master and edge roles across different jobs.
- The ability to pin files or folders to always be local or always be stubbed on the edge storage device.
- Alerting to ensure you stay ahead of potential storage capacity limits.

Fundamental Concepts

A master participant has a complete set of hydrated files and no stub files. An edge participant contains a subset of the complete, hydrated files on a master participant, while the rest of the files will be stub files that don't take up any space. Users can retrieve stubbed files directly from a master participant as needed. The goal of dynamic storage utilization (DSU) is to keep as much as possible cached locally on edge participants for rapid access.

Every edge participant must have at least one master participant assigned to it. When a stub file needs to be rehydrated, DSU will retrieve the file from a master participant.

User-defined business rules (volume and utilization policies) manage the storage capacity on edge devices. DSU scans edge participants on a set basis (typically at least once daily) and uses these policies to determine whether adjustments are needed, i.e., whether to stub files to free up space or to rehydrate files. This ensures that the storage capacity is being used at optimum efficiency.

DSU Glossary

This glossary presents some of the most important terms used in conjunction with DSU.

Term	Definition
Stub file	A file that appears to the user to be stored on the local disk and immediately available for use but is actually held either in part or entirely on a different storage medium.

Term	Definition
Local file	A file that is fully available without network access to a master participant; all of its bytes are present (stored locally) on the participant.
Rehydrated file	A file that was stubbed but has been fully reconstituted on the edge participant.
Master participant	Always has a complete set of files for the job. None of its files are stubbed; they are always stored physically on that device.
Edge participant	A subset of the files stored on a master participant are physically stored on an edge participant; the rest of the files on an edge participant are stub files that take up minimal space but can be rehydrated as needed.
Master Data Service	A service that handles requests from edge participants for files on a master participant. The Master Data Service is installed on the Peer Agent server as part of the Peer Agent installation process.
Volume policy	Specifies how much of the available space on the volume monitored by the Agent/edge participant to be assigned for local (hydrated) files.
Temporary storage space	Space that is used to temporarily store the content of stub files that are being rehydrated.
Utilization policy	Defines when a file should be stubbed versus fully hydrated across all volumes of this edge participant. Parameters are based on the size of the files to be potentially stubbed and when they were last accessed and modified. A utilization policy enables you to balance getting the best performance while keeping the cache as full as possible.
Pinning filter	Specifies whether specific files or files in a particular directory are always stubbed or always local on the edge participant. A pinning filter similar is to a utilization policy—it can be applied to multiple jobs. If there is a conflict between a pinning filter and utilization policy (where, for example, you might have something set to be always stubbed), the pinning filter will take precedence.

File Metadata Synchronization

Overview

File metadata is additional information stored as part of a file. The primary component of file metadata is Security Descriptor Information, also known as access control levels (ACLs).

The Security Descriptor Information elements that can be synchronized are:

- **Owner:** NFTS Creator-Owner. By default, the owner is whomever created the object. The owner can modify permissions and give other users the right to take ownership.
- **DACL:** Discretionary Access Control List. It identifies the users and groups that are assigned or denied access permissions to a file or folder.
- **SACL:** System Access Control List. It enables administrators to log attempts to access a secured file or folder and is used for auditing.

File Metadata Conflict Resolution

File metadata conflict resolution occurs only the first time a file is synchronized during the initial scan, and only when one or more security descriptors do not match the designated master host.

If the file does not exist on the designated master host, then no conflict resolution is performed. If a master host is not selected, then no file metadata synchronization is performed during the initial scan.

ACL Requirements

- Enabling ACL synchronization requires that all participants be members of any referenced domains that are configured in the ACL(s) or as the owner of the file. Failure to do so may render the file unreadable on the offending target host.
- All Peer Agents must be run under a domain Administrator account and cannot be run under a local or System account.
- To ensure accurate and consistent ACL propagation, the security settings for the watch set must match EXACTLY across all the participants. The best and easiest way to ensure the security settings match is to compare the permissions in the Microsoft **Advanced Security Settings** dialog for the root folder being watched.


Network of Brokers

The Peer Management Broker is a key technology that is used by PeerGFS to facilitate communication between Agents and the PMC. With the Network of Brokers capability, customers can deploy multiple instances of the Peer Management Broker across their infrastructure to better optimize and control the flow of replication traffic.

For more information on the Network of Brokers capability, please visit: [Getting Started with Network of Brokers](#).

Managing Peer Agents

The ability to remotely manage the configuration for connected [Peer Agents](#) is available from within Peer Management Center. Right-clicking one or more agent names in the **Agents** view displays the following context menu:



Options


Option	Description
Restart Agent Service	<p>Restarts the Peer Agent Windows service running on the corresponding host if the selected Peer Agent is connected. If the Peer Agent is not connected to the Peer Management Broker, an attempt is made to restart the Peer Agent Windows service using the Windows sc command.</p> <p>Note that this works only if the user running the Peer Management Center can access the remote Peer Agent system and has the</p>

Option	Description
	appropriate domain permissions to start and stop services on the remote Peer Agent system.
Remote Desktop to Agent	Launches a Windows Remote Desktop connection to the selected Peer Agent.
Edit Agent Configuration	Displays a dialog through which the selected Peer Agent can be configured. Configurable options include Peer Management Center connectivity, Peer Agent logging, Peer Agent memory usage, among others. For more information, see Editing an Agent Configuration .
Remove Agent	Remove the selected Peer Agent(s) from the Agents view, but if the Peer Agent is still running or connects again, then it will be added back to the list when the next heartbeat is received.
View Properties of Agent	Displays properties for the selected Peer Agent, for example, heartbeat information, host machine configuration, messaging statistics, performance statistics. See Viewing Agent Properties for more details.
Edit Properties of Agent	Allows you to edit the connection type, preferred host, and RDP connection string.
Assign Tags	Displays a dialog where you can view and assign tags to resources.
Technical Support Tools	Displays a list of tools that can be used to assist Peer Software Technical Support.
Test Agent Bandwidth Speed	Runs a bandwidth speed test to be performed in the background if the selected Peer Agent is connected. You are notified at completion with the results of the test.

Option	Description
Transfer Rate Report (not available on Web Client)	(Rich client only) Displays a time series performance chart of average transfer rate for the selected Peer Agent over the last 24 hours.

Technical Support Tools

The options on the **Technical Support Tools** submenu are:

- Run Event Detection Analytics on DGAgent1
-  Retrieve Log Files from DGAgent1
- Open Log Folder for DGAgent1
- Generate Thread Dump File on DGAgent1
- Generate Memory Dump File on DGAgent1
- Memory Garbage Collection on DGAgent1

Command	Description
Run Event Detection Analytics	Runs the Event Detection Analytics tool for the selected job, which looks at real-time activity that has been occurring on that specific agent.
Retrieve Log Files	Retrieves log files for the selected Peer Agent. The log files contain information that the Peer Software Technical Support uses in debugging issues. The log files are encrypted and are located in the support folder of the Peer Management Center installation directory. They can optionally be uploaded to the Technical Support team.
Open Log Folder for Agent	Opens the log folder.
Generate Thread Dump File on Agent	Generates a thread dump file for the selected Peer Agent, which can be used by Peer Software technical support to debug certain issues. The debug file is located in the Peer Agent installation directory.

Command	Description
Generate Memory Dump File on Agent	Generates a memory dump file for the selected Peer Agent, which can be used by Peer Software technical support to debug certain issues. The debug file is located in the Peer Agent installation directory.
Memory Garbage Collection on Agent	Forces a garbage collection operation to attempt to reclaim memory that is no longer used within the Peer Agent's JVM.

Peer Agent Connection Statuses

A connection status indicates the state of the Peer Agent's connection to the Peer Management Broker. The Peer Management Broker serves to connect Peer Agents to Peer Management Center.

Peer Agent connection statuses are displayed in the **Agents** view in the Peer Management Center:

- The status of an Agent is displayed in parentheses after the Agent name.
- The color of an Agent is a visual aid that allows users to quickly identify the status.

Agent can have the following statuses:

Status	Description
Connected	Indicates Peer Agent is currently connected to the Peer Management Broker .
Disconnected	Indicates that Peer Agent has disconnected from the Peer Management Broker. This can be a result of stopping the Peer Agent, or if the network connection between the Peer Agent and the Peer Management Broker was severed.

Status	Description
Pending	This indicates that a heartbeat for the Peer Agent was not received within the configured threshold and that the Peer Agent is in the process on being disconnected if a heartbeat is not received soon. This status can also occur if the Peer Agent does not respond to a pending ping.
Unknown	If no connection status is displayed, then either the Peer Agent was not running on that host when Peer Management Center was started, or the first heartbeat message has not been received from that host.

Re-enabling a Disabled Agent Within a Job

Once disabled within a job, an Agent will not be involved in replication or locking. After the malicious activity that triggered MED is investigated and it is safe to re-enable the afflicted Agent, it will need to be re-enabled on a per job basis.

To review the status of an Agent within a job and to re-enable it, navigate to the **Participants** tab in the job's Runtime Summary view.

If an error is disabled because of a MED action, the message will be similar to the following:

Summary | Session | Event Log | File Conflicts (0) | Alerts (2) | Participants (2) | Configuration

Host Participants

Host	Root Path	Status	State	Message
DellT110a	\\svm9x-1\cifs1\Departments\Sales	Disabled	Disabled	Malicious Event Detection (MED) - Bait File Alert (A
DellT3610b	C:\Departments\Sales			

Participant Details

Host Name: DellT110a

Directory: \\svm9x-1\cifs1\Departments\Sales

Status: Disabled

State: Disabled

Monitoring: false

Message: Malicious Event Detection (MED) - Bait File Alert (Alert and Disable Host: Please check for unwanted activity before re-enabling) Alert Message info=BAIT FILE ALERT appld=113, appSessionId=144 path= See Message Field msg=TriggerAlertFileFound: Path=\\svm9x-1\cifs1\Departments\Sales\pc-med_bin\Doc_001-med.docx - EventName: RENAME details=|Participant Detected=DellT110a|Alert Message=TriggerAlertFileFound: Path=\\svm9x-1\cifs1\Departments\Sales\pc-med_bin\Doc_001-med.docx - EventName: RENAME|Time Detected=Mon Mar 12 19:36:14 EDT 2018|User Detected=MattM|IP Detected=ActiveCounterValue=|Process Detected=SMBVersion=31|Share Detected=cifs1|Job Session ID=3249149797

Status Date: 03-12-2018 19:36:18

Message Date: 03-12-2018 19:36:18

Host Participant State Change Log

Filter by: Host:

Date	Host	Status
03-12-2018 ...	DellT110a	Disabled
03-12-2018 ...	DellT3610b	Not Particip
03-12-2018 ...	DellT110a	Disabled
03-12-2018 ...	DellT110a	Not Particip
03-12-2018 ...	DellT3610b	Not Particip
03-12-2018 ...	DellT3610b	Participatio

Status: ● Halted. (Quorum Lost) Click outside of popup to close

To re-enable the Agent, right-click it within this view, and select **Enable Host Participant**.


Editing an Agent Configuration

The ability to remotely manage the configuration of connected [Peer Agents](#) is available from within Peer Management Center.


Note: For customers using clustered file server roles with Windows Failover Cluster, review this knowledge base article: [Windows Failover Cluster support for the Peer Agent](#). Custom Agent settings must be applied to each potential node in the cluster that may host the Peer Agent. Contact [Peer Software Support](#) for more information.

To edit an Agent's configuration:


1. Right-click the connected Peer Agent in the **Agents** view:



2. Select **Edit Agent Configuration**.
3. If the following dialog appears, Click **OK**:



The **Agent Configuration** dialog appears.



4. Select a page to edit and make the desired changes:

- [Broker](#)
- [General](#)
- [Logging](#)
- [Performance](#)
- [VM Options](#)

5. Click **OK**.

For any configuration change to take effect, the selected Peer Agent must be restarted. If no jobs are running, you will have the option of restarting the Peer Agent at the close of the dialog.

Warning: Changes to any of these options may result in problems when the Peer Agent restarts. Ensure all settings are correct before closing the dialog and restarting the selected Peer Agent.

The settings in **Broker** apply to communication between the selected Peer Agent and Peer Management broker(s) only. It does not apply to communication between Peer Management Center and Peer Management Broker.

Agent Configuration

Broker

WARNING: Changes to these settings may make the Agent unable to start.
These changes will take effect only after the Agent is restarted.

Primary Brokers

Broker Hosts: DGPMC1

Connection Type: ssl

Broker Port: 61617

Failover Brokers

Broker Hosts:

Connection Type: ssl

Broker Port: 61617

Connection Settings

Use Compression

Use Synchronous Sends

Validate TLS Hostname

OK Cancel

Options

Primary Brokers

Options	Description
Broker Hosts	<p>Enter the IP address or fully qualified host name of the server running the primary Peer Management Broker.</p> <p>This option will also accept a comma-separated list of IPs or FQDNs. Agent will connect to any of the primary brokers in the order that they in listed. Agent will try to failover to a primary broker first before trying the failover brokers.</p>

Options	Description
Connecti on Type	Select the type of connection to use when communicating with the primary Peer Management Broker. Types include SSL (encrypted using TLS v1.3 by default) and TCP (not encrypted).
Broker Port	The port on which to communicate with the primary Peer Management Broker.

Failover Brokers

Options	Description
Broker Hosts	<p>Enter the IP address or fully qualified host name of the server running the secondary Peer Management Broker.</p> <p>This option will also accept a comma-separated list of IPs or FQDNs. Agent will connect to any of the failover brokers in the order that they in listed but only after failing to connect to all primary brokers.</p>
Connecti on Type	Select the type of connection to use when communicating with the failover Peer Management Broker. Types include SSL (encrypted using TLS v1.3 by default) and TCP (not encrypted).
Broker Port	The port on which to communicate with the failover Peer Management Broker.


Connection Settings

Option	Description
Use Compre ssion	Enable to compress all communication between the selected Peer Agent and Peer Management Broker(s).
Use Synchro nous Sends	<p>Enable to always send messages from an Agent to Peer Management Broker(s) in synchronous mode. If not enabled, then messages between Agent and Broker(s) will always be sent asynchronously.</p> <p>Note: Enabling this will affect the performance of communication between the Broker(s) and the Agent, especially over connections with high latency.</p>

Option	Description
Validate TLS Hostname	Enable if you are using your own certificates and would like certificate hostnames to be validated between an Agent and Peer Management Broker(s).

The General page has two sets of options:

- [Workspace](#)
- [Location Information](#)



The screenshot shows the 'Agent Configuration' dialog box with the 'General' tab selected. The dialog has a sidebar on the left with the following options: Broker, General (selected), Logging, Performance, and VM Options. The main area is divided into three sections:

- Workspace:** A text field labeled 'Agent Workspace Directory:' containing the value 'workspace'.
- Location Information:** Three text fields: 'Location:' containing 'Centreville, VA, US', 'Longitude:' containing '38.835614202565544', and 'Latitude:' containing '-77.433182073299'.
- Statistics:** Two checked checkboxes: 'Enable Host Statistics' and 'Enable Disk Statistics'.

At the bottom right of the dialog are 'OK' and 'Cancel' buttons.

Options

Workspace

Option	Description
Agent Workspace Directory	Enter the directory where log files and other application data is stored. This path is relative to the Peer Agent's installation directory. It can also be set to an explicit full path.

Location Information

Agent location information is used by [Proactive Monitoring](#). If you change any location values, you must restart the Agent Service.


Option	Description
Location	Enter the city, state, and country where this Agent is located.
Longitude	Enter the longitude coordinates of this Agent.
Latitude	Enter the latitude coordinates of this Agent.

Statistics

These statistics are useful to identify performance bottlenecks. Statistics are collected every 60 seconds and stored in a database that Peer Support can access.

Option	Description
Enable Host Statistics	Select this to collect statistics about network latency, CPU usage, and memory usage.

Option	Description
Enable Disk Statistics	Select this to collect statistics about disk latency. Two key components will be monitored: the workspace folder located in the Agent's installation directory and the watchsets of all jobs tied to that Agent.




Option

Option	Description
Max number of days to keep before archiving	Log files that are older than this date will be relocated automatically to an archive folder, potentially reducing required space on disk. If the default Agent output log files rollover in less than the number of days selected, log bundles sent to Peer Software support may have gaps.

The **Performance** page offers control over settings that affect Agent performance. This page has two sets of options:

- [Network Tuning](#) - These settings control the number of parallel streams of data that can be sent between the Agent and the Broker. In active, latent environments, adjusting these settings can improve performance or limit the data throughput between the Agent and the Broker.
- [Processor Affinity](#) - Allows you to specify the number of processors that the Agent should use.



Options

Network Tuning


Field	Description
Auto Calculate Data Streams	Select this checkbox if you want the number of blob command threads to be calculated rather than using the value in the Parallel Data Streams field. The optimum number of Agent parallel data streams is calculated based on network performance, using the value of Bandwidth to Broker (Mbps) in the calculation along with latency between the Broker and Agent.
Bandwidth to Broker (Mbps)	Enter the bandwidth in megabits per second that you want to use for the connection between the Agent and Peer Management Broker. The default value is -1, which means use all available bandwidth.

Field	Description
Parallel Data Streams	<p>Enter the maximum number of threads to handle data transfer between each Agent and the Peer Management Broker. Increasing this typically improves replication performance but also increases memory consumption.</p> <p>The default value is 4. The minimum is 1; the maximum is 100.</p>
Outstanding Data Packets	<p>Modify this setting only at the instruction of the Peer Software Technical Support Team as it can lead to increased memory consumption.</p> <p>Enter the maximum number of blocks of data to be buffered to be sent to the Agent. The default number is 8; the maximum size is 100.</p>

Processor Affinity

Field	Description
Max Number of Processors to Use (x available)	<p>Enter the number of processors that the Agent process can use on the server where it is installed. This number should be less than or equal to the number of processors available on the server.</p> <p>The default value is -1, which means use all available processors.</p>

The option on the page allows you to tune the maximum amount of system memory that the Peer Agent service will use on the server where it is installed. If you change the value, you must restart the Agent Service.



Options


Field	Description
Maximum Agent Memory (in MB)	Enter the maximum amount of memory in megabytes that the JVM portion of the Agent service can use. We recommend a minimum value of 2048 MB on 64-bit Agent servers with a recommended maximum of 16384 MB. We strongly recommend that this value be set to no lower than 2 GB.

Viewing Agent Properties

To view the properties of an Agent:

1. Right-click the Agent in the **Agents** view.
2. Select **View Properties**.

The **View Agent Properties** dialog opens.




This dialog displays Peer Agent and host machine information across the following tabs:

Tab	Description
General	Displays general Peer Agent run-time information such as discovery time, local time, TLS use, Peer Agent start up time, Peer Agent version, and the user name Peer Agent service is running as.

Tab	Description
Hear tbeat	Displays heartbeat information and statistics such as heartbeat frequency, average heartbeat time, last heartbeat time, total Peer Agent disconnects, total missing heartbeats.
Mach ine	Displays machine information of the host that the Peer Agent is running on such as number of processors, computer name, domain name, IP address, installed memory, O/S.
Mess agin g	Displays general Peer Management Center Broker messaging statistics for the selected host, such as total messages received, total messages sent, # errors.
Perf orma nce	Displays general performance statistics for the underlying host machine such as available virtual memory, available physical memory, memory load.
JVM Perf orma nce	Displays JVM performance statistics for the running Peer Agent application such as active number of threads, heap memory used, non-heap memory used.

Editing Agent Properties

Selecting **Edit Properties** menu item for a selected agent will result in the opening of the following Peer Agent **Properties** dialog:



This dialog displays the following configurable Peer Agent and host machine options:

Option	Description
Connection Type	Allows for the selection of a connection type between the selected Peer Agent and the associated Peer Management Broker. When set, optimizations are made to the communication between the two parties based on the selected connection type.
Preferred Host	A best practice optimization for selecting which Peer Agent has the fastest connection to the Peer Management Broker (or in appropriate cases, for selecting which Peer Agent are on the same subnet as the Peer Management Broker).
RDP Connection String	The connection string to use when activating a Remote Desktop Protocol (RDP) session to this Peer Agent.

Updating a Peer Agent

If the Peer Agent software running on a host is out of date, the host is shown as having a pending update in the [Agents view](#).

When right-clicking the host, the option to automatically update the Peer Agent software is also available. This process can be done from Peer Management Center and usually does not require any additional actions on the host server itself.

PeerGFS API

The PeerGFS API is a RESTful API. It allows system administrators to monitor PeerGFS activity and developers to integrate PeerGFS functionality into their own application.

Currently, the API allows users to:

- Get information about running jobs, such as open files as well as files in the process of being synchronized; statistical info about watch set, queue sizes, replication metrics; scan status, alerts, and quarantined files.
- Start and stop jobs.
- View and restart agents.
- View scheduled tasks.
- Trigger log uploads.

Additional functionality, such as the ability to create and edit jobs, will be provided in future versions of the API.

Accessing the PeerGFS API

Access to the PeerGFS API is available as a combination of two elements:

- A web URL hosted by the API service. This URL is defined as a combination of a PMC server name or IP and a port, as specified by the [Web and API Configuration](#) settings in [Preferences](#).


- Local (aka basic) authentication with a user name and password that is passed into a script or the API web interface. This user name and password is used to authenticate the user with the PeerGFS API service.

If you are authenticated, you are authorized to access the entire API. Role-based access will be added in future versions of the API.

Testing the PeerGFS API

One way to test the PeerGFS API is to use the API web interface.

To access the web interface, open a browser, go to the API endpoint (e.g., `https://<PMC IP or name> or <8442>`), and try the API calls.



Integrating Your Own Tools and Scripts with the PeerGFS API

The PeerGFS installation folder contains PowerShell and Bash toolkits in the **tools** subfolder of the PMC's installation folder. If you need a different language, contact support@peersoftware.com for our latest YAML file.

If you would like to access the API through a client in a language other than PowerShell or BASH, you can use the Swagger Editor to convert our YAML file to the appropriate client code:

1. Save the PeerGFS YAML file to your desktop.
2. Open a web browser tab and point it to <https://editor.swagger.io/#/>.
3. Go to the **File** menu inside the web interface, and then select **Import file**.
4. Select the PeerGFS YAML file on the desktop.

The manifest should appear on the left with the front-end mockup on the right.

5. Use the Swagger Editor to generate client code.

API Quick Reference

The PeerGFS API REST specifications are documented using OpenAPI (also known as Swagger). This documentation is visible via the PMC API's web interface. To access the web interface, see [Testing the PeerGFS API](#).

Within the API web interface, you can also send test requests and view responses as well as see REST calls that can be made to the API service.

The PeerGFS is divided into four types of API calls:

- Jobs - Generic job-related calls
- Jobs-File - Job-specific calls
- Agents - Agent-related calls
- PMC - Calls related to alerts, tasks, and logs

The PeerGFS API has three status codes:

200 - Success

401 - Unauthorized

404 - Job(s) not found

Scheduled Replication

Scheduled replication is a feature that allows you to delay replication of certain file and folders, allowing you to manage bandwidth and prioritize the replication of critical data in real-time. By using scheduled replication, you can reduce the impact of replication on network bandwidth and ensure that critical data is replicated in real-time while less critical data is replicated on a schedule that makes sense for your organization. This can help to ensure that your data replication processes are efficient and effective, and that your network resources are being used as efficiently as possible.

To use scheduled replication, you create a **scheduled replication filter** that identifies the files and folders you want to replicate at a later time. The filter is based on file type. Once the filter is applied to a job, any files or folders that meet the criteria will be queued for replication at a scheduled time or interval that you specify.

Scheduled replication filters can be used with file collaboration, file replication, and file synchronization jobs. For information on defining a scheduled replication filter, see [Scheduled Replication Filters](#) in [Preferences](#).

Note: When a scheduled replication filter is used in a file collaboration job, files that meet the filter criteria will not be locked.

Smart Data Seeding

Overview

Smart data seeding applies to File Collaboration, File Replication, and File Synchronization jobs.

Occasionally, a new host or a host which has been removed from the session for a long time, needs to be introduced into an existing collaboration. Smart Data Seeding supports integrating new hosts into a collaboration seamlessly. Conventional seeding methods take a long time over typically slow WAN connections and require a cut-over with a final scan to get the data synchronized. With Smart Data Seeding's default settings, real-time events are processed from

the Smart Data Seeding hosts while the initial one-way background scan ensures the target(s) have all the files in place.

Smart Data Seeding provides the ability to set one or more participants in a Smart Data Seeding mode. Smart Data Seeding hosts are considered the hosts from where files will be copied to all the other participants in the session. When a host is in Smart Data Seeding mode, it follows the rules of the job's Smart Data Seeding Mode configuration (see below). Initial scans run in a one-way mode to avoid bringing back deleted files. It is not recommended to have active ([Active-Active](#)) users on the target hosts. Once the initial scan is completed, the Smart Data Seeding host(s) are set back to their default full collaboration mode with no user interaction or final scan.

To enable advanced settings in the Conflict Resolution window, add the following fc.ini option and restart Peer Management Center:

```
fc.scan.enable.preseeding.ui=true
```

Smart Data Seeding Options

From the **Conflict Resolution** window, select from one of the following Smart Data Seeding modes:

Mode	Description
PASSIVE (Default)	Initial scan will be one-way only with any host in Smart Data Seeding mode: <ul style="list-style-type: none"> • Real-time activity on Smart Data Seeding host is disabled. • Real-time events on that host will be quarantined. • Renamed files will be restored.
PASSIVE_WITH_RESTORE	Initial scan will be one-way only with any host in Smart Data Seeding mode: <ul style="list-style-type: none"> • Real-time activity on Smart Data Seeding host is disabled. • Any activity on that host will be restored to its original state.
ACTIVE_LIMITED	Initial scan will be one-way only with any host in Smart Data Seeding mode: <ul style="list-style-type: none"> • Real-time activity on Smart Data Seeding host is enabled in a limited mode (real-time file adds are processed).

Mode	Description
	<ul style="list-style-type: none"> • Unsynchronized file updates will be quarantined. • Unsynchronized file renamed will be restored. • Unsynchronized file deletes will be restored.
ACTIVE_FULL	<p>Initial scan will be one-way only with any host in Smart Data Seeding mode except for updates (updates will be processed as Latest Modified wins):</p> <ul style="list-style-type: none"> • Real-time activity on Smart Data Seeding host is enabled with latest modified file wins, regardless of whether the latest file is on the Smart Data Seeding host.
REACTIVATION	<p>Initial Scan will be one-way only with any host in Smart Data Seeding mode:</p> <ul style="list-style-type: none"> • Real-time activity on Smart Data Seeding host is enabled with Quarantine (Added and Updated Files will be quarantined during the scan). • Unsynchronized file updates will be quarantined during real-time. • Unsynchronized file renames will be restored. • Unsynchronized deletes will be restored.

The default setting is `ACTIVE_LIMITED`, which will initiate a one-way scan with any host in Smart Data Seeding mode. During the scan, new files will be deleted, newer files will be overwritten, and deleted files will be restored on the Target(s). During real-time activity, add events will be processed, but updates will be quarantined if the files are unsynchronized. Renames and deletes will be restored if the files are unsynchronized.

The `ACTIVE_LIMITED` setting is recommended in most cases in which a new host or a host which has been removed from the session for a long time needs to be introduced into an existing collaboration.

Storage Capacity

The storage capacity available for your jobs is based on your Peer Global File Service [license](#). Automated alerts will notify you when you close to reaching your licensed storage capacity. If you exceed your licensed storage capacity, contact your Peer Software sales representative.

Total capacity consumed is defined by the total number of unique TBs under management across all participants rather than the total capacity used by all participants. In this unique TB model, a 1 TB file that is synchronized across 10 participants only counts as 1 TB and not 10 TBs. For example, if your licensed storage capacity is 100 TB and you have a job with 5 participants totaling 20 unique TBs, you have used total of 20% of your storage capacity, not 100%.

TLS Certificates

You can use custom or private Transport Layer Security (TLS) certificates to connect a Peer Agent to Peer Management Broker. The Keytool certificate management utility will be used to store the key and certificate into a keystore file, which protects the private keys with a password.

Note the paths in the following topics reference a default install directory for both Peer Management Center and Peer Agent.

For step-by-step instructions, see:

- [Creating New Certificates](#)
- [Using Existing Certificates](#)

For additional information, please contact Peer Software's support team via email: support@peersoftware.com.

Creating New Certificates

Keytool Utility

Perform the necessary commands using the Keytool certificate management utility bundled with your Peer Management Center or Peer Agent installation. The location of the utility is:

- Peer Management Center system: `PMC_INSTALLATION_FOLDER\jre\bin`

- Peer Agent system: PEER_AGENT_INSTALLATION_FOLDER\jre\bin

Broker Keystore Generation

Step 1. Using the Keytool utility, create a certificate for Peer Management Center.

```
keytool -genkey -alias broker -keyalg RSA -keystore broker.ks -storepass plBroker4321 -validity 3000
```

broker	The alias of the new broker keystore containing the new certificate.
broker.ks	Destination broker keystore that will be created containing the new certificate.
plBroker4321	The password you assign to the new broker keystore.

Note: The broker.ks file will be created in the \jre\bin folder.

Example:

```
C:\Program Files\Peer Software\File Collaboration Enterprise\jre\bin>keytool -genkey -alias
broker -keyalg RSA -keystore broker.ks -storepass plBroker4321 -validity 3000
What is your first and last name?
[Unknown]: Monika Cuellar
What is the name of your organizational unit?
[Unknown]: Peer Software, Inc.
What is the name of your organization?
[Unknown]: Peer Software, Inc.
What is the name of your City or Locality?
[Unknown]: Centreville
What is the name of your State or Province?
[Unknown]: VA
What is the two-letter country code for this unit?
[Unknown]: US
Is CN=Monika Cuellar, OU="Peer Software, Inc.", O="Peer Software, Inc.", L=Centreville,
ST=VA, C=US
correct?
[no]: yes

Enter key password for <broker>
(RETURN if same as keystore password):

C:\Program Files\Peer Software\File Collaboration Enterprise\jre\bin>
```

Step 2: Export the broker's certificate so it can be shared with clients.

```
keytool -export -alias broker -keystore broker.ks -file broker.cer
```

broker	The alias of the new broker keystore containing the new certificate.
broker.ks	Destination broker keystore that will be created containing the new certificate.
broker.cer	The name of the broker's certificate to be created.

Note: The broker.cer file will be created in the \jre\bin folder.

Example:

```
C:\Program Files\Peer Software\File Collaboration Enterprise\jre\bin>keytool -export -alias
broker -keystore broker.ks -file broker.cer
Enter keystore password: plBroker4321
Certificate stored in file <broker.cer>

C:\Program Files\Peer Software\File Collaboration Enterprise\jre\bin>
```

Step 3: Create a certificate/keystore for the client.

```
keytool -genkey -alias client -keyalg RSA -keystore client.ks -storepass
plClient4321 -validity 3000
```

client	The alias of the new client keystore containing the new certificate.
client.ks	Destination keystore for the client that will be created containing the new certificate.
plClient4321	The password you assign to the new client keystore.

Note: The client.ks file will be created in the \jre\bin folder.

Example:


```

C:\Program Files\Peer Software\File Collaboration Enterprise\jre\bin>keytool -genkey -alias
client -keyalg RSA -keystore client.ks -storepass plClient4321 -validity 3000
What is your first and last name?
[Unknown]: Monika Cuellar
What is the name of your organizational unit?
[Unknown]: Peer Software, Inc.
What is the name of your organization?
[Unknown]: Peer Software, Inc.
What is the name of your City or Locality?
[Unknown]: Centreville
What is the name of your State or Province?
[Unknown]: VA
What is the two-letter country code for this unit?
[Unknown]: US
Is CN=Monika Cuellar, OU="Peer Software, Inc.", O="Peer Software, Inc.", L=Centreville, ST=VA,
C=US
correct?
[no]: yes

Enter key password for <client>
(RETURN if same as keystore password):

C:\Program Files\Peer Software\File Collaboration Enterprise\jre\bin>

```

Step 4: Create a truststore for the client and then import the broker's certificate. This establishes that the client "trusts" the broker.

```
keytool -import -alias broker -keystore client.ts -file broker.cer -
storepass plClient4321
```

broker	The alias of the broker keystore created in step 1.
client.ts	Destination truststore for the client that will be created containing the broker's certificate.
broker.cer	The broker's certificate created in step 2.
plClient4321	The password assigned to the client keystore in Step 3.

Example:

```
C:\Program Files\Peer Software\File Collaboration Enterprise\jre\bin>keytool -import -alias
broker -keystore client.ts -file broker.cer -storepass plClient4321
Owner: CN=Monika Cuellar, OU="Peer Software, Inc.", O="Peer Software, Inc.", L=Centreville,
ST=VA, C
=US
Issuer: CN=Monika Cuellar, OU="Peer Software, Inc.", O="Peer Software, Inc.", L=Centreville,
ST=VA,
C=US
Serial number: 4fa7f34f
Valid from: Mon May 07 12:07:43 EDT 2012 until: Fri Jul 24 12:07:43 EDT 2020
Certificate fingerprints:
    MD5:  2C:18:DD:B5:CD:C5:3D:B2:9B:E3:93:50:D6:74:2B:64
    SHA1: 30:77:94:9B:34:63:6C:DE:2C:98:9C:00:C2:B9:F6:21:AE:22:D7:DE
Trust this certificate? [no]: yes
Certificate was added to keystore

C:\Program Files\Peer Software\File Collaboration Enterprise\jre\bin>
```

Optional: List the certificates in the broker keystore.

```
keytool -list -v -keystore broker.ks -storepass plBroker4321
```

Example:

```
C:\Program Files\Peer Software\File Collaboration Enterprise\jre\bin>keytool -list -v -
keystore broker.ks -storepass plBroker4321

Keystore type: jks
Keystore provider: SUN

Your keystore contains 1 entry

Alias name: broker
Creation date: May 7, 2012
Entry type: keyEntry
Certificate chain length: 1
Certificate [1]:
Owner: CN=Monika Cuellar, OU="Peer Software, Inc.", O="Peer Software, Inc.", L=Centreville,
ST=VA, C=US
Issuer: CN=Monika Cuellar, OU="Peer Software, Inc.", O="Peer Software, Inc.", L=Centreville,
ST=VA, C=US
Serial number: 4fa7f34f
Valid from: Mon May 07 12:07:43 EDT 2012 until: Fri Jul 24 12:07:43 EDT 2020
Certificate fingerprints:
    MD5:  2C:18:DD:B5:CD:C5:3D:B2:9B:E3:93:50:D6:74:2B:64
    SHA1: 30:77:94:9B:34:63:6C:DE:2C:98:9C:00:C2:B9:F6:21:AE:22:D7:DE

*****
*****

C:\Program Files\Peer Software\File Collaboration Enterprise\jre\bin>
```

Verify Client Certificate

If you want to verify client certificates, you need to take a few extra steps.

Step 1: Export the client's certificate so it can be shared with broker.

```
keytool -export -alias client -keystore client.ks -file client.cer -  
storepass plClient4321
```

Note: The client.cer file will be created in the \jre\bin folder.

Example:

```
C:\Program Files\Peer Software\File Collaboration Enterprise\jre\bin>keytool -export -alias  
client -keystore client.ks -file client.cer -storepass plClient4321  
Certificate stored in file <client.cer>  
  
C:\Program Files\Peer Software\File Collaboration Enterprise\jre\bin>
```

Step 2: Create a truststore for the broker and import the client's certificate. This establishes that the broker "trusts" the client:

```
keytool -import -alias client -keystore broker.ts -file client.cer -  
storepass plBroker4321
```

Example:

```
C:\Program Files\Peer Software\File Collaboration Enterprise\jre\bin>keytool -import -alias  
client -keystore broker.tx -file client.cer -storepass plBroker4321  
Owner: CN=Monika Cuellar, OU="Peer Software, Inc.", O="Peer Software, Inc.", L=Centreville,  
ST=VA, C  
=US  
Issuer: CN=Monika Cuellar, OU="Peer Software, Inc.", O="Peer Software, Inc.", L=Centreville,  
ST=VA,  
C=US  
Serial number: 4fa7f982  
Valid from: Mon May 07 12:34:10 EDT 2012 until: Fri Jul 24 12:34:10 EDT 2020  
Certificate fingerprints:  
MD5: A7:D9:6E:78:8B:A9:AD:32:96:2D:51:6B:53:0B:E4:BD  
SHA1: 16:05:7C:C4:D5:AB:E7:D3:7D:5B:2E:02:B5:3B:69:54:D1:C3:53:52  
Trust this certificate? [no]: yes  
Certificate was added to keystore  
  
C:\Program Files\Peer Software\File Collaboration Enterprise\jre\bin>
```

Optional: List the certificates in the client keystore.

```
keytool -list -v -keystore client.ks -storepass plClient4321
```

Example:

```
C:\Program Files\Peer Software\File Collaboration Enterprise\jre\bin>keytool -list -v -
keystore client.ks -storepass plClient4321

Keystore type: jks
Keystore provider: SUN

Your keystore contains 1 entry

Alias name: client
Creation date: May 7, 2012
Entry type: keyEntry
Certificate chain length: 1
Certificate[1]:
Owner: CN=Monika Cuellar, OU="Peer Software, Inc.", O="Peer Software, Inc.", L=Centreville,
ST=NY,
C=US
Issuer: CN=Monika Cuellar, OU="Peer Software, Inc.", O="Peer Software, Inc.", L=Centreville,
ST=NY,
C=US
Serial number: 4fa80618
Valid from: Mon May 07 13:27:52 EDT 2012 until: Fri Jul 24 13:27:52 EDT 2020
Certificate fingerprints:
    MD5: 06:11:97:71:D6:23:91:63:2F:19:F4:05:EA:2F:9D:14
    SHA1: A7:26:80:9E:18:2B:46:8E:92:BB:AD:89:44:0A:8A:9C:8C:1F:62:38

*****
*****

C:\Program Files\Peer Software\File Collaboration Enterprise\jre\bin>
```

Copy the Generated Keystore Files into Their Appropriate Location

On the Peer Management Center system: Copy the following files from the "C:\Program Files\Peer Software\Peer Management Hub\jre\bin" directory into the "C:\Program Files\Peer Software\Peer Management Hub\Broker\keys" directory on the Peer Management Center system. Overwrite the existing files.

broker.ks

broker.ts

On the Peer Agent system: Copy the following files from the "C:\Program Files\Peer Software\Peer Management Hub\jre\bin" directory into the "C:\Program Files\Peer Software\Peer Agent\keys" directory on the Peer Agent systems. Overwrite the existing files.

client.ks

client.ts

Restart All Peer Management Center Services for the Changes to Take Effect

We recommend you create a folder outside the Peer Management Center/Peer Agent installation directories in which to store the keystore files. This will ensure that upgrades will not clear/overwrite these files. The steps outlining this process will be posted shortly.

Using Existing Certificates

Keytool Utility

Perform the necessary commands using the Keytool certificate management utility bundled with your Peer Management Center or Peer Agent installation. The location of the utility is:

- Peer Management Center system: PMC_INSTALLATION_FOLDER\jre\bin
- Peer Agent system: PEER_AGENT_INSTALLATION_FOLDER\jre\bin

Peer Management Broker and Peer Agent Keystore Generation

You will need to have two custom/private certificates. One for the Peer Management Broker and one for all the participating Peer Agents. You may select different algorithms and encryption key size (e.g., RSA, DSA with 1024 or 2048 key size).

Step 1. Using the Keytool utility, list the contents of the custom/private certificates. Perform these steps for both certificates (Peer Management Broker and Peer Agent. Make a note of the Alias of the certificate, if it exists.

```
keytool -list -v -keystore HubCert.pfx -storetype pkcs12
```

HubCert.pfx	Represents the custom/private certificate for Peer Management Center Broker.
AgentCertificate.pfx	Represents the custom/private certificate for the Peer Agents.

Note: The command will prompt you to enter the password you set on your custom certificate, if applicable.

Step 2. Add the custom/private Peer Management Center Broker certificate into the Peer Management Center Broker keystore.

```
keytool -importkeystore -deststorepass plBroker4321 -destkeypass
plBroker4321 -destkeystore broker.ks -srckeystore HubCert.pfx -
srcstoretype PKCS12 -srcstorepass PASSWORD -alias ALIAS -destalias broker
```

plBroker4321	The password you assign to the new Broker keystore.
broker.ks	Destination keystore that will be created containing the custom/private certificate.
HubCert.pfx	Custom/private certificate being imported into the new keystore.
PASSWORD	The password of the custom/private certificate, if it exists. If you omit the -srcstorepass command, you will be prompted for the certificate password if needed.
ALIAS	The Alias of the custom/private certificate you discovered in Step 1 above.
broker	The Alias of the new keystore containing the custom/private.

Note: The broker.cer and broker.ks files will be created in the \jre\bin folder where the keytool utility resides.

Step 3. Add the custom/private Peer Agent certificate into the Client keystore.

```
keytool -importkeystore -deststorepass plClient4321 -destkeypass
plClient4321 -destkeystore client.ks -srckeystore AgentCert.pfx -
srcstoretype PKCS12 -srcstorepass PASSWORD -alias ALIAS -destalias client
```

plClient4321	The password you assign to the new Broker keystore.
client.ks	Destination keystore that will be created containing the custom/private certificate.
AgentCertificate.pfx	Custom/private certificate being imported into the new keystore.
PASSWORD	The password of the custom/private certificate, if it exists. If you omit the <code>-srcstorepass</code> command, you will be prompted for the certificate password if needed.
ALIAS	The Alias of the custom/private certificate you discovered in Step 1 above.
client	The Alias of the new keystore containing the custom/private.

Note: The `client.cer` and `client.ks` files will be created in the `\jre\bin` folder where the `keytool` utility resides.

Step 4. Export the broker's certificate so it can be shared with clients.

```
keytool -export -alias broker -keystore broker.ks -file broker.cer
```

broker	The Alias of the broker keystore containing the custom/private certificate created in Step 2 above.
broker.ks	The keystore file created in Step 2 above containing the custom/private certificate for the Broker.
broker.cer	The certificate file created in Step 2 above.

The command will prompt you to enter the password for the broker keystore (e.g., `plBroker4321`).

Step 5. Export the client's certificate so it can be shared with broker.

```
keytool -export -alias client -keystore client.ks -file client.cer
```

client	The Alias of the client keystore containing the custom/private certificate created in Step 3 above.
client.ks	The keystore file created in Step 3 above containing the custom/private certificate for the Peer Agents.
client.cer	The certificate file created in Step 3 above.

The command will prompt you to enter the password for the client keystore (e.g., plClient4321).

Step 6. Create a truststore for the broker and import the client's certificate. This establishes that the broker "trusts" the client:

```
keytool -import -alias client -keystore broker.ts -file client.cer
```

client	The Alias of the client keystore containing the custom/private certificate created in Step 3 above.
broker.ts	The broker trust store to be created.
client.cer	The certificate file created in Step 3 above.

The command will prompt you to enter the password for the broker keystore (e.g., plBroker4321).

Step 7. Create a truststore for the client and import the broker's certificate. This establishes that the client "trusts" the broker.

```
keytool -import -alias broker -keystore client.ts -file broker.cer
```


broker	The Alias of the client keystore containing the custom/private certificate created in Step 3 above.
client.ts	The client truststore to be created.
client.cer	The certificate file created in Step 2 above.

The command will prompt you to enter the password for the client keystore (e.g., pIClient4321).

Copy the Generated Keystore Files into Their Appropriate Location

On the Peer Management Center system:

Copy the following files from the **Peer Management Center_INSTALLATION_FOLDER\jre\bin** directory into **the Peer Management Center_INSTALLATION_FOLDER\Broker\keys** directory on the Peer Management Center system. Overwrite the existing files.

broker.ks

broker.ts

On the Peer Agent system:

Copy the following files from **Peer Management Center_INSTALLATION_FOLDER\jre\bin** directory into the **PEER_AGENT_INSTALLATION_FOLDER\keys** directory on the Peer Agent systems. Overwrite the existing files.

client.ks


client.ts

Restart All Peer Management Center Services for the Changes to Take Effect

We recommend you create a folder outside the Peer Management Center/Peer Agent installation directories in which to store the keystore files. This will ensure that upgrades will not clear/overwrite these files.

Preferences

The **Preferences** dialog enables you to configure global settings, as well as settings specific to a job type. Before creating any jobs or configuring individual aspects of a job, Peer Software recommends first configuring a number of settings. Some settings are global and apply program-wide and/or to all job types; others are specific to a job type.



Configuring Global Settings

Peer Software strongly recommends configuring the following settings before creating any jobs:

- [Email Configuration](#)
- Contacts and Distribution Lists
- System Alerts

Modify other global settings as needed. You may want to consult with Peer Software Technical Support when modifying the other global settings.

Configuring Job Type Specific Settings


Job Type	Setting
Cloud Backup and Replication	<ul style="list-style-type: none">• Email Alerts• File and Folder Filters• Proxy Configuration.
File Collaboration, File Replication, and File Synchronization	<ul style="list-style-type: none">• Email Alerts• File and Folder Filters
DFS-N Management	<ul style="list-style-type: none">• Email Alerts• File and Folder Filters

Configuring Preferences

To modify settings:

1. Click a category on the left to see its corresponding options appear on the right side of the dialog.

For example, click the **General Configuration** category to view and configure general program-wide settings.



2. Make as many changes as you like to the category settings, and then click:
 - **Apply and Close** to save the new settings and return to the program.
 - **Cancel** to close the dialog without saving your changes.
 - **Apply** to save your changes and keep the **Preferences** dialog open.

Analytics Preferences


The **Analytics Preferences** page allows you to enable and disable the Analytics settings.

For information about Analytics, see [Analytics](#) in [Advanced Topics](#).

To modify Analytics settings:

1. Select **Preferences** from the **Window** menu.

2. Select **Analytics** in the navigation tree.




3. Select options as needed.

Option	Description
Enable the sending of analytics data to the Peer Analytics VM	Select this option to enable the flow of PeerGFS telemetry to PeerIQ. PeerIQ, a virtual appliance based analytics engine, offers a new set of dashboards to system administrators for monitoring the health and performance of PeerGFS and the replication environment.
Share anonymous diagnostic data with Peer Software	Select this option to share anonymous diagnostic information with Peer Software. This information will help us improve PeerGFS. No customer-identifiable information is sent. More details can be found in our knowledge base.

4. Click **Apply and Close** or **Apply**.

Proactive Monitoring Preferences



Cloud Backup and Replication Job Preferences

You can modify the following Cloud Backup and Replication settings:

- [Cloud Backup and Replication](#)
- [Database Connections](#)


- [Destination Credentials](#)
- [Email Alerts](#)
- [File Retries and Source Snapshots](#)
- [File and Folder Filters](#)
- [Performance](#)
- [Proxy Configuration](#)
- [Replication and Retention Policies](#)
- [SNMP Notifications](#)
- [Scan Manager](#)

Cloud Backup and Replication

Cloud Backup and Replication settings control the overall performance of all Cloud Backup and Replication jobs.

To modify these settings:

1. Select **Preferences** from the **Window** menu.
2. Select **Cloud Backup and Replication** in the navigation tree.



3. Modify the settings as needed.

Automatic Reporting Interval (Seconds)	Each Peer Agent automatically reports its statistics to Peer Management Center at regular intervals. Select the number of seconds between these intervals. The default is 10 seconds.
Show Volumes in Jobs View	Select this checkbox if you want volumes to be displayed in the Jobs view.
24-hour format	Select this checkbox if you want times to be displayed in a 24-hour format rather than a 12-hour format.
Hide Internal Volumes	Select this checkbox if you don't want internal volumes displayed when choosing which volumes to replicate.

4. Click **Apply and Close** or **Apply**.

Database Connections

Cloud Backup and Replication uses a Microsoft SQL Server or SQL Server Express database to track files and folders that have been replicated, individual file versions, and snapshots. When creating a Cloud Backup and Replication job, the Management Agent that you select for the job

Create Database Connection

Configure connection information for MS SQL Server.

*Database Connection Name:

*Management Agent:

*DB Host Name:

Port:

Instance Name:

*Database Name:

Authentication: Integrated Credentials

Username:

Password:


4. Enter the required values.

Field	Description
Database Connection Name	Enter a name for this database connection.
Management Agent	Select the Management Agent that will use this connection. The Agent must be the same one as managing the job.
DB Host Name	Enter the name of the SQL Server hosting the database. If the database is installed on the Agent server itself, enter the name of the Agent server.

Field	Description
Port	Optional. Enter the port to be used to communicate with the specified SQL Server. If not defined, the connection defaults to port 1433.
Instance Name	Optional. Enter the database instance name to use on the specified SQL Server. If no named instances are installed on the specified SQL Server, leave this blank.
Database Name	Enter the name of the database that Cloud Backup and Replication will create. The default name is <i>peercloud</i> , but it can be changed to a name that follows your company's naming conventions.
Authentication	Select Integrated if the Agent service account is granted admin rights on the selected SQL instance. Otherwise, select Credentials to enter the user name and password of a database administrator.
Username	Required when Credentials is selected for Authentication . Enter the user name of an account to be used to connect to the database. This can be a locally defined account such as "sa" or a domain account. The account must have adequate privileges to manage the database, such as database owner.
Password	Required when Credentials is selected for Authentication . Enter the password for account being used to connect to the database.

5. Click **Validate** to test the connection, and then click **OK** in the confirmation message that appears.
6. Click **OK** to close the dialog.

The new database connection is listed in the **Database Connections** table.



7. Click **Apply and Close** or **Apply**.


Destination Credentials

When you create a Cloud Backup and Replication job, you can select existing destination storage account credentials to apply to the job or you can create new credentials and apply them to the job. This [Preferences](#) page lists the existing credentials. From this page, you can view, create, edit, and delete credentials. However, you cannot edit or delete credentials while they are applied to a job.

To create new destination storage account credentials:

1. Select **Preferences** from the **Window** menu.
2. Expand **Cloud Backup and Replication** in the navigation tree, and then select **Destination Credentials**.

Any existing credentials are listed in the **Destination Credentials** table.



3. Click the **Create** button.

The **Storage Account** dialog appears.

Create Destination Credentials

Platform:

- Microsoft Azure Blob Storage
- Amazon S3
- NetApp StorageGRID
- Nutanix Objects
- S3 Compatible
- File System

*Description:

*Account:

*Shared Key: Show Key

*Endpoint Type: ▾

Use SSL

OK Cancel

4. Enter the required values. For information about the required values, see [Step 8: Destination Credentials](#) in [Creating a Cloud Backup and Replication Job](#).
5. Click **OK**.

The new credential is listed in the **Destination Credentials** table and can now be applied to jobs.

6. Click **Apply and Close** or **Apply**.

Email Alerts


When you create a job, you can select existing email alerts to apply to the job or you can create new email alerts and apply them to the job. This [Preferences](#) page lists the existing email alerts. From this page, you can view, create, edit, and delete email alerts. However, you cannot edit or delete an email alert while it is applied to a job. See [Email Alerts](#) in the [Basic Concepts](#) section for more information about email alerts.

Note: An SMTP email connection must be configured before email alerts can be sent. See [Email Configuration](#) for information about configuring SMTP email settings.

To create an email alert:

1. Select **Preferences** from the **Window** menu.
2. Expand **Cloud Backup and Replication** in the navigation tree, and then select **Email Alerts**.

Any existing Cloud Backup and Replication email alerts are listed in the **Email Alerts** table.



3. Click the **Create** button.

The **Create Email Alert** dialog appears.

Create Email Alert

Name:

Temporarily Disable

Event Types

Job Start Job Stop Job Failure Participant Failure

System Event Malicious Event

Report Types

Scan Destination Snapshot

Recipients

Enter email, contact, or distribution list:

Recipients:

4. Enter a name for the alert.
5. Select the event types to be alerted.

The event type determines what will trigger the email alert to be sent.

Event Type	Description
Job Start	Sends an alert when the job starts.
Job Stop	Sends an alert when the job stops.

Event Type	Description
Job Failure	Sends a notification when job stops unexpectedly.
Participant Failure	Sends an alert when the Management Agent disconnects or stops responding.
System Event	Sends an alert when a system event such as low memory or low hub disk space occurs.
Malicious Event	Sends an alert when Peer MED detects potentially malicious activity. For more information, see MED Configuration .

6. Select the report types to be sent.

Report Type	Description.
Scan	Sends scan statistics after a scan has completed.
Destination Snapshot	Sends information about the snapshot after the snapshot is taken.

7. Enter alert recipients, and then click **Add to List**.

The recipients are listed in the **Recipients** field.

8. Click **OK**.

The new email alert is listed in the **Email Alerts** table and can now be applied to jobs.

9. Click **Apply and Close** or **Apply**.


File Retries and Source Snapshots

This page allows you to specify two sets of options:

- **File Retries** - Settings that are used when retry issues that arise while replicating a file or folder.
- **Source Snapshot Replication** - Settings that control how and when source snapshots are used.

To modify these options:

1. Select **Preferences** from the **Window** menu.
2. Expand **Cloud Backup and Replication** in the navigation tree, and then select **File Retries and Source Snapshots**.



3. Modify the **Retry Options** as needed:

Option	Description
Max Number of Retry Threads	Enter the maximum number of threads available for handling retries of failed file or folder transfers.
Max Number of Retries	Enter the maximum number of retries to perform on a file or folder that has failed to be replicated. If the number of retries is exceeded, the file or folder will be added to the Failed Events view and will need to be manually processed.
Retry Interval in seconds	Enter the number of seconds to wait in between retries of the failed replication of a file or folder.
Multi-part Upload	Enter the maximum number of retries when performing multi-part upload.

Option	Description
Retry Count	
Multi-part Upload Retry Interval in Milliseconds	Enter the number of minutes to wait between retries of multi-part uploads.

4. Modify the **Source Snapshot Replication Options** as needed:

Option	Description
Max Number of Transfer Threads	Enter the maximum number of threads available for replicating files from a source snapshot.
Max Number of Transfer Retries	Enter the maximum number of retries to perform on a file or folder that has failed to be replicated from a source snapshot. If the number of retries is exceeded, the file or folder will be added to the Failed Events view and will need to be manually processed.
Transfer Retry Interval in Minutes	Enter the number of minutes to wait between retries of the failed replication of a file or folder from a source snapshot.
Managed File Extensions	Enter the extensions for managed files that should be read from a source snapshot.

5. Click **Apply and Close** or **Apply**.


File and Folder Filters

When you create a Cloud Backup and Replication job, you can select existing file filters to apply to the job or you can create new file filters and apply them to the job. This [Preferences](#) page lists the existing file filters. From this page, you can view, create, edit, update, and delete file filters. However, you cannot edit or delete a file filter while it is applied to a job. See [File and Folder Filters](#) in the [Basic Concepts](#) section for more information about file and folder filters.

To create a file filter:

1. Select **Preferences** from the **Window** menu.
2. Expand **Cloud Backup and Replication** in the navigation tree, and then select **File and Folder Filters**.

Any existing Cloud Backup and Replication file filters are listed in the **File Filters** table.




3. Click the **Create** button.

The **Create File Filter** dialog appears.

The screenshot shows a 'Create File Filter' dialog box. It features a title bar with a close button. The main area contains several sections: a 'Name' text field, a 'Filter Type' dropdown menu currently set to 'General', an 'Auto Excluded' section with a link to 'View file types that are automatically excluded', an 'Excluded Patterns' list with 'Add', 'Edit', and 'Delete' buttons, an 'Included Patterns' list with 'Add', 'Edit', and 'Delete' buttons, an 'Included Last Modified Dates' section with a dropdown set to 'Include all dates' and a '0 days' input, and an 'Excluded File Sizes' section with a dropdown set to 'None' and a '0 bytes' input. At the bottom are 'OK' and 'Cancel' buttons.


4. Enter a unique name for the filter.
5. Select the [filter type](#).
6. (Optional) In the **Excluded Patterns** section, click the **Add** button to enter a filter pattern for files that you want excluded from the job. Repeat to add more filter patterns.

See [Defining Filter Patterns](#) for information about filters patterns.



Dialog box titled "Add Exclusion Pattern" with a close button (X) in the top right corner. The main text reads "Enter a single file name or a single path pattern:" followed by an empty text input field. Below the input field, the error message "String cannot be empty." is displayed. At the bottom right, there are "OK" and "Cancel" buttons.

- (Optional) In the **Included Patterns** section, click the **Add** button to enter a filter pattern for files that you want included in the job. Repeat to add more filter patterns.



Dialog box titled "Add Inclusion Pattern" with a close button (X) in the top right corner. The main text reads "Enter a single file name or a single path pattern:" followed by an empty text input field. Below the input field, the error message "String cannot be empty." is displayed. At the bottom right, there are "OK" and "Cancel" buttons.

- (Optional) Select a value for [Included Last Modified Dates](#).

Note: A filter cannot use **Included Last Modified Dates** in conjunction with any other excluded or included patterns.

- (Optional) Select a value for [Excluded File Sizes](#).

Note: A filter cannot use **Excluded File Sizes** in conjunction with any other excluded or included patterns.

- Click **OK**.

The new file filter is listed in the **File Filters** table and can now be applied to jobs.


- Click **Apply and Close** or **Apply**.

Performance

Performance settings allow you to adjust the performance of Cloud Backup and Replication jobs.

To modify the Cloud Backup and Replication performance settings:

1. Select **Preferences** from the **Window** menu.
2. Expand **Cloud Backup and Replication** in the navigation tree, and then select **Performance**.



3. Modify the settings as needed:

Setting	Description
Max Number of Real-time Replication Threads	Enter the maximum number of threads available for replicating files as they are updated in real-time on the source storage device.
Max Number of Scan Replication Threads	Enter the maximum number of threads available for replicating files during scheduled and on-demand scans of the source storage device.
Max Number of Upload Threads	Enter the maximum number of threads available for uploading files to the destination storage device.
Max Number of Restore Threads	Enter the maximum number of threads available for restoring from the destination storage device.

4. Click **Apply and Close** or **Apply**.


Proxy Configuration

The **Proxy Configuration** page allows you to create a proxy to be used with Microsoft Azure Blob Storage, Amazon S3, and S3 Compatible storage accounts.

To create a proxy configuration:

1. Select **Preferences** from the **Window** menu.
2. Expand **Cloud Backup and Replication** in the navigation tree, and then select **Proxy Configuration**.

Any existing proxies are listed in the **Proxy Configuration** table.



Create Proxy Configuration

Agent:

IP Address:

Port:

Use Authentication

Domain:

Username:

Password: Show Password

OK **Cancel**

4. Select the Agent that that manages your storage device.
5. Enter values for the following fields:

Field	Description
IP Address	Enter the IP address or fully qualified domain name of the proxy server.
Port	Enter the port number.
User Authentication	Select if your proxy server requires authentication. This option does not apply for proxy servers connecting to an Azure storage device

6. If your proxy server requires authentication, select the **Use Authentication** checkbox, and then supply the necessary values:

Field	Description
Domain	Enter the domain name on the proxy server.
Username	Enter the user name for the proxy server.
Password	Enter the password for the proxy server.

7. Click **OK**.

The new proxy configuration is listed in the **Proxy Configuration** table.


The screenshot shows the 'Preferences' window with the 'Proxy Configuration' section selected. The 'Proxy Configuration' table is visible, containing one entry:

Target Hostname	Type	IP Address	Port	Use Authentication
DGWin16A	Manual proxy	[Redacted]	8088	No

Buttons for 'Create', 'Edit', 'Delete', and 'Validate' are located to the right of the table. At the bottom of the window, there are buttons for 'Apply and Close', 'Cancel', and 'Apply'.

8. Click **Apply and Close** or **Apply**.

The **Replication and Retention Policy Wizard** opens.



The screenshot shows the 'Replication and Retention Policy Wizard' dialog box. The title bar reads 'Replication and Retention Policy Wizard'. Below the title bar, the main heading is 'Replication and Retention Policy'. A red error message with a small 'x' icon states: 'You must enter a name for the policy.' The dialog is divided into two main sections. On the left is a navigation pane with four items: 'Replication and Retention' (highlighted in blue), 'Replication Schedule', 'Retention', and 'Source Snapshots'. The main area on the right contains a text input field labeled '*Name:' which is currently empty. Below the input field is a checked checkbox labeled 'Enable Backup with Destination Snapshots'. At the bottom of the dialog, there are four buttons: '< Back', 'Next >', 'Finish', and 'Cancel'. A scrollbar is visible on the left side of the main content area.

4. Enter a name, and then click **Next**.
5. Complete the wizard.

See [Step 11: Replication and Retention Policy](#) in [Creating a Cloud Backup and Replication Job](#) for assistance in completing the wizard.

6. Click **Apply and Close** or **Apply**.


SNMP Notifications

When you create a job, you can select an existing SNMP notification to apply to the job or you can create a new notification and apply it to the job. You cannot edit or delete an SNMP notification while it is applied to a job. See [SNMP Notifications](#) in the [Basic Concepts](#) section for more information about SNMP notifications.

To create an SNMP notification:

1. Select **Preferences** from the **Window** menu.
2. Expand **Cloud Backup and Replication** in the navigation tree, and then select **SNMP Notifications**.

Any existing SNMP notifications are listed in the **SNMP Notifications** table.



3. Click the **Create** button.

The **Add SNMP Notification** dialog appears.

Create SNMP Notification

Name:

Temporarily Disable

Event Types

Job Start Job Stop Job Failure Participant Failure

System Event Malicious Event

4. Select the types of events that will trigger the generation of an SNMP trap:

Event Type	Description
Job Start	Sends a notification when the job starts.
Job Stop	Sends a notification when the job stops.
Job Failure	Sends a notification when job stops unexpectedly.
Participant Failure	Sends a notification when the Management Agent job disconnects or stops responding.
System Event	Sends a notification when a system event such as low memory or low hub disk space occurs.

Event Type	Description
Malicious Event	Sends a notification when a malicious event is detected. For more information, see MED Configuration .

5. Click **OK**.

The new notification is listed in the **SNMP Notifications** table and can now be applied to jobs


6. Click **Apply and Close** or **Apply**.

Scan Manager

The Cloud Backup and Replication Scan Manager is responsible for handling all scheduled and on-demand scans of the source storage device.

To modify the Scan Manager settings for Cloud Backup and Replication jobs:

1. Select **Preferences** from the **Window** menu.
2. Expand **Cloud Backup and Replication** in the navigation tree, and then select **Scan Manager**.



3. Modify the settings as needed.

Setting	Description
Scan Item Limit	Enter the maximum number of files and folders to obtain from a folder structure at a time during a scan.

Setting	Description
Max Number of Scan Threads	Enter the maximum number of threads available for scanning files and folders. Set the number to at least the maximum number of jobs running on any single Management Agent.
Max Number of Concurrent Scans	Enter the maximum number of scans that can run in parallel. If the number of active scan threads is greater than this number, scan threads will process on a rotating basis. Increasing this number can increase scan performance but will also increase system memory and CPU utilization.

4. Click **Apply and Close** or **Apply**.

Collaboration, Replication, and Synchronization Job Preferences

You can modify the following settings for File Collaboration, File Synchronization, and File Replication jobs:

- [Collab Sync, and Replication](#)
- [DFS-N Management](#)
- [Dynamic Storage Utilization](#)
- [Email Alerts](#)
- [File Retries](#)
- [File and Folder Filters](#)
- [Locking](#)
- [Performance](#)
- [Real-time Event Detection](#)
- [Revit Enhancements](#)


- [SMNP Notifications](#)
- [Scan Manager](#)
- [Scheduled Replication Filters](#)

Collab, Sync, and Replication

These settings control basic GUI and reconnect settings for all File Collaboration, File Synchronization, and File Replication jobs.

To modify these settings:

1. Select **Preferences** from the **Window** menu.
2. Select **Collab, Sync, and Replication** in the navigation tree.



3. Modify the settings as needed.

Option	Description
Auto Reconnect When Host Becomes Available	When an Agent reconnects to Peer Management Center after a failure, automatically re-enables it in any associated jobs. Highly recommended.
Minimum Host Reconnect Time (in minutes)	Enter the minimum number of minutes to wait after an Agent reconnects before re-enabling it in any associated jobs.
Enable Advanced Reporting Tab	Enables the Reporting tab in the global Collab, Sync, and Repl Summary view.
Enable Real-Time Tracking	Enables Event Detection Analytics to track and report common activity processed by Peer Global File Service. If enabled, every 24 hours, an Excel-based report will be written to disk that shows top folders, files, extensions, and users by total processed activity over the previous 24-hour window. These reports are stored under the installation folder of Peer Management Center and can be reviewed by Peer Software Technical Support when uploading log files.

4. Click **Apply and Close** or **Apply**.


Application Enhancements

The settings on this page finetune how the specified file types are replicated. Most of the settings on this page are automatically configured based on selections in the Application Support page for the job. Consult with Peer Support before changing any settings as modifying values may cause unexpected results.

Default values are based on user selections on the Application Support page. But can enter extensions for applications that are listed on Application Support page.

To set advanced settings for Revit Enhancements:

1. Select **Preferences** from the Window menu.
2. Expand **Collab, Sync, and Replication** in the navigation tree, and then select **Application Enhancements**.



3. Modify the options as needed.

Option	Description
Sync On Save Override File Extensions	Extensions configured here will overwrite the Sync. On Save values configured in the interface for the job. In addition, these extensions use the delay value in Sync On Save Override Delay setting instead of the delay value configured in the interface. If no delay value is set, it will default to using a one second delay. Extensions configured in this list will still be processed via Sync. On Save even if they also exist in the user defined non-collaborative extension list (under the Window > Preferences menu option). Extensions in the normal Sync. On Save list that also exist in this list will not be processed.

Option	Description
Sync On Save Override Delay	The Sync. On Save delay value in seconds that applies only to the internal list of extensions listed in the Sync On Save Override File Extension field.
Target Sharing Violation File Extensions	This is an option to retry setting the target lock when receiving error code 32 for the specified list of extensions. This may be useful for file types such as .one (OneNote), .rvt (Revit), and .dat (associated Revit files) that don't sustain a handle when the user has the file open.
Bulk Context Minimum Rejected Event Threshold	The number of bulk add files that can process immediately before batching the remainder of the files and process them in a single thread.
Retry Quarantine File List	Quarantined files that are in this list will be automatically removed and flagged as unsynchronized and will be retried every second after a delay period (delay is configured by fc.retryQuarantinesDelay). Any change event that is detected for the files will trigger a scan of the files where the newest file will win. This list can contain file names (wperms.dat, eperms.dat, requests.dat, deltas.dat, users.dat) or extensions (*.dat,*.abc).
Last Write Override Extensions	Act on every write event performed on these extensions instead of waiting for the last write event prior to the closing of a file.
Expedited Fast Sync File List	Access events and transfer events will be expedited for the list of extension or files in this list.
Expedited Slow Sync File List	Access events received for files or extension in this list will be expedited. Transfers will go through a slow priority queue.
Direct Target Write List	List of files to be updated without the use of a temp file. This list can contain file names (wperms.dat, eperms.dat, requests.dat, deltas.dat, users.dat") or extensions.


4. Click **Apply and Close** or **Apply**.

DFS-N Management

These settings control the [failover and failback](#) capabilities for [PeerGFS-managed namespaces](#) that are [linked to File Collaboration and File Synchronization jobs](#).

To modify these settings:

1. Select **Preferences** from the **Window** menu.
2. Expand **Collab, Sync, and Replication** in the navigation tree, and then select **DFS-N Management**.



3. Select options as needed.

Option	Description
Bring folder targets online only after a re-scan is complete	Re-enable a disabled folder target in a PeerGFS-managed DFS namespace only when it has been rescanned and is back in sync after an outage. Highly recommended.
Disable a folder target if its linked participant is not available when a job is started	If a File Collaboration or File Synchronization job is started and a participant is not available, automatically disable its associated folder target in a managed DFS namespace.

4. Click **Apply and Close** or **Apply**.

Dynamic Storage Utilization

These settings control the following aspect of jobs that use [Dynamic Storage Utilization](#):


- [Dynamic Storage Utilization](#)
- [Email Alerts](#)
- [Master Data Service](#)
- [Pinning Filters](#)
- [Utilization Policies](#)
- [Volume Policies](#)

The [Peer Master Data Service](#) and Peer Edge Service are used by Dynamic Storage Utilization. The Peer Master Data service is a web service that handles requests from edge participants for files on a master participant. It runs on Master participants and is [configurable](#). The primary job of the Peer Edge service is to service reparse requests for Peer stub files and read and/or rehydrate stub files.

Use this page to set the frequency that these services are checked to see if they are operational.

To change the frequency:

1. Select **Preferences** from the **Window** menu.
2. Expand **Collab, Sync, and Replication** in the navigation tree, and then select **Dynamic Storage Utilization**.
3. Change the frequency.



4. Click **Apply and Close** or **Apply**.

5. Enter a name for the alert.
6. Select the caching scan event types to be alerted.

Event Type	Description
Scan Start/End	Sends a notification when a caching scan is started or stopped.
Scan Fatal Errors	Sends a notification when a fatal error occurs during a caching scan.


Event Type	Description
Scan Errors	Sends a notification when errors occur during a caching scan.
Cache Size Exceeded	Sends a notification when the amount of volume disk space used by DSU exceeds the size specified by the Cache Size option in the volume policy.
Low Disk Space	Sends a notification the volume disk space falls below the size specified by the Disk space is less than X option in the volume policy.
Cache Safe Percentage Exceeded	Sends a notification when the percentage specified by the Cache usage exceeds X% of cache size option in the volume policy.
Master/Edge Services Health Monitoring	Sends a notification if either the Peer Master Data Service or the Peer Edge Service goes down.

7. Enter alert recipients, and then click **Add to List**.

The recipients are listed in the **Recipients** field.

8. Click **OK**.

The new email alert is listed in the **Email Alerts** table and can now be applied to DSU-enabled jobs.




9. Click **Apply and Close** or **Apply**.

When you create a job that is DSU-enabled, you specify the settings to be used for the Peer Master Data Service. The Peer Master Data Service handles requests from edge participants for files on a master participant. The Peer Master Data Service is installed as part of the Peer Agent installation process. The **Master Data Service** page displays the existing parameters for the Master Data Service.

To edit the Master Data Service configuration:

1. Select **Preferences** from the **Window** menu.
2. Expand **Collab, Sync, and Replication** in the navigation tree, and then select **Dynamic Storage Utilization**.
3. Select **Master Data Service**.

The **Master Data Service** table lists master participants. The **In Use** column identifies whether the participant is currently being used as a master participant in a job.



The screenshot shows a dialog box titled "Edit Master Data Service". It has a title bar with a gear icon, a minus sign, a maximize button, and a close button. The dialog contains four input fields: "Protocol" with the value "HTTPS", "Agent Name" with the value "DGAgent1", "Agent Alias" which is empty, and "Port" with the value "8446". At the bottom of the dialog are two buttons: "OK" and "Cancel".

5. (Optional) Enter a value for **Agent Alias**; the value can be a hostname, FDQN, or IP address.

A value for **Agent Alias** is required only if the name of the Agent cannot be converted to an IP address via DNS. If an alias name is entered, it will be used by the Edge Service on edge participants to connect with the Master Data Service. If no alias name is entered, the name of the Agent will be used.

6. (Optional) Modify the default value for **Port** if you are use a different port.

If you modify the port number, the Master Data Service will be restarted and the new port number will take effect immediately.

7. Click **OK**.


The revised Master Data Service is listed in the Master Data Service table.

8. Click **Apply and Close** or **Apply**.

The new settings will be applied to all DSU-enabled jobs.

When you create a DSU-enabled job, you can select existing pinning filters to apply to the job or you can create new pinning filters and apply them to the job. This [Preferences](#) page lists the existing pinning filters. From this page, you can create, edit, and delete pinning filters. However, you cannot edit or delete a pinning filter while it is applied to a job.

A pinning filter specifies whether specific files or files in a particular directory are always stubbed or always local on the edge participant. A pinning filter similar is to a utilization policy



Create Pinning Filter

*Name:


Pinning Rules:

Path	Pinning State	

Create
Edit
Delete

OK Cancel

5. Enter a name for the pinning filter.



Create Pinning Filter

*Name:


Pinning Rules:

Path	Pinning State	


Create
Edit
Delete

OK Cancel

6. Click **Create** to add a pinning rule to the filter.



7. Enter a file name or enter a path.




8. Choose a pinning state:

- Select **Local at Edge** if you want the specified files or path to always be local and never stubbed.
- Select **Stubbed at Edge** if you want the specified files or path to always be stubbed at edge.
AuA

9. Click **OK**.


The rule appears in the **Pinning Rules** table.



10. If you want to add additional rules to the pinning filter, repeat Steps 6-9.

11. Click **OK** to close the **Create Pinning Filter** dialog.

The new filter is listed in the **Pinning Filters** table and can now be applied to DSU-enabled jobs.



Create DSU SNMP Notification

Name:

Temporarily Disable

Caching Scan Alerts

Scan Start/End Scan Fatal Errors Scan Errors

Volume Alerts

Cache Size Exceeded Low Disk Space

Cache Safe Percentage Exceeded

Service Alerts

Master/Edge Services Health Monitoring

5. Select the types of events that will trigger the generation of an SNMP trap:

Event Type	Description
Scan Start/End	Sends a notification when a caching scan is started or stopped.
Scan Fatal Errors	Sends a notification when a fatal error occurs during a caching scan.
Scan Errors	Sends a notification when errors occur during a caching scan.
Cache Size Exceeded	Sends a notification when the amount of volume disk space used by DSU exceeds the size specified by the Cache Size option in the volume policy.
Low Disk Space	Sends a notification the volume disk space falls below the size specified by the Disk space is less than X option in the volume policy.

Create Utilization Policy

*Name:

File Size

Keep files local if less than

Stub files if greater than

Time Period

Keep recently used files local based on a dynamic set of rules

Keep recently used files local based on the following rules:

Stub files if not modified within the past

Stub files if not accessed within the past

Stubbing Override

Select to override time period rules and Stub at Edge pinning rule:

Stub files if not accessed within the past

Advanced Options

Do not hydrate files during caching scan

5. Enter a name for the policy.
6. (Optional) In the **File Size** section, select one or both options:

Field	Description
Keep files local if less than X size	Select this option if you want files under a specified size to remain local.
Stub files if greater than X size	Select this option if you want files over a specified size to be stubbed.

7. (Optional) In the **Time Period** section, select one of the options:

Field	Description
Keep recently used files local based on a dynamic set of rules	Select this option if you want DSU to control when to stub files based on last accessed and last modified times. DSU dynamically adjusts the accessed and modified time periods it uses based on the total amount of space that DSU is actively using on a volume.
Keep recently used files local based on the following rules	Select this option if you want to specify the dates used when stubbing files based on the last accessed and last modified.

8. If you selected the **Keep recently used files local based on the following rules** option in **Time Period**, two additional options are enabled; select the options to be used and specify the time periods to be used:


Field	Description
Stub files if not modified within the past X time period	Select this option and specify a time range to use the last modified date of a file to determine if it should be kept local or stubbed.
Stub files is not accessed within the past X time period	Select this option and specify a time range to use the last accessed date of a file to determine if it should be kept local or stubbed.

9. (Optional) in the **Stubbing Override** section, select the checkbox and a time period if you want to use the last accessed date of all recently hydrated files to determine if they

should be kept local or re-stubbed.

10. Click **OK**.

The new policy is listed in the **Utilization Policies** table and can now be applied to jobs.



The screenshot shows the 'Preferences' dialog box with the 'Utilization Policies' section selected. The 'Utilization Policies' table is displayed with the following data:

Name	Dynamic Rules Enabled	In Use
Default Utilization Policy	Enabled	Yes
File Size Utilization Policy	Enabled	No
Time Period Utilization Policy	Disabled	No

The dialog box also features a 'Create' button (disabled), an 'Edit' button (active), a 'Copy' button, and a 'Delete' button. At the bottom, there are 'Apply and Close', 'Cancel', and 'Apply' buttons.

11. Click **Apply and Close** or **Apply**.

When you create a DSU-enabled job, you specify a volume policy for an edge participant. A **volume policy** specifies how much of the available space on the volume monitored by the edge participant to assign for local (hydrated) files. This space is referred to as a **cache**. The volume refers to the drive letter of the path set on the **Path** page of the wizard (for example, if the participant is configured to monitor D:\Data, the volume policy for this participant would apply to the D volume).

If the Agent you selected is already being used as an edge participant in another job utilizing DSU, the existing volume policy will be displayed on this page. You can edit the existing volume policy; however, be aware that any modifications to the volume policy will be applied to every other job that use this Agent as an edge participant and "touch" the same volume.

From this page, you can edit and delete volume policies. However, note that:

- Any changes made to a volume will not be applied to a running job until the job is restarted.
- You cannot delete a volume policy while it is being used by an edge participant.

To edit a volume policy:

1. Select **Preferences** from the **Window** menu.
2. Expand **Collab, Sync, and Replication** in the navigation tree, and then select **Dynamic Storage Utilization**.
3. Select **Volume Policies** in the navigation tree.



Any existing volume policies are listed in the **Volume Policies** table.

The screenshot shows the 'Preferences' dialog box with the 'Volume Policies' section selected in the navigation tree. The 'Volume Policies' table is displayed with the following data:


Agent	Volume Na...	Cache Size	In Use	Utilization Policy
DGAgent2	C:\	10 GB	Yes	Default Utilization Policy

Buttons for 'Edit' and 'Delete' are visible to the right of the table. At the bottom of the dialog, there are buttons for 'Apply and Close', 'Cancel', and 'Apply'.

4. Select the policy you want to modify, and then click **Edit**.
5. If you have created a DSU email alert or a DSU SNMP notification but not saved it, you will be prompted to save it.



6. If you selected a policy currently being used in a job, the **In Use Configuration** message appears.



7. Click **OK** to close the dialog.

The **Edit Volume Policy** dialog appears.

8. If you want to associate a different utilization policy with this volume policy, click **Select Different Utilization Policy** link, select the policy, and then click **OK**.

9. In the **Cache Size** section, choose an option for setting the cache size.

- Use up to X % of this volume
- Use up to X size of this volume

Edit Volume Policy (DGAgent2 - C:\)

Volume Policy
Define volume policy and set temporary storage path.

Volume Policy
Email Alerts
SNMP Notifications

Select Different Utilization Policy

Cache Size

- Use up to 75 % of this volume
- Use up to 10 GB of this volume

Cache Threshold Alerts

Send alerts when:

Disk space is less than 500 MB

Cache usage exceeds 80 % of the cache size

Caching Scan Schedule

- Scan every 1 day(s) at 10:00:00 PM
- Define schedule

*Temporary Storage Path: C:\ Browse

C:\PeerTempPath

< Back Next > **Finish** Cancel

10. In the **Cache Threshold Alerts** section, enter values for automatic alerts about free disk space and cache usage.

Peer Management Center will automatically display alerts in the **Alerts** tab and send alerts via email (if configured) when:

- The amount of free disk space on the volume falls below the specified value. For example, if a 1TB volume has 500MB of free space and the threshold is set to 512MB, an alert will be sent.
- Cache usage on the volume exceeds the specified percentage of the cache size. For example, if the cache size is set to 80%, equating to 750 GB, DSU will start sending alerts when it has used 600 GB.

Edit Volume Policy (DGAgent2 - C:\)

Volume Policy
Define volume policy and set temporary storage path.

Volume Policy
Email Alerts
SNMP Notifications

Select Different Utilization Policy

Cache Size

Use up to 75 % of this volume

Use up to 10 GB of this volume

Cache Threshold Alerts

Send alerts when:

Disk space is less than 500 MB

Cache usage exceeds 80 % of the cache size

Caching Scan Schedule

Scan every 1 day(s) at 10:00:00 PM

Define schedule

*Temporary Storage Path: C:\ Browse

C:\PeerTempPath

< Back Next > **Finish** Cancel

11. In the **Caching Scan Schedule**, set the frequency that the volume should be scanned to optimize the balance of fully hydrated vs stubbed files.

This scan can be run daily at a specified time or you can define a more customized schedule.

The screenshot shows the 'Edit Volume Policy (DGAgent2 - C:\)' dialog box. The 'Volume Policy' section is active, and the 'Caching Scan Schedule' section is highlighted with a red box. The 'Temporary Storage Path' field is set to 'C:\'.

Volume Policy
Define volume policy and set temporary storage path.

Volume Policy
Email Alerts
SNMP Notifications

Select Different Utilization Policy

Cache Size

Use up to 75 % of this volume

Use up to 10 GB of this volume

Cache Threshold Alerts

Send alerts when:

Disk space is less than 500 MB

Cache usage exceeds 80 % of the cache size

Caching Scan Schedule

Scan every 1 day(s) at 10:00:00 PM

Define schedule

*Temporary Storage Path: C:\ Browse

C:\PeerTempPath

< Back Next > Finish Cancel

12. In the **Temporary Storage Path** field, enter a path or browse to the location you want to be used as temporary storage space.

The temporary storage space will be used to store the content of stub files as they are being rehydrated. The content of files undergoing rehydration are referred to as **file blocks**. File blocks are fixed-length chunks of data that are read into memory when requested by an application. DSU will create a subfolder named **.PeerTempPath** under the location that you specify and temporarily store the file blocks in that subfolder.

For optimal performance, we recommend that the temporary storage space be on the same volume as the watch set. If that is not possible, it should be on a high performance disk.

Edit Volume Policy (DGAgent2 - C:\)

Volume Policy

Define volume policy and set temporary storage path.

Volume Policy

Email Alerts

SNMP Notifications

Select Different Utilization Policy

Cache Size

Use up to 75 % of this volume

Use up to 10 GB of this volume

Cache Threshold Alerts

Send alerts when:

Disk space is less than 500 MB

Cache usage exceeds 80 % of the cache size

Caching Scan Schedule

Scan every 1 day(s) at 10:00:00 PM

Define schedule


*Temporary Storage Path: C:\ Browse

C:\PeerTempPath

< Back Next > Finish Cancel

13. Click **Next**.

14. (Optional) Select one or more email alerts to be associated with this volume policy, and then click **Next**.



15. (Optional) Select one or more SNMP notifications to be associated with this volume policy.

Create Email Alert

Name:

Temporarily Disable

Event Types

Job Start Job Stop Job Failure Participant Failure Participant Reconnect File Quarantine
 Scan Error Malicious Event

Queued Items

<input type="checkbox"/> Number of Queued Items	<input type="checkbox"/> Size of Queued Items:
Exceeds: <input type="text" value="5000"/> Items	Exceeds: <input type="text" value="10240"/> MB
Recovers Below: <input type="text" value="1000"/> Items	Recovers Below: <input type="text" value="1024"/> MB
<input type="checkbox"/> Alert on Recovery	<input type="checkbox"/> Alert on Recovery

Reports

Scan

Batch Email Alerts

Quarantined Files

Recipients

Enter email, contact, or distribution list:

Recipients:

4. Enter a name for the alert.
5. Select the types of events that will trigger an email alert to be sent.

Event Type	Description
Job Start	Sends an alert when the job starts.
Job Stop	Sends an alert when the job stops.
Job Failure	Sends an alert when the job is aborted because of lack of quorum due to one or more failed participants.
Participant Failure	Sends an alert when a participant timeout occurs, and the participant is taken out of the running job.
Participant Reconnect	Sends an alert when a participant reconnects to the job and the job resumes with the reconnected participant.
File Quarantine	Sends an alert when a file is marked as quarantined because a file conflict was not able to be resolved.
Scan Error	Sends an alert when an error occurs during the initial synchronization process .
Malicious Event	Sends an alert when Peer Malicious Event Detection (MED) detects potentially malicious activity. For more information, see MED Configuration .

6. Select options in the **Queued Items** section.


Option	Description
Number of Queued Items section	<p>Select this checkbox if you want alerts to be sent regarding number of items in the queue. This is useful to notify you about when there is a queue backlog potentially due to latency issues.</p> <p>If you select this checkbox, you need to enter two values that work in tandem:</p> <ul style="list-style-type: none"> • Exceeds X Items - Enter the highest number of queued items before an email alert is sent. The default value is 5000. • Recovers Below X Items - Enter a value. The default value is 1000. <p>An alert is sent the first time that the Queued Items counter has items is greater than the value set in Exceeds X Items. The counter's value is displayed in the Queued Items column in the in the Collab, Sync, and Repl Summary view. The counter's value is a combination of the Real-time and File Sync queues.</p> <p>Another alert will not be sent until the Queued Items counter has dropped below the Recovers Below x Items value and then exceeds the Exceeds X Items value again. This prevents multiple or redundant alerts from being sent.</p>
Alert on Recovery	<p>Select this option if you want an alert to be sent when the number of queued items has fallen below the Recovers Below value.</p>
Size of Queued Items section	<p>Select this if you want alerts to be sent based on the total data size of queued items for a job. This is useful to notify you about when there is a queue backlog potentially due to bandwidth issues.</p> <p>If you select this checkbox, you need to enter two values that work in tandem:</p> <ul style="list-style-type: none"> • Exceeds X MB - Enter the highest number of queued items before an email alert is sent. The default value is 10240 MB. • Recovers Below X MB - Enter a value. The default value is 1024 MB. <p>An alert is sent the first time that the Pending Bytes for a job has items is greater than the value set in Exceeds X MB. The counter's value is displayed in the Pending Bytes column in the Collab, Sync, and Repl Summary view.</p>
	<p>Another alert will not be sent until the Pending Bytes counter has dropped below the Recovers Below x MB value and then exceeds the Exceeds X MB value again. This prevents multiple or redundant alerts</p>

File Retries

File retries settings enable you to configure the frequency of attempts and the maximum number of attempts. These settings apply to all File Collaboration, File Replication, and File Synchronization jobs. For more information about file retries, see [Conflicts, Retries, and Quarantines](#).

To modify the file retries settings:

1. Select **Preferences** from the **Window** menu.
2. Expand **Collab, Sync, and Replication** in the navigation tree, and then select **File Retries**.



3. Modify the settings as needed.

Setting	Description
Enable Retries	Select this checkbox to enable the retry of failed file transfers. If this option is not enabled, files that would have been candidates for retries will be automatically quarantined.
Maximum Number of File Retries	Enter the maximum number of attempts to retry a failed file transfer before it is quarantined.
Delay Between Retries in Seconds	Enter the number of seconds to wait between retries of a failed file transfer.

4. Click **Apply and Close** or **Apply**.


File and Folder Filters

When you create a File Collaboration, File Synchronization, or File Replication job, you can select existing file and folder filters to apply to the job or you can create new file filters and apply them to the job. This [Preferences](#) page lists the existing file and folder filters. From this page, you can view, create, edit, update, and delete file filters. However, you cannot edit or delete a file filter while it is applied to a job. See [File and Folder Filters](#) in the [Basic Concepts](#) section for more information about file and folder filters.

To create a file and folder filter:

1. Select **Preferences** from the **Window** menu.
2. Expand **Collab, Sync, and Replication** in the navigation tree, and then select **File and Folder Filters**.

Any existing file filters are listed in the **File and Folder Filters** table.



3. Click **Create**.

The screenshot shows the 'Create File Filter' dialog box. It features a title bar with a logo and the text 'Create File Filter'. The main area is divided into several sections: a 'Name' field, a 'Filter Type' dropdown menu set to 'General', an 'Auto Excluded' section with a link to 'View file types that are automatically excluded', two large text areas for 'Excluded Patterns' and 'Included Patterns', each with 'Add', 'Edit', and 'Delete' buttons, and two sections for 'Included Last Modified Dates' (set to 'Include all dates' with a '0 days' input) and 'Excluded File Sizes' (set to 'None' with a '0 bytes' input). At the bottom are 'OK' and 'Cancel' buttons.

4. Enter a unique name for the filter.
5. Select the [filter type](#).
6. (Optional) Click **Add** to enter a filter pattern for files that you want excluded from the job. Repeat to add more filter patterns.

See [Defining Filter Patterns](#) for information about filter patterns.

7. (Optional) Click **Add** to enter a filter pattern for files that you want included in the job. Repeat to add more filter patterns.

8. (Optional) Select a value for [Included Last Modified Dates](#).


Note: A filter cannot use **Included Last Modified Dates** in conjunction with any other excluded or included patterns.

9. (Optional) Select a value for [Excluded File Sizes](#). Note: This cannot be combined with any other filter criteria

Note: A filter cannot use **Excluded File Sizes** in conjunction with any other excluded or included patterns.

10. Click **Apply and Close** or **Apply**.

The new file filter is listed in the **File and Folders Filters** table and can now be applied to jobs.




Locking

An option is available to mark certain file types as non-collaborative, changing the way locks on the specified file types are handled. These settings apply to all File Collaboration, File Synchronization, and File Replication jobs. These settings are critical for certain file types so that the job can correctly read these files, ensuring that managed file types are synchronized in a consistent and usable state.

To modify the locking settings:

1. Select **Preferences** from the **Window** menu.
2. Expand **Collab, Sync, and Replication** in the navigation tree, and then select **Locking**.



3. Modify the options as needed.


Option	Description
Default Non-Collaborative File Extensions	Non-editable. Displays the default, comma-separated list of file extensions of non-collaborative file types (e.g., database files). Write access to source files of these types is denied while the files are being synchronized.
User Defined Non-Collaborative File Extensions	Displays an editable, comma-separated list of file extensions of non-collaborative file types (e.g., database files). Write access to the source files of these types is denied while the files are being synchronized.

4. Click **Apply and Close** or **Apply**.

Performance

To customize the performance settings of File Collaboration, File Synchronization, and File Replication jobs:

1. Select **Preferences** from the **Window** menu.
2. Expand **Collab, Sync, and Replication** in the navigation tree, and then select **Performance**.



3. Modify the options as needed.


Option	Description
Real-Time Expedited Threads	Enter the maximum number of threads for controlling file locking and renames.
Real-Time Background Threads	Enter the maximum number of threads for controlling the replication of file content.
Background Scan Synchronization Threads	Enter the maximum number of threads for processing the differences found by background scans.
Multipart Transfer Threads	Enter the maximum number of threads to be used for processing chunks of large files in parallel.
Debug Mode	Select to enable debug mode for the various types of threads.

4. Click **Apply and Close** or **Apply**.

Real-time Event Detection

To modify the File Collaboration real-time detection settings:

1. Select **Preferences** from the **Window** menu.
2. Expand **Collab, Sync, and Replication** in the navigation tree, and then select **Real-time Event Detection**.



3. Modify the options as needed.

Option	Description
Change Dispatch Quiet Period (Seconds)	The number of seconds to wait before acting on a file modification, rename, or delete.
Bulk Add Delay (Seconds)	Controls when the bulk add logic is triggered. This is used to help deprioritize mass copying or adding of files to a directory.
Bulk Add Minimum Rejected Threshold	The minimum number of file adds that must occur within the Bulk Add Delay for bulk add logic to be triggered.
Bulk Add Max Events	The maximum number of file adds to lump together in one batch.

4. Click **Apply and Close** or **Apply**.

Add SNMP Notification

Name:

Temporarily Disable

Event Types

Job Start Job Stop Job Failure Participant Failure

File Quarantine Scan Error Malicious Event

Queued Items

Number of Queued Items

Exceeds: Items

Recovers Below: Items

Alert on Recovery

Size of Queued Items

Exceeds: MB

Recovers Below: MB


Alert on Recovery

4. Select the types of events that will trigger the generation of an SNMP trap:

Event T	Description
Job Start	Sends a notification when the job starts.
Job Stop	Sends a notification when the job stops.
Job Failure	Sends a notification when the job is aborted because of lack of quorum due to one or more failed participants.
Participant Failure	Sends a notification when a participant timeout occurs, and the participant is taken out of session.
Participant Reconnect	Sends a notification when a participant reconnects to the job and the job resumes with the reconnected participant.
File Quarantine	Sends a notification when a file is marked as quarantined because a file conflict was not able to be resolved.
Scan Error	Sends a notification when an error occurs during the initial synchronization process .
Malicious Event	Sends a notification when Peer MED detects potentially malicious activity. For more information, see MED Configuration .

5. Select options in the **Queued Items** section.

Option	Description
Number of Queued Items section	<p>Select this checkbox if you want alerts to be sent regarding number of items in the queue. This is useful to notify you about when there is a queue backlog potentially due to latency issues.</p> <p>If you select this checkbox, you need to enter two values that work in tandem:</p> <ul style="list-style-type: none"> • Exceeds X Items - Enter the highest number of queued items before an email alert is sent. The default value is 5000. • Recovers Below X Items - Enter a value. The default value is 1000. <p>An notification is sent the first time that the Queued Items counter has items is greater than the value set in Exceeds X Items. The counter's value is displayed in the Queued Items column in the in the Collab, Sync, and Repl Summary view. The counter's value is a combination of the Real-time and File Sync queues.</p> <p>Another notification will not be sent until the Queued Items counter has dropped below the Recovers Below x Items value and then exceeds the Exceeds X Items value again. This prevents multiple or redundant alerts from being sent.</p>
Alert on Recovery	<p>Select this option if you want a notification to be sent when the number of queued items has fallen below the Recovers Below value.</p>
Size of Queued Items section	<p>Select this if you want notifications to be sent based on the total data size of queued items for a job. This is useful to notify you about when there is a queue backlog potentially due to bandwidth issues.</p> <p>If you select this checkbox, you need to enter two values that work in tandem.</p> <ul style="list-style-type: none"> • Exceeds X MB - Enter the highest number of queued items before an email alert is sent. The default value is 10240 MB. • Recovers Below X MB - Enter a value. The default value is 1024 MB . <p>An alert is sent the first time that the Pending Bytes for a job has items is greater than the value set in Exceeds X MB. The counter's value is displayed in the Pending Bytes column in the Collab, Sync, and Repl Summary view.</p>



3. Modify the options as needed.

Option	Description
Scan Item Limit	The maximum number of file and folder scan results that are returned in one scan iteration during a job's initial scan. This value is used to constrain the amount of memory used when performing initial scans with a large number of jobs.
Max Sync Work Queue Count	The per job maximum number of pending file synchronization tasks that are queued in memory before pausing the current scan. This value only has an effect on jobs with large numbers of files that must be synchronized during initial synchronization .
Max Number of Scan Threads	The maximum number of threads that can be created to scan folders and files. This number should be set to at least the number of jobs that you are running.
Max Number of Concurrent Scans	The maximum number of scan threads that can be actively working at the same time. This differs from the Max Number of Scan Threads in that not all created scan threads can be simultaneously doing work. For example, if 20 scan threads are configured but only 10 can run concurrently, 10 of the 20 threads will be paused at any one time, waiting for a time slot to continue working. Each of the 20 scan threads will get a chance to work in a round-robin fashion.

4. Click **Apply and Close** or **Apply**.

Scheduled Replication Filters

When you create a job, you can select existing scheduled replication filters to apply to the job or you can create new scheduled replication filters and apply them to the job. This [Preferences](#) page lists the existing scheduled replication filters. From this page, you can view, create, edit, and delete scheduled replication patterns. However, you cannot edit or delete a scheduled replication filter while it is applied to a job. See [Scheduled Replication](#) in the [Advanced Topics](#) section for more information about scheduled replication.

To create a scheduled replication filter:

1. Select **Preferences** from the **Window** menu.

Create Scheduled Replication Filter

Name:

Filter Type: Scheduled Replication

Included Patterns

Scheduling Options

Process every: 1 minute

Process on a schedule

Daily Weekly

Day(s):

Sunday

Monday

Tuesday

Wednesday

Thursday


Friday

Saturday

Time:

4. Enter a unique name for the filter.
5. Click **Add** under **Included Patterns** to enter a filter pattern for files that you want to delay replication. Repeat to add more filter patterns.

A **filter pattern** is a character string that defines a logical expression that is evaluated to determine which files and folders match the pattern. A filter pattern can contain complex regular expressions and wildcards.



The image shows a dialog box titled "Add Inclusion Pattern" with a close button (X) in the top right corner. The dialog contains the text "Enter a file name or path." followed by an empty text input field. Below the input field, the text "String cannot be empty." is displayed. At the bottom right of the dialog, there are two buttons: "OK" and "Cancel".

6. Click **OK**.

The pattern appears in the **Included Patterns** field.

Create Scheduled Replication Filter

Name:

Filter Type:

Included Patterns

.

Scheduling Options

Process every:

Process on a schedule

Daily Weekly

Day(s):

Sunday

Monday

Tuesday

Wednesday

Thursday


Friday

Saturday

Time:

7. Select a scheduling option:
 - **Interval** - Process at a specified interval.
 - **Schedule** - Process at a scheduled time.
8. After selecting a scheduling option, click **OK**.

The new filter is listed in the **Scheduled Replication** table and can now be applied to jobs.



3. Modify settings as needed.

Setting	Description
DFS Roots Folder	The default folder for namespace roots is C:\DFSRoots\. If you want a different folder to be used, enter the local path to the folder.
Timeout	Enter the number of seconds to wait for a response from any Agent. The default value is 120 seconds.
Namespace Checking Period	Enter the number of seconds to delay between checking namespace information calls. This check catches any changes made to a namespace using the Microsoft DFS Management tool. Selecting a low value will negatively affect performance but will

Setting	Description
	reflect changes to the user interface more quickly. The default value is 120 seconds.
Event Timeout	Enter the number of seconds to wait before marking an event containing DFS namespace information from the Agent as timed out. The default value is 120 seconds.
Namespace Checking Retries	Enter the maximum number of times for checking namespace information if the namespace is not found. Once the maximum number is exceeded, the job is stopped. The default value is 5 retries.
Namespace Search Timeout	When a user tries to import a namespace, PeerGFS searches for the namespace. This may take some time, depending on the environment. Enter the number of minutes to before timing out. The default value is 10 minutes.
Install DFS-N Management Tools	Select this option if you want Microsoft's DFS-N Management tools installed when creating or importing a namespace.
Show Resources	Select this option if you want to display individual namespace folders under each namespace in the Jobs view.

- Click **Apply and Close** or **Apply**.

Email Alerts

When you create a job, you can select existing email alerts to apply to the job or you can create new email alerts and apply them to the job. This [Preferences](#) page lists the existing email alerts. From this page, you can view, create, edit, and delete email alerts. However, you cannot edit or delete an email alert while it is applied to a job. See [Email Alerts](#) in the [Basic Concepts](#) section for more information about email alerts.

Note: An SMTP email connection must be configured before email alerts can be sent. See [Email Configuration](#) for information about configuring SMTP email settings.

To create an email alert:

4. Enter a name for the alert.
5. Select the event types to be alerted.

The event type determines what will trigger the email alert to be sent.

Event Type	Description
Job Start	Sends an alert when the job starts.
Job Stop	Sends an alert when the job stops.
Job Failure	Sends an alert when the job stops unexpectedly.
Participant Failure	Sends an alert when the Management Agent job disconnects or stops responding.


Event Type	Description
Participant Reconnect	Sends an alert when the Management Agent reconnects.

6. Select the DFS-N event types.

Event Type	Description
Namespace Offline	Sends an alert when a namespace goes offline.
Namespace Not Found	Sends an alert when a namespace is not found.
Folder Target Offline	Sends an alert when a folder target goes offline.
All Folder Targets Offline	Sends an alert when all folder targets go offline
DFS Server Offline	Sends an alert when a DFS server goes offline.


7. Enter the alert recipients, and then click **Add to List**.

The recipients are listed in the **Recipients** field.



3. Click the **Create** button.

The **Create SNMP Notification** dialog appears.



4. Select the types of events that will trigger the generation of an SNMP trap.

Event Type	Description
Job Start	Sends a notification when the DFS-N Management job starts.

Event Type	Description
Job Stop	Sends a notification when the DFS-N Management job stops.
Job Failure	Sends a notification when the DFS-N Management job stops unexpectedly.
Participant Failure	Sends a notification when the Management Agent of the DFS-N Management job disconnects or stops responding.
Participant Reconnect	Sends a notification when the Management Agent of the DFS-N Management job reconnects.


5. Select the DFS-N event types that will trigger the generation of an SNMP trap.

Event Type	Description
Namespace Offline	Sends a notification when a namespace goes offline.
Namespace Not Found	Sends a notification when a namespace is not found.
Folder Target Offline	Sends a notification when a folder target goes offline.
All Folder Target Offline	Sends a notification when all folder targets go offline

Event Type	Description
DFS Server Offline	Sends a notification when a DFS server goes offline.

6. Click **OK**.

The new notification is listed in the **SNMP Notifications** table and can now be applied to jobs.



7. Click **Apply and Close** or **Apply**.

Email Configuration

Before Peer Management Center can send emails on behalf of any job, a few key SMTP email settings must be configured. In addition, you can define contacts and distribution lists.

To configure email settings:

1. Select **Preferences** from the **Window** menu.
2. Select **Email Configuration** in the navigation tree.

The screenshot shows the 'Preferences' dialog box with the 'Email Configuration' section selected. The left sidebar lists various configuration categories, with 'Email Configuration' highlighted. The main area contains the following settings:

- SMTP Email Configuration**
 - *SMTP Host: smtp.office365.com
 - *SMTP Port: 587
 - Encryption:
 - *Encryption Type: TLS
 - *Username: debrag@peersoftware.com
 - *Password: [Redacted]
 - *Sender Email: debrag@peersoftware.com
 - Use Recommended Office 365 Settings:
 - Test Email Settings (button)
- Batch Email Alerts for Quarantined Files**
 - Batch Quiet Period (in seconds): 60
 - Maximum Number of Alerts: 1000

At the bottom of the dialog, there are three buttons: 'Apply and Close', 'Cancel', and 'Apply'.

3. Enter values for the following fields:

Field	Description
SMTP Host	Enter the host name or IP address of the SMTP mail server through which Peer Management Center will send emails.
SMTP Port	Enter the TCP/IP connection port (default is 25 and 465 for encryption) on which the mail server is hosting the SMTP service. We recommend that you leave the default setting unless your email provider specifies otherwise.
Encryption	Select this checkbox if the SMTP mail server requires an encrypted connection.
Encryption Type	If encryption is enabled, an encryption method must be selected. TLS and SSL are the available options. If you do not know which one your mail server requires, try one, and then the other.
Username	Enter the user name to authenticate as on the SMTP mail server.
Password	Enter the password for the user specified above.
Sender Email	Enter the email address to appear in the From field of any sent emails. This email address sometimes needs to have a valid account on the SMTP mail server.
Use Recommended Office 365 Settings	Select this checkbox if you are connecting to an Office 365 SMTP server. Follow Microsoft's Direct Send recommendations to set up email configuration with an Office 365 SMTP server.

- (Recommended) Click **Test Email Settings**, enter an email address, and then click **OK**.

It is highly recommended that you test your SMTP settings before saving them. You will be prompted for an email address to send the test message to. Upon submission, Peer Management Center will attempt to send a test message using the specified settings.

- Enter values for the fields in the **Batch Email Alerts for Quarantined Files** section:

Field	Description
Batch Quiet Period (in seconds)	Enter the number of seconds to wait before releasing a batch of alerts.
Maximum Number of Alerts	Enter the maximum number of alerts that should be sent in a single email.

6. Click **OK** or **Apply**.

General Configuration

The **General Configuration** settings affect the overall operation of Peer Management Center, Peer Agents, the Peer Broker, and other general operations. They are not specific to jobs or job types.

You can modify the following settings:

[General Configuration](#)

[Agent Connectivity](#)

[Broker Configuration](#)

[Email Alerts](#)

[Software Updates](#)

[Tags Configuration](#)


[Web and API Configuration](#)

General Configuration

To modify General Configuration settings:

1. Select **Preferences** from the **Window** menu.
2. Select **General Configuration** in the navigation tree.

The first page of the General Configuration options is displayed.



3. Modify the first four settings as needed:

Setting	Description
Launch Dashboard at Start	Select this option if you want the Dashboard to be automatically displayed when Peer Management Center is started.

Setting	Description
Launch Summary Views at Start	Select this option if you want the Summary views to be automatically displayed when Peer Management Center is started. Summary views will be displayed for all job types, even for job types without currently running jobs.
Always Run Tasks in Background	Select this option to run tasks like log gathering and Agent updates in the background, preventing these tasks from blocking the use of the Peer Management Center client while they run.
Auto Expand Job Resources	Select this option if you want all jobs with associated resources to start expanded in the Jobs view. Currently only available for Cloud Backup and Replication jobs and DFS-N Management jobs.
Display Job Types When No Jobs Are Configured	Select this option if you want to display a job type in the Jobs view, even when no jobs of that type have been configured.

4. Select options for alerts regarding the operation of Peer Management Center in the [Alerts view](#):

Option	Description
Severity	Select one of these options: <ul style="list-style-type: none"> • INFO • DEBUG • TRACE
Auto Display Alerts View	Select this option if you want the alerts to be automatically displayed in the Alerts view .

5. Select options for managing browsing files and folders on remote file systems in the **Browsing Files/Folders** section:


Option	Description
Remote Browser Page Size	Enter the maximum page size for the remote file system browser. This browser is used for selecting paths during the creation of most new jobs.
Show System Folders	Select this checkbox to show system folders in the remote file system browser.
Show Hidden Folders	Select this checkbox to show hidden folders in the remote file system browser.

6. (Optional) Enter the name of your PMC server or environment in the **Environment Name** field; if left blank, reports and dashboards will use the name of the PMC server.
7. Click **OK** or **Apply**.

Agent Connectivity

To modify Agent Connectivity settings:

1. Select **Preferences** from the **Window** menu.
2. Expand **General Configuration** in the navigation tree, and then select **Agent Connectivity**.



3. Modify the settings as needed:

Option	Description
Missed Heartbeats before Agent Disconnect	Enter the maximum number of heartbeats that can be missed on a host before Peer Management Center labels the Agent as disconnected. If a running job hits a timeout when communicating with a specific Agent, Peer Management Center will check this status to decide if the Agent should be dropped from the job.
Check Agent Availability Frequency (in seconds)	Enter the frequency (in seconds) that Peer Management Center should check whether an Agent is back online.
Minimum Number of Minutes Between Reconnects	Enter the minimum number of minutes that must elapse before Peer Management Center attempts to retry reconnecting to the Agent.
Maximum Number of Consecutive Reconnect Attempts	Enter the maximum number of attempts that Peer Management Center tries to reintegrate a previously connected agent into one or more jobs. Once the maximum number of attempts has been reached, you must manually reintegrate the Agent into affected jobs, typically by restarting the affected jobs.

4. Click **OK** or **Apply**.


Broker Configuration

The **Broker Configuration** page displays a non-editable field that shows the URL used by the Peer Management Center service to connect to the Broker service.

To view the Broker Configuration URL:

1. Select **Preferences** from the **Window** menu.

2. Expand **General Configuration** in the navigation tree, and then select **Broker Configuration**.



3. Click **OK** or **Apply**.

Email Alerts


System email alerts notify recipients when certain types of system events occur, for example, low memory, low disk space, disconnected agents. This [Preferences](#) page lists the existing system email alerts. From this page, you can create, edit, and delete system email alerts. You can also disable and enable alerts. See [Email Alerts](#) in the [Basic Concepts](#) section for more information about email alerts.

Note: An SMTP email connection must be configured before email alerts can be sent. See [Email Configuration](#) for information about configuring SMTP email settings.

To create a system email alert:


1. Select **Preferences** from the **Window** menu.
2. Expand **General Configuration** in the navigation tree, and then select **Email Alerts**.

Any existing system email alerts are listed in the **Email Alerts** table.



3. Click **Create**.

The **Create Email Alert** dialog appears.



4. Enter a name for the alert.
5. Select the **Enable** checkbox if you want to enable the alert.


If you choose not to enable the alert, you can enable it later.

6. Select the type of events for which you want alerts sent:

Event Type	Description
Low Memory	Sends an alert when Peer Management Center or connected Agent services are low on memory.
Low PMC Disk Space	Sends an alert when the space on the disk where Peer Management Center software is installed running low.
Agent Install Disk Space	Sends an alert when the space on the disk where the Peer Agent software is installed is running low.
Agent Disconnects	Sends an alert whenever an Agent is disconnected.
License Warnings	Sends an alert when a license has expired or when a license violation is about to occur (for example, when storage usage reaches 95% of maximum storage and when storage usage exceed license limits).

7. Enter alert recipients, and then click **Add to List**.
8. Click **OK** or **Apply**.

The new alert is listed in the **Email Alerts** table.




Software Updates

You can configure Peer Management Center to automatically check for updates and download the updates. Peer Management Center checks for updates every evening at 11 p.m. local time. Only minor updates are automatically downloaded; if a major update is available, a notification appears. Major releases require a new license key and must be requested from Peer Software Support.

You can also manually check for updates. See [Updating Peer Management Center](#) for information about manually checking for updates.

To configure Peer Management Center to automatically check for updates:

1. Select **Preferences** from the **Window** menu.
2. Expand **General Configuration** in the navigation tree, and then select **Software Updates**.




3. Select update options:

- **Automatically check for updates and notify me** - Select this option if you want to automatically check for updates.
- **Download new updates automatically and notify me when they are ready to be installed** - Select this option if you want to automatically check for and download available updates.

4. Click **OK** or **Apply**.

Whenever updates are available, a notification appears in the lower right corner of Peer Management Center.



5. Click the notification to review and proceed with the update. See [Updating Peer Management Center](#) for details.


Tags Configuration

The **Tags Configuration** page in Preferences is the starting place for creating [tags](#) and categories that can later be assigned to resources. See [Assigning Tags](#) for more information about assigning to resources.

To create a tag:


1. Select **Preferences** from the **Window** menu.
2. Expand **General Configuration** in the navigation tree, and then select **Tags Configuration**.

Any existing tags are listed in the **Tags** table.



3. Click the **Create** button.

The **New Tag** dialog appears.



4. Enter a name for a tag.
5. Select a category or create a new category.
6. Click **OK**.

The tag appears in the **Tags** table.


7. Click **OK** or **Apply**.

Web and API Configuration

As part of the Peer Management Center installation process, you are prompted to configure access to the web and API services. If you do not enable access during the initial installation or want to modify settings at a later date, you can modify them in [Web and API Configuration](#) in [Preferences](#).

To modify web and API settings:

1. Select **Preferences** from the **Window** menu.
2. Expand **General Configuration** in the navigation tree, and then select **Web and API Configuration**.



3. Modify the configuration options.

Option	Description
Hostname or IP	<p>Enter the hostname or IP address via which the services can be accessed:</p> <ul style="list-style-type: none"> • Enter localhost or 127.0.0.1 if you want the services to be accessible only to users of the local server via the loopback interface.

Option	Discription
	<ul style="list-style-type: none">• Enter 0.0.0.0 to make the services accessible via all network interfaces.• Enter a specific IP address to restrict access to a specific network interface.
Enable HTTPS Web Access	Select this checkbox to enable HTTP access to the web service using the specified port.
Enable HTTPS REST API	Select this checkbox to enable HTTPS access to the REST API service using the specified port.

4. Click **OK** or **Apply**.

Licensing

Peer Global File System is licensed by the number of unique [participants](#) and by the number of terabytes in the [watch set](#).


Installing or Upgrading a License File

After purchasing or requesting a trial download of Peer Management Center, you will receive a license file representing your purchase or trial.

To install a new license file or upgrade an existing license:


1. From the **Window** menu, select **Preferences**.
2. Select **Licensing** in the navigation tree.

Existing valid licenses are listed in the **Peer Software Licensing Configuration** table.



3. Click the **Add/Update** button to browse for a license file.
4. Select the license file, and then click **Open**.

If you are prompted with a message that an existing license already exists, click **Yes** to overwrite the existing license.



After successful installation of the license, it is listed in the table, along with the license quantity, version, and an expiration date (if applicable). You can now create, configure, and run jobs using the new license.

Note: You will need to restart existing jobs if any of the following applies:

- Software version is different (typically when upgrading to a new version).
 - Software package level is different.
 - New license is insufficient for the number of existing hosts.
5. Click the license in the table to view details about the license.
 6. Click **OK** or **Apply**.

Deleting a License File

To delete a license.

1. From the **Windows** menu, select **Preferences**.
2. Select **Licensing** in the navigation tree.
3. Select the license you want to delete.
4. Click the **Delete** button

Any job types enabled by that license will be hidden from Peer Management Center.


MED Configuration

Peer's Malicious Event Detection (MED) real-time engine can spot unwanted activity being executed on storage platforms by ransomware, viruses, malware, hackers, or rogue users. MED technology provides alerting capabilities, as well as the ability to minimize the amount of encrypted or deleted content from being replicated to remote locations. Once MED is enabled and jobs are restarted, these capabilities apply to all jobs. For more information, see our knowledge base article [Introduction to Peer MED](#).

Peer MED deploys three different mechanisms for spotting malicious activity, each of which can be enabled and tuned independently. These settings are configured on a global level.


To modify MED settings:

1. From the **Window** menu, select **Preferences**.
2. Select **MED Configuration** in the navigation tree.



3. Select the **Enable Default Settings** or click **Show Advanced Settings**.

If you selected **Show Advanced Settings**, the following is displayed.



4. Modify the options as needed:

- [Primary MED Options](#)
- [Bait File Advanced Options](#)
- [Trap Folders Advanced Options](#)

5. Click **OK**.

Primary MED Options

The main options are as follows:

Option	Description
Enable Default Settings	Enables/disables Peer MED using default settings. By default, all three MED mechanisms are enabled.
Show/Hide Advanced Settings	Shows/hides options for each of the three MED mechanisms.
Enable Malicious Event Detection (MED)	The master on/off switch for MED. If unchecked, all MED mechanisms will be disabled.
Restore Default Settings	Restores all defaults across the three MED mechanisms.

Bait File Advanced Options

Bait files are files of common types, inserted into the file system in a way that hides them from users. Though hidden, these bait files are likely to be accessed by automated processes (like ransomware) or by mass deletions of entire folder structures. As soon as these files are touched, an action is triggered.

The options for bait files are:

Option	Description
Enable Bait Files	Enables/disables bait file creation and monitoring.
Add Bait Files to shares	At the start of each job, creates bait files under the root of each participant's watch directory. To see the watch directory for a job, review Host Participants and Directories .

Option	Description
Trigger Action	Defines the action to take when MED detects malicious activity on a bait file. See Action Types for more details on available actions.

Action Types

For each MED mechanism, one of four actions can be configured on the detection of malicious activity. These actions are:

Action	Description
Alert Only	<p>Triggers an alert in Peer Management Center.</p> <p>If email alerts are configured for MED Alerts and enabled for a job, an email will also be sent. See Email Alerts in the Basic Concepts section for more information about email alerts.</p> <p>If SNMP traps are configured for MED Alerts and enabled for a job, an SNMP trap will also be sent. See SNMP Notifications in the Basic Concepts section for more information about SNMP notifications.</p>
Alert and Disable Host	Triggers an alert while also removing the afflicted Agent from the job in which the malicious activity was detected. Once disabled, Agents will need to be manually re-enabled for collaboration to resume. See Re-enabling a Disabled Agent Within a Job for details.
Alert and Stop Job	Triggers an alert while also stopping the job where the malicious activity was detected. Jobs will need to be restarted in order for collaboration to resume.
Alert, Disable Host and Stop Job	Triggers an alert, removes the afflicted Agent from the job where the malicious activity was detected, and stops the job. This option is the most aggressive and will require administrators to re-enable Agents as well as restart jobs. See Re-enabling a Disabled Agent Within a Job for details.

An example of an alert as displayed in Peer Management Center is as follows:

Peerlet Advisory Alert Details	
Received Date:	03-12-2018 19:23:26
Severity:	FATAL
Category:	Event Detection
Host Name:	DelIT110a
Locally Created at:	03-12-2018 19:23:26
Message:	Malicious Event Detection (MED) - Bait File Alert (Alert Only: Please check for unwanted activity) Alert Message info=BAIT FILE ALERT appld=113, appSessionId=142 path= See Message Field msg= TriggerAlertFileFound: Path=\\svm9x-1\cifs1\Departments\Sales\pc-med_bin\Doc_000-med.docx - EventName: RENAME details= Participant Detected=DelIT110a Alert Message= TriggerAlertFileFound: Path=\\svm9x-1\cifs1\Departments\Sales\pc-med_bin\Doc_000-med.docx - EventName: RENAME Time Detected= Mon Mar 12 19:23:26 EDT 2018 User Detected=MattM IP Detected=Doc_000-med.docx Process Detected=SMBVersion=31 Share Detected= cifs1 Job Session ID=3248744344
Class Name:	WatchDirectoryOperations
App Session Key:	142
Error Code:	2520
Action:	Alert Only

Click outside of popup to close

Trap Folders Advanced Options

On Windows file servers, Peer MED can be configured to create hidden, recursive folders that attempt to trap or slowdown ransomware as it enumerates a folder structure. As with the bait files, these folders cannot be seen by users but will be accessible by automated processes. If bait files (above) are enabled, a bait file will be placed within each trap folder, and an action will be triggered as soon as these files are touched.

Options for trap folders are:

Option	Description
Enable Trap Folders	Enables/disables the creation and monitoring of trap folders.

Option	Description
Add Trap Folders to shares	At the start of each job, create trap folders under the root of each participant's configured watch directory. To see the watch directory for a job, review Host Participants and Directories . Note: Trap Folders will only be used with participants that are Windows file servers. As such, these settings will not apply to any other enterprise NAS device.

NAS Configuration

This section contains information about configuring your NAS for use with Peer Global File System:

- [Amazon FSxN Configurations](#)
- [Dell EMC Configurations](#)
- [NetApp 7-Mode Configurations](#)
- [NetApp cDOT Configurations](#)
- [Nutanix Configurations](#)

Amazon FSxN Configurations

Peer Management Center supports the ability to include content from CIFS/SMB shares on one or more Amazon FSxN file system within most available job types. In order to work with Amazon FSxN, Peer Management Center leverages the FPolicy API built into the NetApp operating system that powers FSxN. For detailed information about Amazon FSxN prerequisites and configuration, see [Amazon FSxN Prerequisites](#).

To create a new Amazon FSxN configuration:

1. Select **Preferences** from the **Window** menu.
2. Select **NAS Configuration** in the navigation tree.

Storage Information
Enter the required information to connect to the storage

Management Agent
Storage Information

Credentials

*SVM Name:

*SVM User Name:

*SVM Password:

SVM Management IP:

*Peer Agent IP:

Advanced

Validate You must enter the name.

Having trouble connecting? Please verify that all [prerequisites](#) are met for Amazon FsxN environments.

< Back Next > Finish Cancel

6. Enter the required values in **Credentials**.

Field	Description
SVM Name	Enter the name, FQDN, or IP address of the Storage Virtual Machine hosting the data to be replicated.
SVM Username	Enter the user name for the account managing the Storage Virtual Machine. This must not be a cluster management account.
SVM Password	Enter the password for the account managing the Storage Virtual Machine. This must not be a cluster management account.
SVM Management IP	Enter the IP address used to access the management API of the Storage Virtual Machine. If the data LIFs (Logical Interfaces) corresponding to the SVM Name above already allow management access, this field is not required.
Peer Agent IP	Select the IP address of the server hosting the Agent that manages the Storage Virtual Machine. The Storage Virtual Machine must be able to route traffic to this IP address. If the IP address you want does not appear, manually enter the address.

7. (Optional) Click [Advanced](#) and enter the required values.
8. Click **Validate**.
9. Click **Next**.
10. Click **OK**.

The following configuration options are available for AmazonFSxN devices:

Amazon FSxN Options

Advanced FPolicy FSxN Settings for host: DGAgent1 and SVM: SVM-12

*SVM Username:

*SVM Password:

SVM Management IP:

*Agent IP for SVM Conn.:

Filtered Extensions:

Admin Share Override:

Additional Properties:

NOTE: Any changes made to these Advanced FPolicy FSxN Settings will be used with every other session in which this FPolicy Server is connecting to the same Storage Virtual Machine.

Validate OK Cancel

Option	Description
SVM Username	The account name of the VSAdmin or similar account on the SVM that has the appropriate access to ONTAPI.
SVM Password	The password of the VSAdmin or similar account on the SVM that has the appropriate access to ONTAPI. This value will be encrypted.
SVM Management IP	Optional. If the primary data LIF for the SVM (whose IP address is registered in DNS) does not support management calls, enter the management IP address of SVM.
Agent IP for SVM Conn.	The IP address over which this Peer Agent will connect to the configured SVM. This MUST be an IP address.
Filtered Extensions	Optional. A comma-separated list of file extensions to exclude (without a leading asterisk (*)).
Admin Share Override	Optional. Enter the administrative-type share that you created on the cDOT SVM. To take advantage of performance improvements when using this option, the share must be created at the root of the SVM's namespace (/). Ideally it should be named to something similar to PMCSave\$ to prevent users from being able to see it.


Dell EMC Configurations

Peer Management Center supports the ability to include content from CIFS/SMB shares on one or more Dell EMC storage devices within most available job types. These Dell EMC devices can be running PowerScale/Isilon, Unity, or VNX. For detailed information about Dell EMC prerequisites, see [Dell EMC Prerequisites](#).

To create a new Dell EMC configuration:


1. Select **Preferences** from the **Window** menu.
2. Select **NAS Configuration** in the navigation tree.
3. Select **Dell EMC Configurations**.

The **Dell EMC Configurations** page is displayed. It lists any existing configurations.



4. Click the **Create** button.

The **Management Agent** page appears.



5. Select a Management Agent, and then click **Next**.

The **Storage Information** page appears. The fields in the **Credentials** section vary, depending on the selected platform type; VNX is selected by default.

Storage Information

Enter the required information to connect to the storage

Management Agent
Storage Information

Credentials

Device Type: VNX

*CIFS Server Name:

*Control Station Username:

*Control Station Password:

*Control Station IP:

Advanced

Validate You must enter the name.

Having trouble connecting? Please verify that all [prerequisites](#) are met for Dell EMC VNX/Celerra environments.

< Back Next > Finish Cancel

6. Select the device type, and then enter the required values in **Credentials**:

[Dell PowerScale | EMC Isilon Credentials](#)

[Dell EMC Unity Credentials](#)

[Dell EMC VNX Credentials](#)

7. (Optional) Click the **Advanced** button if you want to specify advanced options, and then enter the required values:

[Dell PowerScale | EMC Isilon Advanced Options](#)

[Dell EMC Unity Advanced Options](#)

[Dell EMC VNX Advanced Options](#)

8. Click **Validate**.

9. Click **Next**.
10. Click **OK**.

1. Enter the required values.

Field	Description
Cluster Name	Enter the name of the PowerScale or Isilon cluster hosting the data to be replicated.
Cluster Username	Enter the user name for the account managing the PowerScale or Isilon cluster.

Field	Description
Cluster Password	Enter the password for account managing the PowerScale or Isilon cluster.
Cluster Management IP	Enter the IP address of the system used to manage the PowerScale or Isilon cluster. Required only if multiple Access Zones are in use on the cluster.

2. (Optional) Click [Advanced](#) and enter the required values.
3. Click **Validate**.
4. Click **Finish**.

Dell PowerScale | EMC Isilon Advanced Options

The options are divided into two groups:

- [Dell PowerScale | EMC Isilon Options for this job](#)
- [Dell PowerScale | EMC Isilon Advanced Settings](#)

Dell EMC PowerScale | Isilon Options

Dell EMC PowerScale | Isilon Options for this Job

Filter open/close events from these users:

Filter all events from these users:

Filter events from these IP Addresses:

Access Event Suppression Time:

Advanced Settings for Agent DGAgent1 and Dell EMC PowerScale | Isilon: CLUSTER 1

Filtered IP Addresses:

Nodes:

Audit Cluster Name:

Cluster IP:

Cluster Port:

*Cluster Username:

*Cluster Password:

Cluster Access Zone:

Validate Cluster:

Update CEE Log Time:

NOTE: Any changes made to these Advanced Dell EMC Settings will be used with every other session in which this CEE Event Server is connecting with a Dell EMC storage device.

Validate OK Cancel

Dell PowerScale | EMC Isilon Options for this Job

The following configuration options are available for Dell PowerScale | EMC Isilon devices jobs:

Option	Description
Filter open/close events from these users	A comma-separated list of user names to exclude from access event detection. For example, if "USER1" is excluded, any access event activity generated by USER1 will be ignored, e.g., file is opened and closed.
Filter all events from these users	A comma-separated list of user names to exclude from all event detection. For example, if "USER"1 is excluded, any activity generated by USER1 will be ignored, e.g., file is open and modified.
Filter events from these IP Addresses	A comma-separated list of IP addresses to exclude from all event detection. For example, if "192.168.0.100" is excluded, any activity generated by 192.168.0.100 will be ignored, e.g., file is open and modified.
Access Event Suppression Time	Represents the number of seconds that an open event will be delayed before being processed. Used to help reduce the amount of chatter generated by Windows clients when mousing over files in Windows Explorer. The default value is -1, which will be adjusted based on the selected NAS platform. A value of 0 will allow for dynamic changes to the amount of time that an open event will be delayed based on the load of the system.

Dell PowerScale | EMC Isilon Advanced Settings

The following advanced settings are available for Dell PowerScale | EMC Isilon devices:

Option	Description
Filtered IP Addresses	Optional. Events generated from these IP addresses will be filtered. It is recommended that the IP address of the CEE Server is added to this list.
Nodes	Optional. Comma-delimited listed of additional node IP address to query for open files. These addresses must be accessible from the CEE Server where the Agent is running.
Audit Cluster Name	Optional. The hostname that is set in the PowerScale or Isilon audit system configuration.
Cluster IP	Optional. The cluster IP address of the PowerScale or Isilon system.
Cluster Port	Optional. The cluster port number of the PowerScale or Isilon system. Default value is 8080.
Cluster Username	The user name used to sign into the PowerScale or Isilon cluster.
Cluster Password	The password used to sign into the PowerScale or Isilon cluster.
Cluster Access Zone	Optional. The name of the access zone that is being monitored.
Validate Cluster	If enabled, the cluster will be validated both on registration and periodically by a maintenance thread.
Update CEE Log Time	If enabled, the audit log time on the PowerScale or Isilon cluster will be set to the start time of the first job to communicate with this Isilon cluster.

1. Enter the required values.

Storage Information
Enter the required information to connect to the storage

Management Agent
Storage Information

Credentials

Device Type: Unity

*CIFS Server Name:

*Unisphere Username:

*Unisphere Password:

*Unisphere Management IP:

Advanced

Validate You must enter the name.

Having trouble connecting? Please verify that all [prerequisites](#) are met for Dell EMC Unity environments.

< Back Next > Cancel

Field Description	Description
CIFS Server Name	Enter the name of the CIFS server hosting the data to be replicated.
Unisphere Username	Enter the user name for the Unisphere account managing the Unity storage device.
Unisphere Password	Enter the password for the Unisphere account managing the Unity storage device.


Field Description	Description
Unisphere Management IP	Enter the IP address of the Unisphere system used to manage the Unity storage device. This should not point to the NAS server.

2. (Optional) Click [Advanced](#) and enter the required values.
3. Click **Validate**.
4. Click **Finish**.

Dell EMC Unity Advanced Options

The options are divided into two groups:

- [Dell EMC Unity Options for this Job](#)
- [Dell EMC Unity Advanced Settings](#)



Dell EMC Unity Options

Dell EMC Unity Options for this Job

Filter open/close events from these users:

Filter all events from these users:

Filter events from these IP Addresses:

Access Event Suppression Time:

Advanced Settings for Agent DGAgent1 and Dell EMC Unity:UNITY1

Filtered IP Addresses:

*Unisphere Management IP:

Unisphere Management Port:

*Unisphere Username:

*Unisphere Password:

Validate Unisphere:

NOTE: Any changes made to these Advanced Dell EMC Settings will be used with every other session in which this CEE Event Server is connecting with a Dell EMC storage device.

OK Cancel

Dell EMC Unity Options for this Job

The following configuration options are available for EMC Unity devices:

Option	Description
Filter open/close events from these users	A comma-separated list of user names to exclude from access event detection. For example, if "USER1" is excluded, any access event activity generated by USER1 will be ignored, e.g., file is opened and closed.
Filter all events from these users	A comma-separated list of user names to exclude from all event detection. For example, if "USER1" is excluded, any activity generated by USER1 will be ignored, e.g., file is open and modified.
Filter events from these IP Addresses	A comma-separated list of IP addresses to exclude from all event detection. For example, if "192.168.0.100" is excluded, any activity generated by 192.168.0.100 will be ignored, e.g., file is open and modified.
Access Event Suppression Time	Represents the number of seconds that an open event will be delayed before being processed. Used to help reduce the amount of chatter generated by Windows clients when mousing over files in Windows Explorer. The default value is -1, which will be adjusted based on the selected NAS platform. A value of 0 will allow for dynamic changes to the amount of time that an open event will be delayed based on the load of the system.

Dell EMC Unity Advanced Settings

The following advanced settings are available for Dell EMC Unity devices:

Option	Description
Filtered IP Addresses	Optional. Events generated from these IP addresses will be filtered. It is recommended that the IP address of the CEE Server is added to this list.
Unisphere Management IP	The Unisphere Management IP address of the Unity system. This address is used for making API calls to validate configuration.
Unisphere Management Port	Optional. The Unisphere Management port number of the Unity system. Default value is 443.
Unisphere Username	The user name used to sign into Unisphere.
Unisphere Password	The password used to sign into Unisphere.
Validate Unisphere	Optional. If enabled, Unisphere settings will be validated both on registration and periodically by a maintenance thread.

1. Enter the required values.

Storage Information
Enter the required information to connect to the storage

Management Agent
Storage Information

Credentials

Device Type: VNX

*CIFS Server Name:

*Control Station Username:

*Control Station Password:

*Control Station IP:

Advanced

Validate You must enter the name.

Having trouble connecting? Please verify that all [prerequisites](#) are met for Dell EMC VNX/Celerra environments

< Back Next > Cancel

Field	Description
CIFS Server Name	Enter the name of the CIFS Server hosting the data to be replicated.
Control Station Username	Enter the user name for the Control Station account managing the VNX/Celerra storage device.
Control Station Password	Enter the password for the Control Station account managing the VNX/Celerra storage device.

Field	Description
Control Station IP	Enter the IP address of the Control Station system used to manage the VNX/Celerra storage device. This should not point to the CIFS Server.

2. (Optional) Click [Advanced](#) and enter the required values.
3. Click **Validate**.
4. Click **Finish**.

Dell EMC VNX/Celerra Advanced Options

The options are divided into two groups:

- [Dell EMC VNX Options for this Job](#)
- [Dell EMC VNX Advanced Settings](#)

Dell EMC VNX Options

Dell EMC VNX Options for this Job

Filter open/close events from these users:

Filter all events from these users:

Filter events from these IP Addresses:

Access Event Suppression Time:

Advanced Settings for Agent DGAgent1 and Dell EMC VNX:VNX1

Filtered IP Addresses:

*Control Station IP:

Control Station Port:

*Control Station Username:

*Control Station Password:

Validate Control Station:

NOTE: Any changes made to these Advanced Dell EMC Settings will be used with every other session in which this CEE Event Server is connecting with a Dell EMC storage device.

OK Cancel

Dell EMC VNX/Celerra Options for this Job

The following configuration options are available for Dell EMC VNX/Celerra devices:

Option	Description
Filter open/close events from these users	A comma-separated list of user names to exclude from access event detection. For example, if "USER1" is excluded, any access event activity generated by USER1 will be ignored, e.g., file is opened and closed.
Filter all events from these users	A comma-separated list of user names to exclude from all event detection. For example, if "USER1" is excluded, any activity generated by USER1 will be ignored, e.g., file is open and modified.
Filter events from these IP Addresses	A comma-separated list of IP addresses to exclude from all event detection. For example, if "192.168.0.100" is excluded, any activity generated by 192.168.0.100 will be ignored, e.g., file is open and modified.
Access Event Suppression Time	Represents the number of seconds that an open event will be delayed before being processed. Used to help reduce the amount of chatter generated by Windows clients when mousing over files in Windows Explorer. The default value is -1, which will be adjusted based on the selected NAS platform. A value of 0 will allow for dynamic changes to the amount of time that an open event will be delayed based on the load of the system.

Dell EMC VNX/Celerra Advanced Settings

The following advanced settings are available for Dell EMC VNX/Celerra devices:

Option	Description
Filtered IP Addresses	Optional. Events generated from these IP addresses will be filtered. It is recommended that the IP address of the CEE Server is added to this list.
Control Station IP	The Control Station IP address of the VNX/Celerra system.
Control Station Port	Optional. The Control Station Port number of the VNX/Celerra system. The default value is 443.
Control Station Username	The user name used to sign into the VNX/Celerra Control Station.
Control Station Password	The password used to sign into the VNX/Celerra Control Station.
Validate Control Station	Optional. If enabled, the VNX/Celerra Control Station will be validated both on registration and periodically by a maintenance thread.


NetApp 7-Mode Configurations

Peer Management Center supports the ability to include content from CIFS/SMB shares on one or more NetApp storage devices within most available job types. These NetApp devices can be running Data ONTAP 7-Mode or clustered Data ONTAP. In order to work with NetApp devices, Peer Management Center leverages the FPolicy API built into the NetApp device. For detailed information about NetApp prerequisites and configuration, see [NetApp Prerequisites](#).

To create a new NetApp 7-Mode configuration:


1. Select **Preferences** from the **Window** menu.
2. Select **NAS Configuration** in the navigation tree.
3. Select **NetApp 7-Mode Configurations**.

The **NetApp 7-Mode Configurations** page is displayed. It lists any existing configurations.



4. Click the **Create** button.

The **Management Agent** page appears.



5. Select a Management Agent, and then click **Next**.

The **Storage Information** page appears.

Storage Information
Enter the required information to connect to the storage

Management Agent
Storage Information

Credentials
*Filer/vFiler Name:

Advanced

Validate You must enter the name.

Having trouble connecting? Please verify that all [prerequisites](#) are met for NetApp 7-Mode environments.

< Back Next > Finish Cancel


6. Enter the required values in **Credentials**.

Field	Description
File Name	Enter the name of the NetApp 7-Mode filer or vFiler hosting the data to be replicated.

7. (Optional) Click [Advanced](#) and enter the required values.
8. Click **Validate**.
9. Click **Next**.
10. Click **OK**.

The options are divided into two groups:

- [NetApp 7-Mode Options for this Job](#)
- [NetApp FPolicy 7-Mode Advanced Settings](#)



The image shows a dialog box titled "NetApp Options". It is divided into two main sections. The first section, "NetApp Options for this Job", contains four input fields: "Filter open/close events from these users:", "Filter all events from these users:", "Filter events from these IP Addresses:", and "Access Event Suppression Time:" (with a spinner control set to 0). Below these fields is a note: "A '*' represents a required configuration item." The second section, "Advanced (Optional) FPolicy Settings for: DGAgent1", contains an "Excluded Extensions:" input field, a section for "Include or Exclude Volumes" with radio buttons for "Include" (selected) and "Exclude", and a list box with "Add", "Edit", and "Delete" buttons. At the bottom of this section is a bold note: "NOTE: Any changes made to these Advanced FPolicy Settings will be used with every other session in which this FPolicy Server is connecting with a NetApp Filer." The dialog box has "Validate", "OK", and "Cancel" buttons at the bottom.

NetApp 7-Mode Options for this Job

The following configuration options are available for NetApp 7-Mode devices:

Option	Description
Filter open/close events from these users	A comma-separated list of user names to exclude from access event detection. For example, if "USER1" is excluded, any access event activity generated by USER1 will be ignored, e.g., file is opened and closed.
Filter all events from these users	A comma-separated list of user names to exclude from all event detection. For example, if "USER1" is excluded, any activity generated by USER1 will be ignored, e.g., file is open and modified.
Filter events from these IP Addresses	A comma-separated list of IP addresses to exclude from all event detection. For example, if "192.168.0.100" is excluded, any activity generated by 192.168.0.100 will be ignored, e.g., file is open and modified.
Access Event Suppression Time	Represents the number of seconds that an open event will be delayed before being processed. Used to help reduce the amount of chatter generated by Windows clients when mousing over files in Windows Explorer. The default value is -1, which will be adjusted based on the selected NAS platform. A value of 0 will allow for dynamic changes to the amount of time that an open event will be delayed based on the load of the system.

NetApp FPolicy 7-Mode Advanced Settings

Option	Description
Excluded Extensions	<p>Extensions entered here are excluded from event detection on the NetApp Filer. Values are comma-separated and must not contain any periods.</p> <p>FPolicy enables you to restrict a policy to a certain list of file extensions by excluding extensions that need to be screened.</p> <p>Note: The maximum length of a file name extension supported for screening is 260 characters. Screening by extensions is based only on the characters after the last period (.) in the file name. For example, for a file named fle1.txt.name.jpg, file access notification takes place only if a file policy is configured for the jpg extension.</p>
Include or Exclude Volumes	<p>List all volumes on the NetApp Filer to exclude or include based on selected choice.</p> <p>FPolicy enables you to restrict a policy to a certain list of volumes by including or excluding volumes that need to be screened.</p> <p>Using the include list, you can request notifications for the specified volume list. Using the exclude list, you can request notifications for all volumes except the specified volume list. However, by default, both the include and exclude list are empty.</p> <p>You can use the question mark (?) or asterisk (*) wildcard characters to specify the volume. The question mark (?) wildcard character stands for a single character. For example, entering vol? in a list of volumes that contain vol1, vol2, vol23, vol14, will result in only vol1 and vol2 being matched.</p> <p>The asterisk (*) wildcard character stands for any number of characters that contain the specified string. Entering *test* in a list of volumes to exclude from file screening excludes all volumes that contain the string such as test_vol and vol_test.</p>


NetApp cDOT Configurations

Peer Management Center supports the ability to include content from CIFS/SMB shares on one or more NetApp storage devices within most available job types. These NetApp devices can be running Data ONTAP 7-Mode or clustered Data ONTAP. In order to work with NetApp devices, Peer Management Center leverages the FPolicy API built into the NetApp device. For detailed information about NetApp prerequisites and configuration, see [NetApp Prerequisites](#).

To create a new NetApp cDOT configuration:


1. Select **Preferences** from the **Window** menu.
2. Select **NAS Configuration** in the navigation tree.
3. Select **NetApp cDot Configurations**.

The **NetApp cDOT Configurations** page is displayed. It lists any existing configurations.



4. Click the **Create** button.

The **Management Agent** page appears.



5. Select a Management Agent, and then click **Next**.

The **Storage Information** page appears.

Storage Information
Enter the required information to connect to the storage

Management Agent
Storage Information

Credentials

*SVM Name:

*SVM User Name:

*SVM Password:

SVM Management IP:

*Peer Agent IP:

Advanced

Validate You must enter the name.

Having trouble connecting? Please verify that all [prerequisites](#) are met for NetApp ONTAP/cDOT environments.


< Back Next > Cancel

6. Enter the required values in **Credentials**.

Field	Description
SVM Name	Enter the name, FQDN, or IP address of the Storage Virtual Machine hosting the data to be replicated.
SVM Username	Enter the user name for the account managing the Storage Virtual Machine. This must not be a cluster management account.
SVM Password	Enter the password for the account managing the Storage Virtual Machine. This must not be a cluster management account.
SVM Management IP	Enter the IP address used to access the management API of the Storage Virtual Machine. If the data LIFs (Logical Interfaces) corresponding to the SVM Name above already allow management access, this field is not required.
Peer Agent IP	Select the IP address of the server hosting the Agent that manages the Storage Virtual Machine. The Storage Virtual Machine must be able to route traffic to this IP address. If the IP address you want does not appear, manually enter the address.

7. (Optional) Click [Advanced](#) and enter the required values.
8. Click **Validate**.
9. Click **Next**.
10. Click **OK**.

The following configuration options are available for NetApp cDOT devices:



The image shows a dialog box titled "NetApp Options" with a standard Windows window title bar (minimize, maximize, close). The dialog contains a section titled "Advanced FPolicy cDot Settings for host: DGAgent1 and SVM: SVM 1". Below this title are several input fields: "*SVM Username:" (text box), "*SVM Password:" (password box), "SVM Management IP:" (text box), "*Agent IP for SVM Conn.:" (dropdown menu), "Filtered Extensions:" (text box), "Admin Share Override:" (text box), and "Additional Properties:" (text box). At the bottom of the dialog, there is a "NOTE: Any changes made to these Advanced FPolicy cDot Settings will be used with every other session in which this FPolicy Server is connecting to the same Storage Virtual Machine." Below the note are three buttons: "Validate", "OK", and "Cancel".

NetApp Options

Advanced FPolicy cDot Settings for host: DGAgent1 and SVM: SVM 1

*SVM Username:

*SVM Password:

SVM Management IP:

*Agent IP for SVM Conn.:

Filtered Extensions:

Admin Share Override:

Additional Properties:

NOTE: Any changes made to these Advanced FPolicy cDot Settings will be used with every other session in which this FPolicy Server is connecting to the same Storage Virtual Machine.

Validate OK Cancel

Option	Description
SVM Username	The account name of the VSAdmin or similar account on the SVM that has the appropriate access to ONTAPI.
SVM Password	The password of the VSAdmin or similar account on the SVM that has the appropriate access to ONTAPI. This value will be encrypted.
SVM Management IP	Optional. If the primary data LIF for the SVM (whose IP address is registered in DNS) does not support management calls, enter the management IP address of SVM.
Agent IP for SVM Conn.	The IP address over which this Peer Agent will connect to the configured SVM. This MUST be an IP address.
Filtered Extensions	Optional. A comma-separated list of file extensions to exclude (without a leading asterisk (*)).
Admin Share Override	Optional. Enter the administrative-type share that you created on the cDOT SVM. To take advantage of performance improvements when using this option, the share must be created at the root of the SVM's namespace (/). Ideally it should be named to something similar to PMCSave\$ to prevent users from being able to see it.

Nutanix Files Configurations

Peer Management Center supports the ability to include content from CIFS/SMB shares on one or more Nutanix Files (formerly Acropolis File Services or AFS) clusters within most available job types. For detailed information about Nutanix prerequisites, see [Nutanix Prerequisites](#).


To create a new Nutanix Files configuration:

1. Select **Preferences** from the **Window** menu.

The **Preferences** dialog appears.


2. Select **NAS Configuration** in the navigation tree.
3. Select **Nutanix Configurations**.

The **Nutanix Files Configurations** page is displayed. It lists any existing configurations.



- 4. Click the **Create** button.

The **Management Agent** page appears.



5. Select a Management Agent, and then click **Next**.

The **Storage Information** page appears.

Storage Information

Enter the required information to connect to the storage

Management Agent
Storage Information

Credentials

*Nutanix File Server Name:

*Username:

*Password:

*Peer Agent IP:

Advanced

Validate You must enter the name.

Having trouble connecting? Please verify that all [prerequisites](#) are met for Nutanix Files environments.

< Back Next > Finish Cancel

6. Enter the required values in **Credentials**.

Field	Description
Nutanix File Server Name	Enter the name of the Nutanix Files cluster hosting the data to be replicated.
Username	Enter the user name for the account managing the Nutanix Files cluster via its management APIs.
Password	Enter the password for the account managing the Nutanix Files cluster via its management APIs.
Peer Agent IP	Select the IP address of the server hosting the Agent that manages the Nutanix Files cluster. The Files cluster must be able to route traffic to this IP address. If the IP address you want does not appear, manually enter the address. This should not point to the Files cluster itself.

7. (Optional) Click [Advanced](#) button and then enter the required values.

8. Click **Validate**.
9. Click **Next**.
10. Click **OK**.

The options are divided into two groups:

- [Nutanix Files Options for this Job](#)
- [Advanced Settings](#)

Nutanix Files Options

Nutanix Files Options for this Job

Filter open/close events from these users:

Filter all events from these users:

Filter events from these IP Addresses:

Access Event Suppression Time:

Advanced Settings for Agent DGAgent1 and Nutanix File Server Name: AF2

Peer Agent IP:

Username:

Password:

NOTE: Any changes made to these Advanced Nutanix Files Settings will be used with every other session in which this agent is connecting with an Nutanix File Server.

Validate OK Cancel

Nutanix Files Options for this Job

The following configuration options are available for Nutanix Files devices:

Option	Description
Filter open/close events from these users	A comma-separated list of user names to exclude from access event detection. For example, if "USER1" is excluded, any access event activity generated by USER1 will be ignored, e.g., file is opened and closed.
Filter all events from these users	A comma-separated list of user names to exclude from all event detection. For example, if "USER1" is excluded, any activity generated by USER1 will be ignored, e.g., file is open and modified.
Filter events from these IP Addresses	A comma-separated list of IP addresses to exclude from all event detection. For example, if "192.168.0.100" is excluded, any activity generated by 192.168.0.100 will be ignored, e.g., file is open and modified.
Access Event Suppression Time	Represents the number of seconds that an open event will be delayed before being processed. Used to help reduce the amount of chatter generated by Windows clients when mousing over files in Windows Explorer. The default value is -1, which will be adjusted based on the selected NAS platform. A value of 0 will allow for dynamic changes to the amount of time that an open event will be delayed based on the load of the system.

Advanced Settings

The following advanced settings are available for Nutanix Files devices:

Option	Description
Peer Agent IP	The IP address over which the configured Files cluster will send activity to this Peer Agent. This must be an IP address.
User Name	User name used to access the APIs on the Files cluster.
Password	Password used to access the APIs on the Files cluster.

Real-time Event Detection Preferences


Several options are available to tune the way real-time event detection occurs. These options apply to all job types, except for DFS-N Management and PeerSync Management.

Note: There are also real-time event detection settings applicable to most job types in Peer Management Center. See [Real-time Event Detection](#) in the [File Collab, Sync, and Repl, and Locking Preferences](#) topic for more information.

To view and modify real-time event detection settings for all job types:

1. Select **Preferences** from the **Window** menu.
2. Select **Real-time Detection** in the navigation tree.

The following page is displayed.



3. Modify values as needed:

Option	Description
Max Path Length	The maximum length in characters of a file or folder path that can be detected and worked with. In rare cases, this can be increased to 2048 or even 4096 but doing so will impact memory usage of the Peer Agents.
Event Buffer Size	The buffer size used by the Peer Agents to communicate with various Windows and enterprise NAS platform APIs.
Access Polling Delay (Seconds)	Controls how often a Peer Agent will poll a Windows File Server for its open files list.
Debug Mode	Turns on debug logging for real-time detection. This logs additional information that is often useful in troubleshooting issues but can increase overhead.

Option	Description
Advanced Job Configuration Options	When selected, enables advanced job-level options tied to real-time event detection.
Raw Event Logging	When selected, turns on raw logging. This logs every single event that we receive from a storage platform, even ones that we may be able to consolidate and coalesce. This additional information is often useful in troubleshooting issues but will increase overhead.
Advanced Configuration	A list of strings to enable advanced real-time detection options not found in the GUI. This should only be used when instructed by Peer Software support.


4. Click **OK** or **Apply**.

SNMP Configuration

Before Peer Management Center can send SNMP notifications on behalf of any job, a few key SNMP settings must be configured.

To configure SNMP settings:

1. Select **Preferences** from the **Window** menu.
2. Select **SNMP Configuration** in the navigation tree.



3. In the **Source IP Address** field, select or manually enter the IP address over which the trap will be sent.
4. In the **Destination** field, enter the destination host name, IP address, or broadcast address.
5. For **Trap Prefix**, enter a prefix that will help to identify whether the message is coming from different instances of Peer Management Center or from different jobs. In the default prefix, "1.3.5.1.4.1" represents IANA-registered private enterprises, "58279" is reserved for Peer Software, and the trailing ".2" represents the Peer Management Center.
6. Click **Test SNMP Settings**, and then click **OK** in the **Test Connection** dialog.

You can verify the result by checking in your SNMP management tool.

7. Click **Apply and Close** or **Apply**.

User Management


Peer Management Center has both a rich client interface and a web client interface. The **User Management** page allows you to manage users of the web client interface. From this page, you can [manage web client users](#), [manage web roles](#), and [configure Active Directory authentication](#).

Note: The User Management page can be accessed by any rich client user but only by web client users that have an **Administrator** role.

To access the User Management page:

1. Select **Preferences** from the **Window** menu.
2. Select **User Management** from the navigation tree.

The **User Management** page is displayed:



- From this page, you can add, edit, and remove [web roles](#), [internal users](#), [active directory users and groups](#), and [configure Active Directory authentication](#).

Managing Web Client Users

Web client users are users that access Peer Management Center through the web client.

Web users can be divided into two types based on how their access to the web client is authenticated:

- [Internal users](#) - Users whose access to the web client is authenticated through the internal PMC database.
- [Active Directory \(AD\) users and groups](#) - Users whose access to the web client is authenticated through Active Directory.

You add, modify, and delete web users through the [User Management](#) page in [Preferences](#). The **User Management** page is also where you specify the Active Directory account that will be used when Peer Management Center queries Active Directory for authentication.

Management of web users can be performed through the rich client or through the web client by a user with an **Administrator** role. For more information, see:

- [Managing Internal Users](#)
- [Managing Active Directory Users and Groups](#)
- [Configuring Active Directory Authentication](#)


Managing [internal users](#) involves:

- [Creating internal users](#)
- [Editing internal users](#)
- [Deleting internal users](#)

Creating an Internal User


To add an internal user, follow these steps:

1. From the **Window** menu, select **Preferences**.
2. Select **User Management** from the navigation tree.



3. Select the **Create** button for Internal Users.

The **New Internal User** dialog appears.



The screenshot shows a dialog box titled "New Internal User" with a close button in the top right corner. The dialog contains the following fields and controls:

- Username:** A text input field with a cursor. Below it, the text "Example: 'JohnM'" is displayed.
- Password:** A text input field.
- Password Confirm:** A text input field.
- Enabled:** A checkbox that is checked.
- Role:** A dropdown menu showing "Power User".
- Contact:** A dropdown menu showing "None".
- At the bottom right, there are two buttons: "OK" and "Cancel".

4. Enter the following information.

- **Username:** The username can contain letters, numbers, and spaces; it cannot contain special characters. The minimum number of characters is 6; the maximum number of characters is 20.
- **Password:** The minimum number of characters is 6; the maximum number of characters is 20. The password cannot be the same as the username.
- **Password Confirm:** Re-enter the password you entered.
- **Enabled:** Select this checkbox if you want to enable this user to access Peer Management Center. You can enable or disable the user at a later date by [editing the user](#).
- **Role:** Select the [web role](#) you want to assign to the user. It can be a standard role or a custom role. For more details on the available roles, see [Web Roles](#)
- **Contact:** Select the user's email address from the drop-down list. If the user's email address does not appear in the list, you can add it to **Contacts** in the [Email Configuration](#) in [Preferences](#).

5. Click **OK**.

The new user appears in the list of internal users on the User Management page.

6. Click **Apply and Close** or **Apply**.

Editing an Internal User

Once an internal user has been created, its user name, password, email address, and web role can all be changed.

Note: The [default admin user](#) cannot be renamed, nor can its role be changed. However, you should change the default password for the default admin user.

To edit an internal user from Peer Management Center:

1. From the **Window** menu, select **Preferences**.
2. Select **User Management** from the navigation tree.
3. Select the user from the list of internal users.
4. Click **Edit**.
5. Make the changes in the **Edit User Information** dialog.
6. Click **OK**.
7. Click **Apply and Close** or **Apply**.

Deleting an Internal User

Once the account of an internal user is deleted, that user can no longer access Peer Management Center through the web client.

Note: The [default admin user](#) cannot be deleted.

To delete an Active Directory user or group from Peer Management Center:

1. From the **Window** menu, select **Preferences**.
2. Select **User Management** from the navigation tree.
3. Select the user from the list of internal users.
4. Click **Delete**.
5. Click **OK** in the **Remove User** dialog.
6. Click **Apply and Close** or **Apply**.


Managing Active Directory users involves:

- [Adding an Active Directory User or Group](#)
- [Editing an Active Directory User or Group](#)
- [Deleting an Active Directory User or Group](#)

Adding an Active Directory User or Group


To add Active Directory users and groups to Peer Management Center, follow these steps:

1. From the **Window** menu, select **Preferences**.
2. Select **User Management** from the navigation tree.




3. Add an Active Directory user or group by clicking the appropriate **Add** button.
4. Enter the information required in the dialog that appears:

- For an individual user, enter the domain name, user name, and select a role.



The screenshot shows a dialog box titled "Add a new Active Directory User". It contains three input fields: "Domain:" with a text box and an example "Example: 'MYDOMAIN.local' or 'MYDOMAIN.com'", "Username:" with a text box and an example "Example: 'JohnM'", and "Role:" with a dropdown menu currently set to "Power User". At the bottom right, there are "OK" and "Cancel" buttons.

- For a user group, enter the domain name, group name, and select a role.



The screenshot shows a dialog box titled "Add a new Active Directory Group". It contains three input fields: "Domain:" with a text box and an example "Example: 'MYDOMAIN.local' or 'MYDOMAIN.com'", "Group:" with a text box and an example "Example: 'Domain Admins' or 'Power Users'", and "Role:" with a dropdown menu currently set to "Power User". At the bottom right, there are "OK" and "Cancel" buttons.

Directory users and groups are saved in the following format:
username@mydomain.local

5. Click **OK**.

The added user or group appears in the list of Active Directory users or groups.

6. Click **OK**.

Editing an Active Directory User or Group

To edit an Active Directory user or group:

1. From the **Window** menu, select **Preferences**.

2. Select **User Management** from the navigation tree.
3. Select the AD user or group from the list of AD users or groups.
4. Click **Edit**.
5. Make the changes.
6. Click **OK**.

Deleting an Active Directory User or Group

If you delete an Active Directory user or group from Peer Management Center, that user or group will no longer have access to Peer Management Center through the web client. However, deleting the AD user or group from Peer Management Center does not delete that user or group from the Active Directory.

To delete an Active Directory user or group from Peer Management Center:

1. From the **Window** menu, select **Preferences**.
2. Select **User Management** from the navigation tree.
3. Select the AD user or group from the list of AD users or groups.
4. Click **Delete**.
5. Confirm that you want to delete the user or group.
6. Click **OK**.

To configure Active Directory authentication, you need:

- The URL of the LDAP server
- The LDAP administrator credentials

Active Directory users won't be able to access Peer Management Center until the authentication is configured.

To configure Active Directory authentication:

1. From the **Window** menu, select **Preferences**.
2. Select **User Management** from the navigation tree.

The screenshot shows the 'Preferences' window with the 'User Management' section selected in the left-hand navigation pane. The main content area is titled 'User Management' and contains several sections:

- Roles:** A list box containing 'Power User', 'Administrator', and 'Help Desk'. To the right are 'Create', 'Edit', and 'Delete' buttons.
- Users:** A section containing 'Internal Users' with a list box showing 'admin'. To the right are 'Create', 'Edit', and 'Delete' buttons.
- Active Directory Users and Groups:** A section containing 'Active Directory Users' with an empty list box. To the right are 'Add', 'Edit', and 'Delete' buttons.
- Active Directory Groups:** A section containing 'Active Directory Groups' with an empty list box. To the right are 'Add', 'Edit', and 'Delete' buttons.
- Active Directory Authentication:** A section with the warning: **Authentication will not work until the URL and credentials are entered.** It includes three text input fields: 'LDAP Server URL:', 'LDAP Search Domain (Optional):' (with 'Optional' entered), and 'LDAP Credentials:'. Below these fields are two buttons: 'Add/Update LDAP Credentials' and 'Test'.

At the bottom of the window, there are three buttons: 'Apply and Close' (highlighted with a blue border), 'Cancel', and 'Apply'.

3. In the **LDAP Server URL** field in the **Active Directory Authentication** section, enter the URLs of the LDAP servers on the network using one of the following formats:


- ldap://MYDOMAIN.LOCAL
- ldaps://MYDOMAIN.LOCAL

You can enter multiple LDAP URLs separated by spaces for failover redundancy.

4. (Optional) In the **LDAP Server Domain** field, enter a domain name override to use for LDAP searches.

Enter a value when (a) the search domain is different than the domain or DNS name specified in the **LDAP Server URL** field or (b) multiple LDAP servers URLs are specified.

5. Click **Add/Update LDAP Credentials**.



The screenshot shows a dialog box titled "LDAP Admin User Information". It contains the following fields and examples:

- Domain:** [Input field] Example: 'MYDOMAIN.local' or 'MYDOMAIN.com'
- Username:** [Input field] Example: 'JohnM'
- Password:** [Input field]
- Password Confirm:** [Input field]

At the bottom of the dialog are two buttons: "OK" and "Cancel".

6. Enter the domain name, user name, and password.
7. Confirm the password.
8. Click **OK**.

The LDAP user's information appears below the **Add/Update LDAP Admin User** button.

9. Click **Test** to verify the connection to the LDAP server.
10. Click **OK**.

Managing Web Roles


Managing web roles involves:

- [Creating custom web roles](#)

- [Editing and deleting web roles](#)
- [Assigning tags to web roles](#)

To create a custom role:

1. From the **Window** menu, select **Preferences**.
2. Select **User Management** from the navigation tree.



3. Click the **Create** button in the **Roles** section.

The **General** tab of **New Role** dialog is displayed.

The screenshot shows a 'New Role' dialog box with a sidebar on the left containing 'General', 'Permissions', and 'Tags'. The 'General' tab is active. The main area contains the following fields:

- Role Name:** A text input field with the example text: 'Example: 'projectmanager' or 'helpdesk''
- Display Name:** A text input field with the example text: 'Example: 'Administrator' or 'Help Desk''
- Description:** A text input field with the example text: 'Example: Default administrator role.'
- Base Role:** A dropdown menu currently showing 'Administrator'.

At the bottom right of the dialog are 'OK' and 'Cancel' buttons.


4. Enter the following information:

- **Role Name:** Role Name can contain only letters and numbers; it cannot contain any spaces or special characters. The maximum number of characters is 20. The Role Name is used in the internal Peer Management Center database.
- **Display Name:** Display Name can contain spaces and special characters, in addition to letter and numbers. The Display Name is displayed in the PMC user interface and reports.
- **Description:** (Optional) Use the Description to provide a brief summary of the intended use of the role.

5. Select a [standard web role](#) on which to base the custom role.

6. Select the **Permissions** tab.

The **Permissions** tab displays a table of [the permissions that are available to be modified for the new role](#). The **Access** column displays the current level of access that the role has to the resource. The three levels of access are **Full access**, **View-only access**, and **No access**.



7. For each permission that you want to modify, click in the **Access** column, and then select the access level that you want for the new role.
8. (Optional) Click **Tags** to assign tags to the role.

The screenshot shows a web application window titled "New Role". On the left, a sidebar menu includes "General", "Permissions", and "Tags". The "Tags" tab is active, displaying the "Tags" configuration area. At the top of this area, it states: "Assigning tags to a role allows you to restrict user access to only specific jobs matching the selected tags." Below this, there are two checkboxes: "Show all jobs (non matched jobs will have read-only access)" which is unchecked, and "Filter tags below by job type:" which is checked. The "Filter tags below by job type:" dropdown menu is set to "All tags".

Below the filters, there are two main sections: "Unassigned tags" and "Assigned tags". Each section contains a "Tag Name Filter" and a "Category Filter" input field. Underneath these filters are two tables with two columns: "Tag Name" and "Category". Both tables are currently empty. Between the two tables, there are four navigation buttons: ">>", ">", "<", and "<<".

At the bottom right of the dialog, there are "OK" and "Cancel" buttons.

See [Assigning Tags](#) for more information.

9. Click **OK**.

The new role appears in the **Roles** section.

Editing a Web Role

You can edit a custom web role, changing its Role Name and Display Name, its base role, associated permissions, and tags assigned to the role.

Editing of a standard role is much more restricted. It is limited to modifying the tags assigned to the role. You cannot edit its names or associated permissions.

To edit a web role, select the role in the **Roles** section in the **User Management** page, and then click **Edit**.

Deleting a Web Role

You cannot delete a standard web role.

To delete a custom web role, select the role in the **Roles** section in the **User Management** page, and then click **Delete**.

For information about assigning a tag to a web role, see [Assigning Tags](#).

Cloud Backup and Replication Jobs

This section provides information about creating, running, and managing a Cloud Backup and Replication job:

- [Overview](#)
- [Before You Create Your First Cloud Backup and Replication Job](#)
- [Creating a Cloud Backup and Replication Job](#)
- [Running a Cloud Backup and Replication Job](#)
- [Monitoring Your Cloud Backup and Replication Jobs](#)
- [Deleting a Cloud Backup and Replication Job](#)
- [Recovering Data from the Cloud](#)

Overview

Cloud Backup and Replication brings file to object replication into Peer Software's capabilities for enterprise NAS environments. Leveraging the same real-time engine that powers Peer Software's multi-site, multi-vendor replication, Cloud Backup and Replication efficiently pushes data into Microsoft Azure or Amazon S3 storage in an open format that is immediately consumable by other applications and services.

Use cases for Cloud Backup and Replication include: (1) pushing exact replicas of on-premises data sets into object storage for use with burstable compute and cloud-borne services and (2) tape replacement-style backup to object with point-in-time recovery capability.

Before You Create Your First Cloud Backup and Replication Job

We strongly recommend that you configure the [Cloud Backup and Replication settings](#) (including [proxy configurations](#)), as well as other global settings such as SMTP configuration, email alerts, and before configuring your first Cloud Backup and Replication job. See [Preferences](#) for details on what and how to configure these settings.

In addition, we recommend that you set up your destination storage account before creating the job.

Creating a Cloud Backup and Replication Job

The **Create Job Wizard** walks you through the process of creating a Cloud Backup and Replication job. The process consists of the following steps:

[Step 1: Job Type and Name](#)

[Step 2: Source Storage Platform](#)

[Step 3: Management Agent](#)

[Step 4: Proxy Configuration](#)

[Step 5: Storage Information](#)

[Step 6: Source Paths](#)

[Step 7: File and Folder Filters](#)

[Step 8: Destination](#)

[Step 9: Destination Credentials](#)

[Step 10: Container or Bucket Details](#)

[Step 11: Replication and Retention Policy](#)

[Step 12: Replication Schedule](#)

[Step 13: Retention](#)

[Step 14: Source Snapshots](#)

[Step 15: Miscellaneous Options](#)

[Step 16: Email Alerts](#)


[Step 17: SNMP Notifications](#)

[Step 18: Confirmation](#)

Step 1: Job Type and Name


1. Open Peer Management Center.
2. From the **File** menu, select **New Job** (or click the **New Job** button on the toolbar).

The **Create New Job** wizard displays a list of job types you can create.



3. Click **Cloud Backup and Replication**, and then click **Create**.
4. Enter a name for the job in the dialog that appears.

The job name must be unique.




5. Click **OK**.

The [Source Storage Platform](#) page appears.

Step 2: Source Storage Platform

The **Source Storage Platform** page lists the types of source storage platforms that Cloud Backup and Replication supports. The source storage device hosts the data you want to replicate.

1. Select the type of storage platform you want to replicate.



2. Click **Next**.


The [Management Agent](#) page appears.

Step 3: Management Agent

Each storage device that you want to replicate must have a Peer Agent that manages that device. The Peer Agent that manages a device is known as its [Management Agent](#). You can have more than one Agent managing a storage device—however, the Agents must be managing different volumes/shares/folders on that storage device.


The **Management Agent** page lists the available Agents. In this step, you should select the Agent that manages the volumes/shares/folders you want to replicate in this job.

1. Select the Management Agent for the volume/share/folder you want replicated.



Tip: If the Agent you want is not listed, the Peer Agent Service may not be running on the server hosting the Agent. Try restarting the Peer Agent Service. If the service successfully connects to the [Peer Management Broker](#), then the list is of available agents will be updated with that Agent.

2. If you select an Agent that does not have a database connection listed in the **Database Connection** column, a message prompts you to create the connection:



3. Click **OK**, and then configure the database connection for the selected Management Agent.

See [Database Connections](#) for instructions about creating a database connection

4. Click **Next**.

The [Proxy Configuration](#) page appears.

Step 4: Proxy Configuration

If you do not need a proxy server to connect to outside networks, skip this step and proceed to [Step 5](#).

If you do need a proxy server to connect to outside networks, you have three options:

- Create a new proxy configuration.
- Use the existing proxy configuration. If there is an existing proxy configuration, details about the configuration will be displayed on the page.


You may have created one in advance through [Cloud Back and Replication Preferences](#) or when you created another Cloud Backup and Replication job. Once a proxy configuration is created for a source storage platform, that proxy configuration is used for all Cloud Backup and Replication jobs using that agent.

- Edit an existing proxy configuration. Click the **Edit Proxy Configuration** link to edit the existing proxy.


If you edit the proxy configuration, it affects other jobs using the same Agent. Editing an existing proxy configuration has the potential to create problems with the other jobs.

If there is not an existing proxy configuration for the selected management agent, follow these steps to create a new proxy configuration:

1. Click **Create Proxy Configuration**.




The **Proxy Configuration** page is displayed. Existing proxies are listed in the Proxy Configuration table.



2. Click the **Create** button.

The **Create Proxy Configuration** dialog is displayed. The Agent you selected in **Step 3: Management Agent** is preselected.



3. Enter values for the following fields:


Field	Description
Address	Enter the IP address or fully qualified domain name of the proxy server.
Port	Enter the port number.
User Authentication	Select this checkbox if the proxy server requires authentication.

4. If your proxy server requires authentication, click the **User Authentication** checkbox, and then supply the necessary values.


Field	Description
Domain	Enter the domain name on the proxy server.
Username	Enter the user name for the proxy server.
Password	Enter the password for the proxy server.

5. Click **OK**.

If you already have jobs managed by this Agent, a message appears and identifies those jobs. They will now use the proxy as well.




After you click OK, the **Proxy Configuration** page is redisplayed. The proxy you just created now appears in the table.



- (Optional) Select the proxy you created and click **Validate**.

The **Validate Proxy Configuration** dialog appears.


- Select the target storage account, and then click **OK**.




Once you click OK, PeerGFS tests the connection to the target storage account using the proxy.

- Click **OK** in the **Validation Result** dialog.


- Click **Close** in the **Validate Proxy Configuration** dialog.



- Click **OK** in the **Proxy Configuration** page.



The **Proxy Configuration** page now displays the details about the proxy configuration.



11. Click **Next**.

The [Storage Information](#) page appears.

Step 5: Storage Information

On the **Storage Information** page, you will select the storage device containing data that you want to replicate and enter other information about the storage device. The contents of the **Storage Information** page varies, depending on your selection in the [Storage Platform](#) page:

- If you selected **Windows File Server**, you are prompted for configuration information relating to Windows File Server. If you selected **Windows File Server** in [Step 2](#), this page doesn't appear; skip to [Step 5: Source Paths](#)

- If you selected any other type of storage device other than Windows File Server, the **Storage Information** page requests the credentials necessary to connect to that storage device. Continue with the steps below.

For storage platforms other than Windows File Server:

1. Select **New Credentials** to enter a new set of credentials for the source storage platform or select **Existing Credentials**.
2. If you selected **Existing Credentials**, select a credential from the drop-down list, and then click **Next** to continue with [Step 5: Source Paths](#).

If you selected **New Credentials**, enter the credentials for connecting to the source storage device. The information you are prompted to enter varies, depending on the type of storage platform:

[Amazon FSxN](#)

[Dell EMC Celerra | VNX | VNX 2](#)

[Dell EMC Unity](#)

[Dell PowerScale | EMC Isilon](#)

[NetApp Data ONTAP 7-Mode](#)

[NetApp ONTAP | Clustered Data ONTAP](#)

[Nutanix Files](#)

3. Click **Validate** to test the credentials.

After the credentials are validated, a success message appears.

4. Click **Next**.

The [Source Paths](#) page appears.

1. Select **New Credentials** or **Existing Credentials** to enter the credentials to connect to the to the Storage Virtual Machine hosting the data to be replicated.

Create Cloud Backup and Replication Job Wizard

Storage Information

Enter the information required to connect to the source storage platform.

- Source Storage Platform
 - Management Agent
 - Proxy Configuration
 - Storage Information**
- Source Paths
 - File Filters
- Destination
 - Azure Storage Credentials
 - Container Details
 - Replication and Retention Policy
 - Miscellaneous Options
 - Email Alerts
 - SNMP Notifications
 - Confirmation

Credentials

New Credentials

*SVM Name:

*SVM User Name:

*SVM Password:

SVM Management IP:

*Peer Agent IP:

Existing Credentials

SVM9X-1, usersadmin

Access Path

Access Path:

Having trouble connecting? Please verify that all [prerequisites](#) are met for NetApp ONTAP/cDOT environments.

< Back Next > Cancel

- If you selected **Existing Credentials**, select a credential from the drop-down list, and then click **Next** to continue to the [Source Paths](#) page.

If you selected **New Credentials**, enter the credentials for connecting to the storage device.

Option	Description
SVM Name	Enter the name, FQDN, or IP address of the Storage Virtual Machine hosting the data to be replicated.
SVM Username	Enter the user name for the account managing the Storage Virtual Machine. This must not be a cluster management account.

Option	Description
SVM Password	Enter the password for the account managing the Storage Virtual Machine. This must not be a cluster management account.
SVM Management IP	Enter the IP address used to access the management API of the Storage Virtual Machine. If the data LIFs (Logical Interfaces) corresponding to the SVM Name above already allow management access, this field is not required.
Peer Agent IP	Select the IP address of the server hosting the Agent that manages the Storage Virtual Machine. The Storage Virtual Machine must be able to route traffic to this IP address. If the IP address you want does not appear, manually enter the address.
Access Path	Use only when experiencing access issues. Contact Peer Software support for more information.

3. Click **Advanced** if you want to set [advanced options](#).
4. Click **Validate** to test the credentials.

After the credentials are validated, a success message appears.

5. Click **Next**.

The [Source Paths](#) page is displayed.

1. Select **New Credentials** or **Existing Credentials** to enter the credentials to connect to the CIFS Server hosting the data to be replicated.

Create Cloud Backup and Replication Job Wizard

Storage Information

Enter the information required to connect to the source storage platform.

- Source Storage Platform
 - Management Agent
 - Proxy Configuration
 - Storage Information**
- Source Paths
 - File Filters
- Destination
 - Azure Storage Credentials
 - Container Details
 - Replication and Retention Policy
 - Miscellaneous Options
 - Email Alerts
 - SNMP Notifications
 - Confirmation

Credentials

New Credentials

*CIFS Server Name:

*Control Station Username:

*Control Station Password:

*Control Station IP:

Existing Credentials

Access Path

Access Path:

Having trouble connecting? Please verify that all [prerequisites](#) are met for EMC VNX/Celerra environments.

- If you selected **Existing Credentials**, select a credential from the drop-down list, and then click **Next** to continue to the [Source Paths](#) page.

If you selected **New Credentials**, enter the credentials for connecting to the storage device.

Field	Description
CIFS Server Name	Enter the name of the CIFS Server hosting the data to be replicated.
Control Station Username	Enter the user name for the Control Station account managing the Celerra/VNX storage device.

Field	Description
Control Station Password	Enter the password for the Control Station account managing the Celerra/VNX storage device.
Control Station IP	Enter the IP address of the Control Station system used to manage the Celerra/VNX storage device. This should not point to the CIFS Server.
Access Path	Use only when experiencing access issues. Contact Peer Software support for more information.

3. Click **Advanced** if you want to set [advanced options](#).
4. Click **Validate** to test the credentials.

After the credentials are validated, a success message appears.

5. Click **Next**.

The [Source Paths](#) page is displayed.

1. Select **New Credentials** or **Existing Credentials** to enter the credentials to connect to the CIFS Server hosting the data to be replicated.

Create Cloud Backup and Replication Job Wizard

Storage Information

Enter the information required to connect to the source storage platform.

- Source Storage Platform
 - Management Agent
 - Proxy Configuration
 - Storage Information
- Source Paths
 - File Filters
- Destination
 - Azure Storage Credentials
 - Container Details
 - Replication and Retention Policy
 - Miscellaneous Options
 - Email Alerts
 - SNMP Notifications
 - Confirmation

Credentials

New Credentials

*CIFS Server Name:

*Unisphere Username:

*Unisphere Password:

*Unisphere Management IP:

Existing Credentials

Access Path

Access Path:

Having trouble connecting? Please verify that all [prerequisites](#) are met for EMC Unity environments.

< Back
Next >
Cancel

- If you selected **Existing Credentials**, select a credential from the drop-down list, and then click **Next** to continue to the [Source Paths](#) page.

If you selected **New Credentials**, enter the credentials for connecting to the storage device.

Field	Description
CIFS Server Name	Enter the name of the CIFS server hosting the data to be replicated.
Unisphere Username	Enter the user name for the Unisphere account managing the Unity storage device.

Field	Description
Unisphere Password	Enter the password for the Unisphere account managing the Unity storage device.
Unisphere Management IP	Enter the IP address of the Unisphere system used to manage the Unity storage device. This should not point to the CIFS server.
Access Path	Use only when experiencing access issues. Contact Peer Software support for more information.

3. Click **Advanced** if you want to set [advanced options](#).

4. Click **Validate** to test the credentials.

After the credentials are validated, a success message appears.

5. Click **Next**.

The [Source Paths](#) page is displayed.

1. Select **New Credentials** or **Existing Credentials** to enter the credentials to connect to the Dell PowerScale or EMC Isilon cluster hosting the data to be replicated or select existing credentials.

Create Cloud Backup and Replication Job Wizard

Storage Information

Enter the information required to connect to the source storage platform.

- Source Storage Platform
 - Management Agent
 - Proxy Configuration
 - Storage Information**
- Source Paths
 - File and Folder Filters
- Destination
 - Azure Storage Credentials
 - Container Details
- Replication and Retention
- Miscellaneous Options
- Email Alerts
- SNMP Notifications
- Confirmation

Credentials

New Credentials

*Cluster Name:

*Cluster Username:

*Cluster Password:

Cluster Management IP:

Existing Credentials

Access Path

Access Path:

Having trouble connecting? Please verify that all [prerequisites](#) are met for Dell PowerScale | EMC Isilon environments.

< Back
Next >
Finish
Cancel

2. If you selected **Existing Credentials**, select a credential from the drop-down list, and then click **Next** to continue to the [Source Paths](#) page.

If you selected **New Credentials**, enter the credentials for connecting to the storage device.

Field	Description
Cluster Name	Enter the name of the PowerScale or Isilon cluster hosting the data to be replicated.
Cluster Username	Enter the user name for the account managing the PowerScale or Isilon cluster.
Cluster Password	Enter the password for account managing the PowerScale or Isilon cluster.

Field	Description
Cluster Management IP	Enter the IP address of the system used to manage the PowerScale or Isilon cluster. Required only if multiple Access Zones are in use on the cluster.
Access Path	Use only when experiencing access issues. Contact Peer Software support for more information.

3. Click **Advanced** if you want to set [advanced options](#).

4. Click **Validate** to test the credentials.

After the credentials are validated, a success message appears.

5. Click **Next**.

The [Source Paths](#) page is displayed.

1. Select **New Credentials** or **Existing Credentials** to enter the credentials to connect to the Storage Virtual Machine hosting the data to be replicated.

Create Cloud Backup and Replication Job Wizard

Storage Information

Enter the information required to connect to the source storage platform.

- Source Storage Platform
 - Management Agent
 - Proxy Configuration
 - Storage Information**
- Source Paths
 - File Filters
- Destination
 - Azure Storage Credentials
 - Container Details
 - Replication and Retention Policy
 - Miscellaneous Options
 - Email Alerts
 - SNMP Notifications
 - Confirmation

Credentials

New Credentials

*SVM Name:

*SVM User Name:

*SVM Password:

SVM Management IP:

*Peer Agent IP:

Existing Credentials

SVM9X-1, usersadmin

Access Path

Access Path:

Having trouble connecting? Please verify that all [prerequisites](#) are met for NetApp ONTAP/cDOT environments.

< Back Next > Cancel

- If you selected **Existing Credentials**, select a credential from the drop-down list, and then click **Next** to continue to the [Source Paths](#) page.

If you selected **New Credentials**, enter the credentials for connecting to the storage device.

Field	Description
SVM Name	Enter the name, FQDN, or IP address of the Storage Virtual Machine hosting the data to be replicated.
SVM Username	Enter the user name for the account managing the Storage Virtual Machine. This must not be a cluster management account.

Field	Description
SVM Password	Enter the password for the account managing the Storage Virtual Machine. This must not be a cluster management account.
SVM Management IP	Enter the IP address used to access the management API of the NetApp Storage Virtual Machine. If the data LIFs (Logical Interfaces) corresponding to the SVM Name above already allow management access, this field is not required.
Peer Agent IP	Select the IP address of the server hosting the Agent that manages the Storage Virtual Machine. The Storage Virtual Machine must be able to route traffic to this IP address. If the IP address you want does not appear, manually enter the address.
Access Path	Use only when experiencing access issues. Contact Peer Software support for more information.

3. Click **Advanced** if you want to set [advanced options](#).
4. Click **Validate** to test the credentials.

After the credentials are validated, a success message appears.

5. Click **Next**.

The [Source Paths](#) page is displayed.

1. Select **New Credentials** or **Existing Credentials** to enter the credentials to connect to the NetApp 7-Mode filer or vFiler hosting the data to be replicated.

- If you selected **Existing Credentials**, select a credential from the drop-down list, and then click **Next** to continue to the [Source Paths](#) page.

If you selected **New Credentials**, enter the credentials for connecting to the storage device.

Field	Description
Filer Name	Enter the name of the NetApp 7-Mode filer or vFiler hosting the data to be replicated.
Access	Use only when experiencing access issues. Contact Peer Software support for more information.

Field	Description
Path	

3. Click **Advanced** if you want to set [advanced options](#).

4. Click **Validate** to test the credentials.

After the credentials are validated, a success message appears.

5. Click **Next**.

The [Source Paths](#) page is displayed.

1. Select **New Credentials** or **Existing Credentials** to enter the credentials to connect to the Nutanix Files cluster hosting the data to be replicated.

Create Cloud Backup and Replication Job Wizard

Storage Information

Enter the information required to connect to the source storage platform.

- Source Storage Platform
 - Management Agent
 - Proxy Configuration
 - Storage Information
- Source Paths
 - File Filters
- Destination
 - Azure Storage Credentials
 - Container Details
- Replication and Retention Policy
- Miscellaneous Options
- Email Alerts
- SNMP Notifications
- Confirmation

Credentials

New Credentials

*Nutanix File Server Name:

*Username:

*Password:

*Peer Agent IP:

Existing Credentials

AFS2, user:admin

Having trouble connecting? Please verify that all [prerequisites](#) are met for Nutanix Files environments.

< Back
Next >
Cancel

2. If you selected **Existing Credentials**, select a credential from the drop-down list, and then click **Next** to continue to the [Source Paths](#) page.

If you selected **New Credentials**, enter the credentials for connecting to the storage device.

Field	Description
Nutanix File Server Name	Enter the name of the Nutanix Files cluster hosting the data to be replicated.
Username	Enter the user name for the account managing the Nutanix Files cluster via its management APIs.

Field	Description
Password	Enter the password for the account managing the Nutanix Files cluster via its management APIs.
Peer Agent IP	Select the IP address of the server hosting the Agent that manages the Nutanix Files cluster. The Files server must be able to route traffic to this IP address. If the IP address you want does not appear, manually enter the address. This should not point to the Files cluster itself.

3. Click **Advanced** if you want to set [advanced options](#).

4. Click **Validate** to test the credentials.

After the credentials are validated, a success message appears.


5. Click **Next**.

The [Source Paths](#) page is displayed.

Step 6: Source Paths

The **Source Paths** page displays a list of available volumes to replicate. You can choose to replicate an entire volume or selectively replicate files and folders. The files/folders/volumes selected for replication are referred to as the [watch set](#).

1. Select the paths to the files/folders/volumes you want to replicate.



Unlike other job types, you can select multiple folders to replicate:

Option	Action
The entire volume (all files and folders, including subfolders and their files)	Select the volume checkbox.
All files at the root level of the volume (but no folders)	Expand the volume, scroll to the bottom of the expanded list, and then select All Files .
A specific folder and its content (including subfolders and their files)	Expand the volume, find the desired folder, and then select its checkbox.
All files within a specific folder (but not the folder)	Expand the folder and select All Files .

Option	Action
Specific files and folders	Select the Show individual files checkbox, expand the folders, and then select the files and folders you want to replicate.

2. (Optional) Click the **Review** button to see your selections.
3. Click **Next**.


The [File and Folder Filters](#) page appears.

Step 7: File and Folder Filters

The **File and Folder Filters** page displays a list of [file and folder filters](#). By default, all files and folders selected in the **Source Paths** page will be replicated. A file or folder filter enables you to exclude and/or include files and folders from the job based on file type, extension, name, or directory path. Any file or folder that matches the filter is excluded or included from replication, depending on the filter's definition.

1. Select the file and folder filters you want to apply to the job.

If you want to create a new file or folder filter or modify an existing one, click **Edit File Filters**. See [File and Folder Filters](#) in the [Preferences](#) section for information about creating or modifying a file filter.



2. Select the **Include Files Without Extensions** checkbox if you want to replicate files that do not have extensions.

Note: Files without extensions are ignored during replication unless you select this checkbox.

3. Click **Next**.

The [Destination](#) page appears.

Step 8: Destination

The **Destination** page displays a list of the available storage platforms to which Cloud Backup and Replication can replicate. Currently, the following platforms are supported:


- Microsoft Azure

- Amazon S3
- NetApp StorageGRID
- Nutanix Objects

In addition, some S3-compatible platforms are also supported. Contact your Peer Software Sales representative to see if the S3 compatible platform you want to use is supported.

Important: You should create the storage account before creating the Cloud Backup and Replication job.

1. Select the type of destination storage platform.



2. Click **Next**.

The [Destination Credentials](#) page appears.

Step 9: Destination Credentials

The **Credentials** page requests the credentials necessary to connect to the destination storage account.

1. Select **New Credentials** to enter a new set of credentials for the destination storage device or select **Existing Credentials**.
2. If you selected **Existing Credentials**, select a credential from the drop-down list.

If you selected **New Credentials**, enter the credentials for connecting to the destination storage account. The information you are prompted to enter varies, depending on the type of storage platform:

[Azure Blob Storage Credentials](#)

[Amazon S3 Credentials](#)

[NetApp StorageGRID](#)

[Nutanix Objects](#)

3. Click **Next**.

The **Details** page for the selected destination storage account.

1. Enter the credentials to connect to a Microsoft Azure storage account. General Purpose and Blob storage accounts are supported.

Create Cloud Backup and Replication Job Wizard

Azure Storage Credentials

Enter new credentials or select existing credentials.

- Source Storage Platform
 - Management Agent
 - Proxy Configuration
 - Storage Information
- Source Paths
 - File Filters
- Destination
 - Azure Storage Credentials**
 - Container Details
 - Replication and Retention Policy
 - Miscellaneous Options
 - Email Alerts
 - SNMP Notifications
 - Confirmation

Credentials

New Credentials

*Description:

*Account:

*Shared Key: Show Key

*Endpoint Type: **Public**

Use SSL

Existing Credentials

Azure Storage

< Back
Next >
Cancel

Description	Enter a name for the credentials.
Account	Enter the name of the Azure storage account, which can be found in the Azure Portal.
Shared Key	Enter one of the shared keys for the Azure Storage account. The shared keys can be found in the Azure Portal.
Endpoint Type	Select the type of data center endpoint. The options are: Public , Germany , China , US Government , and Custom .
Endpoint	If you selected Custom for Endpoint Type , the Endpoint field appears. Enter the IP address of the endpoint.
Use SSL	Select this if you want to use the SSL (Secure Sockets Layer) protocol to communicate with the destination rather than the standard (non-encrypted) HTTP protocol.

2. Click **Validate** to test the connection.

If you are using a proxy in your environment and you get an error while trying to validate, you may want to check the [proxy configuration](#) in [Preferences](#).

3. Click **Next**.

The [Container Details](#) page appears.

1. Enter the credentials to connect to an Amazon S3 storage account.

**Desc
ripti
on**

Enter a name for the credentials.

Access Key	Enter one of the shared keys of the Amazon S3 Storage account, which can be found in the Amazon AWS portal.
Secret Key	Enter the secret key of the Amazon S3 Storage account, which can be found in Amazon AWS portal.
Use SSL	Select this if you want to use the SSL (Secure Sockets Layer) protocol to communicate with the destination rather than the standard (non-encrypted) HTTP protocol.

2. Click **Validate** to test the connection.

If you are using a proxy in your environment and you get an error while trying to validate, you may want to check the [proxy configuration](#) in [Preferences](#).

3. Click **Next**.

The [Bucket Details](#) page appears.

1. Enter the credentials to connect to a NetApp StorageGRID storage account.

Description	Enter a name for the credentials.
Access Key	Enter one of the shared keys of the NetApp StorageGRID account, which can be found in the Tenant Manager.
Secret Key	Enter the secret key of the NetApp StorageGRID account, which can be found in the Tenant Manager.
Service	Enter the IP or name of the object store.

Point	
Use SSL	Select this if you want to use the SSL (Secure Sockets Layer) protocol to communicate with the destination rather than the standard (non-encrypted) HTTP protocol.

2. Click **Validate** to test the connection.
3. Click **Next**.

The [Container Details](#) page appears.

1. Enter the credentials to connect to a Nutanix Objects storage account.

Create Cloud Backup and Replication Job Wizard

Nutanix Objects Credentials

Enter new credentials or select existing credentials.

- Source Storage Platform
 - Management Agent
 - Proxy Configuration
 - Storage Information
- Source Paths
 - File Filters
- Destination
 - Nutanix Objects Credentials**
 - Bucket Details
 - Replication and Retention Policy
 - Miscellaneous Options
 - Email Alerts
 - SNMP Notifications
 - Confirmation

Credentials

New Credentials

*Description:

*Access Key:

*Secret Key: Show Key

*Service Point:

Use SSL

Existing Credentials

Nutanix Objects Credentials

Validate

< Back Next > Cancel

Description	Enter a name for the credentials.
Access Key	Enter one of the shared keys of the Nutanix Objects account, which can be found in Prism Central.
Secret Key	Enter the secret key of the Nutanix Objects account, which can be found in Prism Central.
Service Point	Enter the IP or name of the object store.
Use SSL	Select this if you want to use the SSL (Secure Sockets Layer) protocol to communicate with the destination rather than the standard (non-encrypted) HTTP protocol.

2. Click **Validate** to test the connection.
3. Click **Next**.

The [Container Details](#) page appears.

Step 10: Container or Bucket Details

The **Container Details** or **Bucket Details** page allow you to create a new storage container or bucket or choose an existing one.

1. Select **New Container/New Bucket** to create a new storage container/bucket; otherwise, select **Existing Container/Existing Bucket** to choose an existing one.
2. If you selected **Existing Container** or **Existing Bucket**, select a container or bucket from the drop-down list.

If you selected **New Container** or **New Bucket**, enter the requested information. The information you are prompted to enter varies, depending on the type of storage platform:

[Azure Blob Storage Container Details](#)

[Amazon S3 Bucket Details](#)

[NetApp StorageGRID Bucket Details](#)

[Nutanix Objects Bucket Details](#)

3. Click **Next**.

The [Replication and Retention Policy](#) page appears.

1. Select **New Container** to create a new container or select **Existing Container**.

Choose **Existing Container** if:

- You (or someone else) already created a container you want to use.
- You want to use a container that was created outside Peer Management Center.
- You don't have the permissions required to create a new container and want to use one that someone else will create.

Create Cloud Backup and Replication Job Wizard

Container Details

Create a new container or select an existing one.

Source Storage Platform

- Management Agent
- Proxy Configuration
- Storage Information

Source Paths

- File Filters

Destination

- Azure Storage Credentials
- Container Details**
- Replication and Retention Policy
- Miscellaneous Options
- Email Alerts
- SNMP Notifications
- Confirmation

New Container

*Name:

dgagent2-mykirzevab

Automatically name

Existing Container

< Back Next > Cancel

2. If you selected **Existing Container**, select a container from the drop-down list. If the container does not appear in the list because the person who has the permissions to create a container has not yet created the bucket, click the **Reload** button after the container is created. The container will appear in the updated list.

If you selected **New Container**, you have two options. By default, the **Automatically name** checkbox is selected. You can deselect the checkbox and enter a name for the container; the container name must conform to the following naming rules:

- A container name must be unique.
- A container name must be a valid DNS name.
- A container name must start with a letter or number, and can contain only letters, numbers, and the dash (-) character.
- Every dash (-) character must be immediately preceded and followed by a letter or number; consecutive dashes are not permitted in container names.

- All letters in a container name must be lowercase.
- A container name must be from 3 through 63 characters long.

For more information about container names, see [Naming and referencing containers, blobs, and metadata](#).

3. Click **Next**.

The [Replication and Retention Policy](#) page appears.

1. Select **New Bucket** to create a new bucket or select **Existing Bucket**.

Choose **Existing Bucket** if:

- You (or someone else) already created a bucket you want to use.
- You want to use a bucket that was created outside Peer Management Center.
- You don't have the permissions required to create new buckets and want to use one that someone else will create.

Create Cloud Backup and Replication Job Wizard

Bucket Details

Create a new bucket or select an existing one.

- Source Storage Platform
 - Management Agent
 - Proxy Configuration
 - Storage Information
- Source Paths
 - File Filters
- Destination
 - Amazon S3 Credentials
 - Bucket Details**
 - Replication and Retention Policy
 - Miscellaneous Options
 - Email Alerts
 - SNMP Notifications
 - Confirmation

New Bucket

*Name: dgagent2-qczkmxosg

Automatically name

*Region: US East (N. Virginia)

Existing Bucket

< Back Next > Cancel

- If you selected **Existing Bucket**, select a bucket from the drop-down list. If the bucket does not appear in the list because the person who has the permissions to create a bucket has not yet created the bucket, click **Reload** after the bucket is created. The bucket will appear in the updated list.

If you selected **New Bucket**, you have two options. By default, the **Automatically name** checkbox is selected. You can deselect the checkbox and enter a name for the bucket; the bucket name must conform to the following naming rules:

- A bucket name must be unique across all existing bucket names in Amazon S3 (that is, across all AWS customers). For more information, see [Bucket Restrictions and Limitations](#).
- Bucket names must comply with DNS naming conventions. For information about legacy non-DNS-compliant bucket names, see [Bucket Restrictions and Limitations](#).
- A bucket name must start with a lowercase letter or number.
- A bucket name must not contain uppercase characters or underscores.
- A bucket name must be from 3 through 63 characters long.

- A bucket name must be a series of one or more labels. Adjacent labels are separated by a single period (.). Bucket names can contain lowercase letters, numbers, and hyphens. Each label must start and end with a lowercase letter or a number.
- A bucket name must not be formatted as an IP address (for example, 192.168.5.4).
- When you use virtual hosted-style buckets with Secure Sockets Layer (SSL), the SSL wildcard certificate only matches buckets that don't contain periods. To work around this, use HTTP or write your own certificate verification logic. We recommend that you do not use periods (.) in bucket names when using virtual hosted-style buckets.
- Choose a bucket name that reflects the objects in the bucket because the bucket name is visible in the URL that points to the objects that you're going to put in your bucket. After you create the bucket, you cannot change the name, so choose wisely.

For information about naming buckets, see [Rules for Bucket Naming](#) in the Amazon Simple Storage Service Developer Guide.

3. Select the region where you want the bucket to reside.

Important: After you have created a bucket, you cannot change its region.

4. Click **Next**.

The [Replication and Retention Policy](#) page appears.

1. Select **New Bucket** to create a new bucket or select **Existing Bucket**.

Choose **Existing Bucket** if:

- You (or someone else) already created a bucket you want to use.
- You want to use a bucket that was created outside Peer Management Center.
- You don't have the permissions required to create new buckets and want to use one that someone else will create.

Bucket Details
Create a new bucket or select an existing one.

Source Storage Platform
Management Agent
Proxy Configuration
Storage Information

Source Paths
File Filters

Destination
NetApp StorageGRID Credential
Bucket Details
Replication and Retention Policy
Miscellaneous Options
Email Alerts
SNMP Notifications
Confirmation

New Bucket

*Name:
dgagent2-yvgjhyrdsb

Automatically name

Existing Bucket

< Back Next > Cancel

1. If you selected **Existing Bucket**, select a bucket from the drop-down list. If the bucket does not appear in the list because the person who has the permissions to create a bucket has not yet created the bucket, click **Reload** after the bucket is created. The bucket will appear in the updated list

If you selected **New Bucket**, you have two options. By default, the **Automatically name** checkbox is selected. You can deselect the checkbox and enter a name for the bucket; the bucket name must comply with the following rules:

- Must be unique across each StorageGRID Webscale system (not just unique within the tenant account).
- Must be DNS compliant.
- Must contain between 3 and 63 characters.
- Can be a series of one or more labels, with adjacent labels separated by a period. Each label must start and end with a lowercase letter or a number and can only use lowercase letters, numbers, and hyphens.

- Must not look like a text-formatted IP address.
- Should not use periods in virtual hosted-style requests because periods will cause problems with server wildcard certificate verification.

For information about naming buckets, see [Rules for Bucket Naming](#) in the Amazon Simple Storage Service Developer Guide.

2. Click **Next**.

The [Replication and Retention Policy](#) page appears.

1. Select **New Bucket** to create a new bucket or select **Existing Bucket**.

Choose **Existing Bucket** if:

- You (or someone else) already created a bucket you want to use.
- You want to use a bucket that was created outside Peer Management Center.
- You don't have the permissions required to create new buckets and want to use one that someone else will create.

Bucket Details
Create a new bucket or select an existing one.

Source Storage Platform
Management Agent
Proxy Configuration
Storage Information

Source Paths
File Filters

Destination
Nutanix Objects Credentials
Bucket Details
Replication and Retention Policy
Miscellaneous Options
Email Alerts
SNMP Notifications
Confirmation

New Bucket

*Name:
dgagent2-kolglodhhef

Automatically name

Existing Bucket

< Back Next > Cancel

2. If you selected **Existing Bucket**, select a bucket from the drop-down list. If the bucket does not appear in the list because the person who has the permissions to create a bucket has not yet created the bucket, click **Reload** after the bucket is created. The bucket will appear in the updated list

If you selected **New Bucket**, you have two options. By default, the **Automatically name** checkbox is selected. You can deselect the checkbox and enter a name for the bucket; the bucket name must comply with the following rules:

- Must start with a number or a letter.
- Must be 3 - 255 characters long.
- Can contain lowercase letters, numbers, underscores (_), and dashes (-).
- There may be additional restrictions on bucket names in some AWS regions. We recommend that you create bucket names that are DNS-compliant, if you want to access objects using URL. For more information, see [Amazon Simple Storage Service Console user's guide](#).

3. Click **Next**.

The [Replication and Retention Policy](#) page appears.

Step 11: Replication and Retention Policy

Each Cloud Backup and Replication job must have a Replication and Retention policy. A Replication and Retention policy specifies:

- How often you want to scan the storage device for replication or if you want to replicate in real-time.
- Whether you want to take snapshots of the data. A **snapshot** captures the state of a file system at a point in time. There are two types of snapshots:
 - A **destination snapshot** captures an image of the data on the destination storage device immediately after replication. Destination snapshots are useful for recovering data from different period of times. Destination snapshots track versions of changed files and file system structure that can be used for data recovery. For more information about recovering data, see [Recovering Data](#).
 - A **source snapshot** captures an image of the data on the source storage device immediately before replication. Source snapshots are useful for replicating open and locked files, which otherwise may not be able to be replicated. A source snapshot also ensures that the replicated data is coming from a static version of the source file system. For details about using source snapshots, see [Step 13: Source Snapshots](#).
- How long you want to retain destination snapshots.

The **Replication and Retention Policy** page enables you to create a new Replication and Retention policy or choose an existing policy.

1. Select **New Policy** or **Existing Policy**.

430 Peer Global File Service Help

Create Cloud Backup and Replication Job Wizard

Replication and Retention Policy

✘ You must enter a name for the policy.

- Source Storage Platform
 - Management Agent
 - Proxy Configuration
 - Storage Information
- Source Paths
 - File Filters
- Destination
 - Amazon S3 Credentials
 - Bucket Details
- Replication and Retention Policy
 - Replication Schedule
 - Retention
 - Source Snapshots
 - Miscellaneous Options
 - Email Alerts
 - SNMP Notifications
 - Confirmation

New Policy

*Name:

Enable Backup with Destination Snapshots

Existing Policy

< Back Next > Cancel

- If you selected **Existing Policy**, select a policy from the drop-down list, and then click **Next**. Continue with [Step 14. Miscellaneous Options](#).

If you selected **New Policy**, enter a name for the policy in the **Name** field.

- Select **Enable Backup with Destination Snapshots** if you want to replicate what is on premises to the [destination storage device](#), while taking [destination snapshots](#) at specified points in times.
- Click **Next**.

The [Replication Schedule](#) page appears.

Step 12: Replication Schedule

The **Replication Schedule** page enables you to select the frequency of the replication and when snapshots should be taken. Replication can be performed on a scheduled, batched real-time, or a continuous real-time basis.

1. Select the frequency of the replication:

- [Scheduled Scans](#) – Select this option if you want to replicate files on a scheduled basis. A scan of changes to the file system occurs on a scheduled basis, either daily or weekly, and replication of changes occurs as the scan progresses.
- [Batched Real-time](#) – Select this option if you want to continuously monitor changes to the file system but replicate changes on scheduled basis. Changes are monitored in real-time and only the latest version of changed file is replicated at scheduled times. An initial scan can be performed to establish a baseline.
- [Continuous Data Protection](#) – Select this option if you want continuously monitor changes and replicate changes in real-time. Whenever a file changes, the change is replicated in real-time.

2. Click **Next**.

The [Retention](#) page appears.

If you selected **Scheduled Scans** for the replication frequency:

1. Select the **Scan at Start** checkbox if you want a baseline replication to be performed.

2. Select **Daily** or **Weekly** for the frequency of the scans:

- Select **Daily** if you want replications performed every day. You can schedule one to four scans per day
- Select **Weekly** if you want to select specific days for replication. You can select one scan per day.

3. Select the day(s) and time(s) when you want the replication performed:

- If you selected **Daily**, select the times you want the scans performed. Then, if you selected **Enable Backup with Destination Snapshots** in [Step 10](#), choose when snapshots are taken (you must take at least one snapshot). If you did not select the backup option, the **Take Destination Snapshot** options will not appear.

Create Cloud Backup and Replication Job Wizard

Replication Schedule

✘ You must select at least one replication time.

- Source Storage Platform
 - Management Agent
 - Proxy Configuration
 - Storage Information
- Source Paths
 - File Filters
- Destination
 - Amazon S3 Credentials
 - Bucket Details
- Replication and Retention Policy
 - Replication Schedule**
 - Retention
 - Source Snapshots
- Miscellaneous Options
- Email Alerts
- SNMP Notifications
- Confirmation

Scheduled Scans

Daily Weekly

Times (up to 4)

None	<input type="checkbox"/> Take Destination Snapshot
None	<input type="checkbox"/> Take Destination Snapshot
None	<input type="checkbox"/> Take Destination Snapshot
None	<input type="checkbox"/> Take Destination Snapshot

Scan at Start

Batched Real-time

Continuous Data Protection

< Back Next > Cancel

- If you selected **Weekly**, select the day(s) and time you want the replication performed. Then, if you selected **Enable Backup with Destination Snapshots** in Step 10, choose when snapshots are taken. You must take at least one snapshot. If you did not select the backup option, the **Destination Snapshot** option will not appear.

Replication Schedule

✘ You must select at least one day.

Source Storage Platform
Management Agent
Proxy Configuration
Storage Information

Source Paths
File Filters

Destination
Amazon S3 Credentials
Bucket Details

Replication and Retention Policy
Replication Schedule
Retention
Source Snapshots

Miscellaneous Options
Email Alerts
SNMP Notifications
Confirmation

Scheduled Scans

Daily Weekly

Day(s):

Sunday
 Monday
 Tuesday
 Wednesday
 Thursday
 Friday
 Saturday

Time:
None ▾ Take Destination Snapshot

Scan at Start

Batched Real-time

Continuous Data Protection

< Back Next > Cancel

4. Click **Next**.

The [Retention](#) page appears.

If you selected **Batched Real-time** for the replication frequency:

1. Select **Scan at Start** if you want a baseline replication to be performed.
2. Select the frequency of the replications; you can schedule one to four replications per day.
3. If you selected **Enable Backup with Destination Snapshots** in [Step 10](#), choose when destination snapshots are taken (you must take at least one snapshot). The destination snapshot will be taken after the files have been replicated. If you did not select the backup option, the **Take Destination Snapshot** option will not appear.

Create Cloud Backup and Replication Job Wizard

Replication Schedule

✘ You must select at least one replication time.

- Source Storage Platform
 - Management Agent
 - Proxy Configuration
 - Storage Information
- Source Paths
 - File Filters
- Destination
 - Amazon S3 Credentials
 - Bucket Details
- Replication and Retention Policy
 - Replication Schedule**
 - Retention
 - Source Snapshots
 - Miscellaneous Options
 - Email Alerts
 - SNMP Notifications
 - Confirmation

Scheduled Scans

Batched Real-time

Times (up to 4)

None	<input type="checkbox"/> Take Destination Snapshot
None	<input type="checkbox"/> Take Destination Snapshot
None	<input type="checkbox"/> Take Destination Snapshot
None	<input type="checkbox"/> Take Destination Snapshot

Continuous Data Protection

< Back Next > Cancel

4. Click **Next**.

The [Retention](#) page appears.

If you selected **Continuous Data Protection** for the replication frequency:

1. Enter a value for **Processing Delay** if you want the replication to occur after a slight delay. A delay is useful to ensure that when a file or folder is created and quickly renamed, only the latest copy of the file or folder is replicated. This reduces WAN usage.
2. If you selected **Enable Backup with Destination Snapshots** in [Step 10](#), choose when snapshots are taken (you must take at least one snapshot). If you did not select the backup option, the **Take Destination Snapshot at** options will not appear.

The screenshot shows a wizard window titled "Create Cloud Backup and Replication Job Wizard". The current step is "Replication Schedule". A red error message at the top states: "You must select at least one destination snapshot trigger time." The left sidebar contains a tree view with the following items: Source Storage Platform (Management Agent, Proxy Configuration, Storage Information), Source Paths (File Filters), Destination (Amazon S3 Credentials, Bucket Details), Replication and Retention Policy (Replication Schedule, Retention, Source Snapshots), Miscellaneous Options, Email Alerts, SNMP Notifications, and Confirmation. The "Replication Schedule" section is active and contains three radio buttons: "Scheduled Scans", "Batched Real-time", and "Continuous Data Protection" (which is selected). Below these is a "Processing Delay" field set to "5" minutes. Underneath is a "Take Destination Snapshot at:" section with four dropdown menus, all currently set to "None". At the bottom of the wizard are three buttons: "< Back", "Next >", and "Cancel".

3. Click **Next**.

The [Retention](#) page appears.

Step 13: Retention

The **Retention** page enables you to define how long you want to retain destination snapshots. You have the option to retain destination snapshots on a daily, weekly, monthly, and yearly basis. If you did not select the **Enable Backup with Destination Snapshots** in Step 10, the **Retention** page will not appear.

1. Select the **Purge all versions between snapshots** checkbox if you do not want to indefinitely retain all versions.
2. Select the retention options. The options vary according to the replication schedule you selected.

3. Click **Next**.

The [Source Snapshots](#) page appears.


Step 14. Source Snapshots

The **Source Snapshots** page enables you to choose whether to take snapshots of the source storage before the items are replicated. A [source snapshot](#) is a read-only point-in-time version of the volume. A source snapshot allows the creation of consistent backups of a volume, ensuring that the contents do not change and are not locked while the backup is being made. It can be used to provide a consistent state of a managed file, e.g., pst files, and help with errors accessing files that are currently open.

1. Select a source snapshot option:

- Select the **Disabled** option if you do not want to take source snapshots.

- Select the **Use only for Destination Snapshots** option when you want the source snapshot to be stored on the destination storage as the destination snapshot rather than an actual destination snapshot. To use this option, you must have selected the **Enable Backup with Destination Snapshot** in Step 10.
- Select **Always use when replicating** when you want to replicate always using source snapshots.



2. Click **Next**.

The [Miscellaneous Options](#) page appears.

Step 15: Miscellaneous Options

The **Miscellaneous Options** page displays various options; the options available depend on the destination storage platform selected.

1. Select the options to apply to this job.

Option	Description
NTFS Permissions	<p>If you want NTFS permissions metadata included in the replication, select the elements to include:</p> <ul style="list-style-type: none"> • Owner – The NTFS Creator-Owner who owns the object (which is, by default, whomever created it). • DACL – A Discretionary Access Control List identifies the users and groups that are assigned or denied access permissions on a file or folder. • SACL - A System Access Control List enables administrators to log attempts to access a secured file or folder. It is used for auditing. <p>See File Metadata Synchronization for more information about NTFS permissions metadata.</p>

Option	Description
Storage Tier/Class	<p>Only available with Azure Blob Storage with either a General Purpose v2 (GPv2) account or Blob Storage Account.</p> <p>Select a storage tier. If you do not select a tier, it will default to the tier you configured on your Azure Storage account.</p> <p>Azure Storage offers three storage tiers for blob object storage so that you can store your data most cost-effectively depending on how you use it:</p> <ul style="list-style-type: none"> • Azure Hot Storage Tier is optimized for storing data that is accessed frequently. • Azure Cool Storage Tier is optimized for storing data that is infrequently accessed and stored for at least 30 days. • Azure Archive Storage Tier is optimized for storing data that is rarely accessed and stored for at least 180 days with flexible latency requirements (on the order of hours). The archive storage tier is only available at the blob level and not at the storage account level. <p>To read data in archive storage, Cloud Backup and Replication must first change the tier of the blob to hot or cool. This process is known as rehydration and can take up to 15 hours to complete.</p> <p>Rehydrated data remains in hot or cool storage for a specified number of days before Cloud Backup and Replication automatically returns it to archive storage.</p>
Rehydrated Data Availability (Days)	<p>Only available with Azure Blob Storage with either a General Purpose v2 (GPv2) account or Blob Storage Account.</p> <p>Rehydrated data is automatically returned to archive storage after a specified period. Enter the number of days for rehydrated data to remain in hot or cool storage before returning to archive storage. The default is seven days.</p>

2. Click **Next**.

The [Email Alerts](#) page appears.

Step 16: Email Alerts

This step is optional.


An [email alert](#) notifies recipients when a certain type of event occurs, for example, session abort, host failure, system alert. The **Email Alerts** page displays a list of email alerts that have been applied to the job. When you first create a job, this list is empty. Email alerts are defined in [Preferences](#) and can then be applied to multiple jobs of the same type.

Peer Software recommends that you create email alerts in advance. However, from this wizard page, you can select existing alerts to apply to the job or create new alerts to apply.


To create a new alert, see [Email Alerts](#) in the [Preferences](#) section.

To apply an existing email alert to the job:

1. Click the **Select** button.



The **Select Email Alert** dialog appears.



2. Select an alert from the **Email Alert** drop-down list, and then click **OK**.


The alert is listed in the **Email Alerts** page.

Peer Software recommends that you create SNMP notifications in advance. However, from this wizard page, you can select an existing SNMP notification to apply to the job or create new SNMP notifications.

To apply an existing SNMP notification to the job or disable notifications:

1. Select an SNMP notification from the drop-down list.

To disable, select **None - Disabled**.



2. Click **Next**.

The [Confirmation](#) page appears.

Step 18: Confirmation

The **Confirmation** page displays the job configuration.

1. Review the job configuration.
2. If you need to modify the job configuration after reviewing it, click **Back** until you reach the appropriate page and make your changes.

Note: You cannot change the job name.

Create Cloud Backup and Replication Job Wizard

Confirmation
Review your job configuration.

- Source Storage Platform
 - Management Agent
 - Proxy Configuration
 - Storage Information
- Source Paths
 - File Filters
- Destination
 - NetApp StorageGRID Credential
 - Bucket Details
 - Replication and Retention Policy
 - Miscellaneous Options
 - Email Alerts
 - SNMP Notifications
 - Confirmation**

Source Storage: NetApp ONTAP | Clustered Data ONTAP

Management Agent: DGAgent2

Source Paths: One or more specific paths

Source Items:
Volume: SVM9x1_mm1
Destination: -1
Item(s) to Include:
..\
Destination: NetApp StorageGRID

Replication and Retention Policy: 3x Daily
Replication Schedule: Destination Snapshots

Replicate every day

Times:
- 05:00 (Take destination snapshot)
- 15:00 (Take destination snapshot)
- 20:00 (Take destination snapshot)

Retention Configuration (3x Daily):
Purge all versions between destination snapshots: true

Daily Retention
Keep destination snapshots taken at:
- 05:00
- 15:00
- 20:00
For: 30 day(s)

Weekly Retention
Keep destination snapshots taken on:
- Monday
Taken at: 05:00
For: 52 weeks(s)

Monthly Retention
Keep destination snapshots taken on:
First
Tuesday
Taken at: 15:00
For: 60 month(s)

Yearly Retention
Keep destination snapshots taken on:
First
- Wednesday
in month(s):
- January
Taken at: 20:00
For: 10 year(s)

Source Snapshots:
Disabled


Start job after creation

< Back Next > **Finish** Cancel

3. Select the **Start job after creation** checkbox if you want the job to start immediately after clicking **Finish**.

4. Click **Finish**.

The **Summary** tab in the **Cloud Backup and Replication Job** runtime view is displayed.



Editing a Cloud Backup and Replication Job

Enter topic text here.

Running a Cloud Backup and Replication Job

This section describes:

- [Starting a Cloud Backup and Replication Job](#)
- [Stopping a Cloud Backup and Replication Job](#)

Starting a Cloud Backup and Replication Job


When running a Cloud Backup and Replication job for the first time, you must manually start it. After the initial run, a job will automatically start, even when the Peer Management Center server is rebooted.

Note: You cannot run two jobs concurrently on the same volume if the [watch sets](#) contain an overlapping set of files and folders.

To manually start a job:


1. Choose one of these options:

- Right-click the job name in the **Jobs** view.
- Open a job and then click the **Start/Stop** button to the left of the **Status** field in the bottom left corner of the job's view (shown below).



2. Click **Yes** in the confirmation dialog.

After the job initialization has completed, the job will run. Once the job starts, the icon next to the job name in the **Jobs** view changes from gray to green.



Stopping a Cloud Backup and Replication Job

You can stop a Cloud Backup and Replication job at any time.

To stop a Cloud Backup and Replication job:

1. Right-click the job name in the **Jobs** view or in the **Cloud Backup and Replication Job Summary** view, and then choose **Stop** from the pop-up menu.

Or open the job and then click the **Start/Stop** button to the left of the **Status** field in the bottom left corner of the job's runtime view (shown below)

2. Click **Yes** in the confirmation dialog.

The icon next to the job name in the **Jobs** view changes from green to red.

Monitoring Cloud Backup and Replication Jobs

Monitoring your Cloud Backup and Replication jobs is an important aspect of successfully replicating to the cloud. Monitoring involves checking the execution of a running job, checking the status of a job, reviewing performance statistics, making sure snapshots are created correctly, identifying problems such as a server outage, seeing how much data has been uploaded, and so forth. Cloud Backup and Replication provides several views to help you monitor the health and performance of your Cloud Backup and Replication jobs.


Many of the views are customizable tables. You can sort the columns in the view, filter by columns, add and subtract columns from the default display, and so forth.

To display a view:

- Double-click **Cloud Backup and Replication** in the **Jobs** view to display the summary view for all Cloud Backup and Replication jobs. The **Volume Summary** tab of the **Cloud Summary** view is displayed.

Volume	Job	Management ...	Storage Device	Storage Type	Destination Type	Destinatio...	Status	Mode	Scan Status	Next Scan
afs	CB-2	DGAgent1	AFS2	Nutanix Files	Amazon S3	dgagent1-c...	Running	Scheduled Scans	Last Scan: C...	08-26-2015
afs	CB-1	DGAgent1	AFS2	Nutanix Files	Amazon S3	dgagent1-s...	Running	Scheduled Scans	Last Scan: C...	08-26-2015


- Double-click the name of a Cloud Backup and Replication job in the **Jobs** view to display the runtime view associated with that job. The **Summary** tab of the runtime view is displayed.



Deleting a Cloud Backup and Replication Job


To delete a Cloud Backup and Replication job:

1. Right-click on the job name in the **Jobs** view, and then choose **Delete** from the menu. A confirmation dialog appears.



2. Click **OK** in the confirmation dialog.

Another dialog appears, prompting you to choose whether to delete data associated with the job.



3. Click **Yes** or **No**.

If you click **Yes**, the data associated with this job will be deleted as part of a nightly clean-up process in addition to the job itself. If you click **No**, the data will not be deleted but the job will be deleted.

Recovering Data

When you need to recover data from the cloud to on-premises, you can use the **Data Recovery** wizard. To restore data, you must have an existing Cloud Backup and Replication job that has been replicating that data.

Note: You can recover data from a running job. However, if you plan to restore the data to the original location, you should stop the job first.

To recover data:

1. Open Peer Management Center.
2. In the **Jobs** view, identify the Cloud Backup and Replication job that replicated the data you want to restore.
3. Right-click the job name, and then select **Recover Volume/File(s)** from the menu.


The **Recovery Wizard** opens and displays the **Volume to Recover** page. The **Storage Device** field on the page is a read-only field that displays the name of the source storage device.

4. Select the volume that was the source of the replicated data from the **Volume** drop-down list.

The screenshot shows a window titled "Recovery Wizard" with the subtitle "Volume to Recover". Below the subtitle is the instruction "Select the storage device and volume that the data originated from." The window is divided into two main sections. On the left is a navigation pane with a tree view containing the following items: "Recovery Source" (expanded), "Azure Storage Credentials", "Volume to Recover" (highlighted), "Search By", "Recover To", "Notifications", and "Confirmation". On the right is the main configuration area with two dropdown menus: "Storage Device:" set to "SVM9X-1" and "Volume:" set to "SVM9x1_highcount1_01". At the bottom of the window are three buttons: "< Back", "Next >" (which is highlighted with a blue border), and "Cancel".

5. Click **Next**.

The **Search By** page is displayed.



6. Select one of the search options.

- [Name](#)
- [Snapshot](#)
- [Point in Time](#)
- [Latest Replication](#)

7. Click **Next** and continue with [Recovery Options](#).

The search pages vary according to the search option you selected.

Search Options

1. The search options are:

- [Name](#)
- [Snapshot](#)
- [Point in Time](#)
- [Latest Replication](#)

Use the **Search by Name** option if you know any part of the name of a file or folder but don't know which folder contained it on the original volume on premises.

To search by name:


1. Enter a search string in the **Name** field.

The search string can be a full or partial name and can include wildcards. If you do not enter a search string, all files and folders will be listed in the search results.

The screenshot shows the 'Recovery Wizard' window. The title bar reads 'Recovery Wizard'. Below the title bar, the word 'Name' is displayed in bold, followed by the instruction 'Enter a search string.' Below this is a search input field with a 'Name:' label, a dropdown menu set to 'Any', and a 'Search' button. To the left of the search area is a navigation pane with the following items: '> Recovery Source', 'Volume to Recover', 'v Search By', 'Name' (highlighted), 'File/Folder Versions', 'Recover To', 'Notifications', and 'Confirmation'. Below the search input is a table with the following headers: 'Name', 'Sync Date', 'Last Modified', and 'Size'. The table is currently empty. At the bottom of the window are three buttons: '< Back', 'Next >', and 'Cancel'.

2. Select **File** or **Folder** from the **Any** drop-down list; if you want to search for both files and folders, select **Any**.
3. Click **Search**.


A list of matching files and/or folders appears. The **Sync Date** column shows the date the file was replicated; the **Last Modified Date** column shows the last known date and time that the file was changed on premises.




4. Select the file or folder to recover.
5. Click **Next**.

The **File/Folder Versions** page appears. Your options will vary, depending on whether you are recovering a file or folder.

6. If you selected a file to recover, all available versions of that file are presented below the calendar. Select the time of the desired version and then click elsewhere in the page.



If you selected a folder to recover, you have two options. You can recover the contents of the folder based on a snapshot that was previously taken, or you can recover the contents of the folder as it existed at a specific point in time. Select one of the options, select a time, and then click elsewhere in the page.




7. Click **Next** and continue with [Recovery Options](#).

Use the **Search by Snapshot** option if you want to recover data by browsing a previously taken destination snapshot. All available snapshots will be represented in the calendar widget below.


To search by snapshot:

1. Select the date of the snapshot.



2. Select the time of the snapshot, and then click elsewhere in the page.
3. Click **Next**.

The **File/Folder Browser** page appears.




4. Select the file or folder to restore. If no snapshots are available, click **Back** and select a different search option.
5. Click **Next** and continue with [Recovery Options](#).

Use the **Search by Point in Time** option if you want to restore a data from a specific point in time. This option does not require that a snapshot was taken and is very useful if you selected [Continuous Data Protection](#), where replication is performed on an on-going basis


To search by a point in time:

1. Select a date.



2. Select a date and time, and then click elsewhere in the page.
3. Click **Next**.

The **File/Folder Browser** page appears.




4. Select the file or folder to restore.

5. Click **Next** and continue with [Recovery Options](#).

Use the **Search by Latest Replication** option if you want to restore from the latest replication. For example, you may want to restore data from the last time that replication occurred rather than a snapshot or a point in time. This option is very useful if you selected [Continuous Data Protection](#), where replication is performed on an on-going basis.

To search by latest replication:

1. Select the file or folder to restore.




2. Click **Next** and continue with [Recovery Options](#).

Recovery Options

After you select the data to recover, the **Recover To** page appears.

1. Select the recovery location. You have two options:

- **Another Location** - Enter the UNC path to a location on another storage device.
- **Original Location** - Browse to a location on the device hosting the management agent. However, we recommend not restoring directly to the original location, especially if the job is currently running. If the version that is restored is older than the latest version in the destination storage, the restored version will not be backed up until the next scan.



2. Select the recovery options for when the file to recover already exists in the recovery location:

Recovery Option	Select this option if you want to:
Recover with unique name	Ensure that the existing file is not overwritten with the cloud version.
Overwrite if sizes or timestamps don't match	Overwrite the existing file with the cloud version if the sizes or timestamps the existing file do not match the cloud version.
Overwrite if cloud version is newer	Overwrite the existing file if the cloud version has a more recent modification date.


Overwrite always	Always overwrite the existing file with the cloud version.
Skip	Skip recovering a file if the file already exists.

3. Select the recovery metadata options:

Metadata Option	Select this option if you want to:
Recover Last Modified Time	Set the last modification time of a recovered file to match the last modification time stored at upload rather than the time at which it was recovered.
Recover Create Time	Set the creation time of a recovered file to match the creation time stored at upload rather than the time at which it was recovered.
Recover NTFS Permissions	Set the NTFS permissions of any recovered files and folders to match the original permissions when those files and folders were uploaded.
Recover	Set the attributes of any recovered files and folders to match the original attributes when those files and folders were uploaded.

4. (Optional) Click the **Review** button to see your selections.
5. Click **Next**.


The **Notifications** page appears.



6. (Optional) Select the **Send email notification when complete** checkbox if you want notifications sent when the recovery process is complete. Select **Only on failure** if you want notifications sent only if the recovery does not successfully complete.
7. If sending notifications, enter recipients and add them to the list.
8. Click **Next**.

The **Confirmation** page is displayed.

9. Review your recovery settings.



10. Click **Finish**.

DFS-N Management Jobs

A [DFS namespace](#) enables you to group shared folders that are located on different servers into one or more logically structured namespaces. Each namespace appears to users as a single shared folder with a series of subfolders. However, the underlying structure of the namespace can consist of numerous file shares that are located on different servers and in multiple sites. See [DFS Namespaces](#) for more information about the benefits of using DFS namespaces in PeerGFS.

PeerGFS enables you to create a namespace and manage various activities related to it, such as creating namespace folders, adding folder targets, and linking the namespace to a File Collaboration or File Synchronization job. You could manage DFS namespace using Microsoft tools; however, you can manage DFS namespaces through a dedicated job type in Peer Management Center, the DFS-N Management job.

This section provides information about creating, editing, running, and managing a DFS-N Management job:

- [Creating a DFS-N Management Job](#)
- [Running a DFS-N Management Job](#)

- [Managing DFS Namespaces](#)
 - [Adding a Namespace Server](#)
 - [Adding a Namespace Folder](#)
 - [Adding a Namespace Folder Target](#)
- [Importing an Existing Namespace](#)
- [Linking a DFS Namespace to File Collaboration and File Synchronization Jobs](#)

Creating a DFS-N Management Job

The **Create Job** Wizard walks you through the process of creating a DFS-N Management job. The process consists of the following steps:

[Step 1: Job Type](#)

[Step 2: Management Agent](#)

[Step 3: Agent Verification](#)

[Step 4: Namespace Name](#)

[Step 5: Namespace Servers](#)

[Step 6: Namespace Settings](#)

[Step 7: Namespace Folders](#)

[Step 8: Email Alerts](#)

[Step 9: SNMP Notifications](#)

[Step 10: Review](#)


[Step 11: Results](#)

Step 1: Job Type


1. Open Peer Management Center.
2. From the **File** menu, select **New Job** (or click the **New Job** button on the toolbar).

The **Create New Job** wizard displays a list of job types you can create.

3. Click **DFS-N Management**, and then click **Create**.



The following dialog appears.



4. If you have an existing namespace you want to import, click **Import Namespace**, and then follow the [steps for importing an existing namespace](#).

Otherwise, click **Create Namespace**.

The [Management Agent](#) page appears.

Step 2: Management Agent


On the **Management Agent** page, you select a Management Agent for this DFS-N Management job from the list of servers that have a Peer Agent installed.

Recommendation: Select an Agent that will be dedicated to managing DFS-N Management jobs. This enables the Agent to continue managing the namespace even if other Agent servers go down. If you use a dedicated Agent for DFS-N Management jobs, this Agent will not count against the number of licensed servers.

To reduce the number of Windows servers in your environment, you can [install an Agent](#) that runs on the same server as Peer Management Center and use this Agent to manage DFS-N Management jobs. This Agent will also not count against the number of licensed servers.


1. Select an Agent that is in the domain of the DFS namespace of where you want to create the new DFS namespace.

Note: If you select an Agent that has **No** in the **DFS Mgmt. Enabled** column, the Microsoft DFS PowerShell Management toolkit will be installed in [Step 3: Agent Verification](#).



2. If the DFS PowerShell Management toolkit is not installed, click the **Install** button that will appear next to **Verify DFS PowerShell Management Toolkit Installed**.

After the toolkit is installed, the verification continues. A green dot signifies that the verification of that element was successful.



3. After the verification has successfully completed, click **Next**.

The [Namespace Name](#) page appears.

Step 4: Namespace Name

On the **Namespace Name** page, you enter a name for the new namespace. The name of the namespace will also be the name of this DFS-N Management job.

1. Enter a name for the namespace.

Namespace Name
Enter a name of the new namespace.

<ul style="list-style-type: none">Management AgentAgent VerificationNamespace NameNamespace ServersNamespace SettingsFoldersEmail AlertsSNMP NotificationsReviewResults	<p>This name will appear after the server or domain name in the namespace path, such as \\Server\Name or \\Domain\Name.</p> <p>Namespace Name: <input type="text" value="Example: Public"/></p>
---	---

< Back Next > Cancel

2. Click **Next**.

The [Namespace Servers](#) page appears.

Step 5: Namespace Servers

On the **Namespace Servers** page, you select one or more servers to host the namespace. A [namespace server](#) must be a member server or domain controller in the domain in which the namespace is configured. The Microsoft DFS Namespaces service must also be running on the namespace server.

1. Enter the fully qualified domain of a namespace server in the **Server Name** field, and then click **Add**.

Create DFS-N Management Job Wizard

Namespace Servers

Select one or more servers to host this namespace. The servers you select will be known as namespace servers.

Management Agent
Agent Verification
Namespace Name
Namespace Servers
Namespace Settings
Folders
Email Alerts
SNMP Notifications
Review
Results

Enter the fully qualified domain name of a server running the DFS Namespaces service.

Server Name: Add

Servers: Delete

< Back Next > Cancel

The server path is listed in the **Servers** area below.


The screenshot shows the 'Create DFS-N Management Job Wizard' window at the 'Namespace Servers' step. The title bar reads 'Create DFS-N Management Job Wizard'. The main heading is 'Namespace Servers' with the instruction: 'Select one or more servers to host this namespace. The servers you select will be known as namespace servers.' On the left is a navigation pane with the following items: Management Agent, Agent Verification, Namespace Name, **Namespace Servers** (highlighted), Namespace Settings, Folders, Email Alerts, SNMP Notifications, Review, and Results. The main area contains the text 'Enter the fully qualified domain name of a server running the DFS Namespaces service.' Below this is a 'Server Name:' text box with an 'Add' button to its right. Underneath is a 'Servers:' list box containing the entry 'peertestdc1.peertest.local' and a 'Delete' button to its right. At the bottom of the window are three buttons: '< Back', 'Next >' (highlighted with a blue border), and 'Cancel'.

2. Add additional servers if desired.


This screenshot is similar to the previous one but shows two servers in the 'Servers:' list box: 'peertestdc1.peertest.local' and 'peertestdc2.peertest.local'. The 'Next >' button remains highlighted.

3. Click **Next**.

The [Namespace Settings](#) page appears.




The **Folder Name** dialog appears.



2. Enter a name for the namespace folder in the **Folder Name** field.

After you enter the folder name, a preview of the folder and path name appears below the **Folder Name** field.




The screenshot shows a 'New Folder' dialog box with the following elements:

- Title bar: New Folder
- Section: Folder Name
- Instruction: Enter a name for the folder.
- Navigation: Folder Name (selected), Folder Targets, Confirmation
- Input field: Folder Name: \\PeerTest.local\Documentation\ User Guides
- Preview: Preview of folder: \\PeerTest.local\Documentation\User Guides
- Buttons: < Back, Next > (highlighted), Cancel

3. Click **Next**.

The **Folder Targets** dialog appears.



The screenshot shows a 'New Folder' dialog box with the following elements:

- Title bar: New Folder
- Section: Folder Targets
- Instruction: Select one or more folder targets for this folder.
- Navigation: Folder Name, Folder Targets (selected), Confirmation
- Text: Enter the UNC path to an existing folder. If the folder is not shared, you must share it first.
- Input field: Path to folder target: Example: \\Server\Shared Folder\Folder Target
- Buttons: Add
- Text: Folder targets:
- Input field: (Empty list box)
- Buttons: Delete
- Buttons: < Back, Next > (highlighted), Cancel

- (Optional) To add a folder target, enter the UNC path to a shared folder, and then click **Add**.

If you haven't created your folders target yet, you can skip to Step 6 and [add folder targets to the job](#) later.

The screenshot shows the 'New Folder' dialog box with the 'Folder Targets' tab selected. The dialog has a title bar with a close button. Below the title bar, the text 'Folder Targets' is displayed, followed by the instruction 'Select one or more folder targets for this folder.' The main area is divided into two sections. The left section has three tabs: 'Folder Name', 'Folder Targets' (selected), and 'Confirmation'. The right section contains instructions: 'Enter the UNC path to an existing folder. If the folder is not shared, you must share it first.' Below this is a text input field labeled 'Path to folder target:' containing the text '\\DGWIN16B\User Guides-DC'. To the right of this field is an 'Add' button. Below the input field is a list box labeled 'Folder targets:' which is currently empty. To the right of the list box is a 'Delete' button. At the bottom of the dialog are three buttons: '< Back', 'Next >' (highlighted with a blue border), and 'Cancel'.

After the share is validated, it appears in the **Folder targets** area:

The screenshot shows the 'New Folder' dialog box with the 'Folder Targets' tab selected. The dialog has a title bar with a close button. Below the title bar, the text 'Folder Targets' is displayed, followed by the instruction 'Select one or more folder targets for this folder.' The main area is divided into two sections. The left section has three tabs: 'Folder Name', 'Folder Targets' (selected), and 'Confirmation'. The right section contains instructions: 'Enter the UNC path to an existing folder. If the folder is not shared, you must share it first.' Below this is a text input field labeled 'Path to folder target:' containing the text 'Example: \\Server\Shared Folder\Folder Target'. To the right of this field is an 'Add' button. Below the input field is a list box labeled 'Folder targets:' which now contains the text '\\DGWIN16B\User Guides-DC'. To the right of the list box is a 'Delete' button. At the bottom of the dialog are three buttons: '< Back', 'Next >' (highlighted with a blue border), and 'Cancel'.

- (Optional) Add additional folder targets.

The screenshot shows a 'New Folder' dialog box with the title bar 'New Folder' and standard window controls. The main heading is 'Folder Targets' with the instruction 'Select one or more folder targets for this folder.' On the left, a sidebar contains three tabs: 'Folder Name', 'Folder Targets' (which is selected and highlighted), and 'Confirmation'. The main area contains the following text: 'Enter the UNC path to an existing folder. If the folder is not shared, you must share it first.' Below this is a text input field with the placeholder 'Example: \\Server\Shared Folder\Folder Target' and an 'Add' button to its right. Underneath is a section labeled 'Folder targets:' followed by a list box containing three entries: '\\DGWIN16B\User Guides-DC', '\\DGWIN16C\User Guides-Munich', and '\\DGWIN16D\User Guides-Cape Town'. A 'Delete' button is positioned to the right of the list box. At the bottom of the dialog, there are three buttons: '< Back', 'Next >' (which is highlighted with a blue border), and 'Cancel'.

- Click **Next**.


The **Confirmation** dialog appears.

The screenshot shows the 'New Folder' dialog box at the 'Confirmation' step. The title bar remains 'New Folder'. The main heading is 'Confirmation' with the question 'Do you want to add the following folder and folder targets?'. The left sidebar now has 'Confirmation' selected and highlighted. The main area displays the following information: 'Folder: \\PeerTest.local\Documentation\User Guides' and 'Folder Targets:' followed by the same three entries as in the previous step: '\\DGWIN16B\User Guides-DC', '\\DGWIN16C\User Guides-Munich', and '\\DGWIN16D\User Guides-Cape Town'. At the bottom, there are four buttons: '< Back' (highlighted with a blue border), 'Next >', 'Finish', and 'Cancel'.


- Review the folders and folder targets.

- Click **Back** to add more folder and folder targets; otherwise, click **Finish**.

The **Folders** page reappears.



- Expand the tree to view the folders and folder targets you added.



10. Click **Next**.

The [Email Alerts](#) page appears.

Step 8: Email Alerts


This step is optional.

An [email alert](#) notifies recipients when a certain type of event occurs, for example, session abort, host failure, system alert. The **Email Alerts** page displays a list of email alerts that have been applied to the job. When you first create a job, this list is empty. Email alerts are defined in [Preferences](#) and can then be applied to multiple jobs of the same type.


Peer Software recommends that you create email alerts in advance. However, from this wizard page, you can select existing alerts to apply to the job or create new alerts to apply. To create a new alert, see [Email Alerts](#) in the [Preferences](#) section.

To apply an existing email alert to the job:

1. Click the **Add** button.




The **Select Email Alert** dialog appears.



2. Select an alert from the **Email Alert** drop-down list, and then click **OK**.

The alert is listed in the **Email Alerts** page.



3. (Optional) Repeat steps 1-3 to apply additional alerts.
4. Click **Next**.

The [SNMP Notifications](#) page appears.

Step 9: SNMP Notifications

This step is optional.


An [SNMP notification](#) notifies recipients when certain type of event occurs, for example, session abort, host failure, system alert. The **SNMP Notifications** page displays a list of notifications that have been applied to the job. When you first create a job, this list is empty. Like email alerts and file filters, an SNMP notification is defined in [Preferences](#) and can then be applied to multiple jobs of the same type.

Peer Software recommends that you create SNMP notifications in advance. However, from this wizard page, you can select an existing SNMP notification to apply to the job or create new SNMP notifications. To create a new alert, see [SNMP Notifications](#) in the [Preferences](#) section.


To apply an existing SNMP notification to the job or disable notifications:

1. Select an SNMP notification from the drop-down list.

If you don't want to send a SNMP notification, select **None - Disabled**.



If you select a notification, details about the notification appear in the Selected SNMP Notification Information section.




2. Click **Next**.

The [Review](#) page appears.

Step 10: Review

The **Review** page allows you to review the configuration before it is actually created.

1. Review the namespace configuration.




2. Click **Create** if the configuration is correct; otherwise, click **Back** and correct the configuration.

After you click **Create**, the [Results](#) page appears.

Step 11: Results

The **Results** page has two tabs: **Tasks** and **Errors**.

1. Review the results in the **Tasks** and **Errors** tabs.



2. Review each task to verify that it was successful; if there were any errors, click the **Errors** tab to view more details about the problem.
3. After reviewing, click **Close**.

If there were no errors, the job automatically starts and the summary view for the new job is displayed.

The screenshot shows the Peer Management Center Client interface. The main window displays the 'Namespace Summary' for the namespace '\\PeerTest.local\Documentation'. The 'Jobs' pane on the left shows various tasks like Cloud Backup and Replication, DFS-N Management, and File Collaboration. The 'Agents' pane shows four connected agents: DGWin16A, DGWin16B, DGWin16C, and DGWin16D, all running Windows Serve. The 'Folder Targets' table is currently empty.

Folder Target	Linked to Agent	Status	Reason	AD Site	Replication Status
---------------	-----------------	--------	--------	---------	--------------------

Below the table, the 'Alerts' pane shows a summary of 0 errors, 9 warnings, and 22 others. A detailed list of alerts follows:

Received Date	Severity	Type	Name	Host	Message	Exception
03-31-2022 10:41:10	Info	Connection	Startup	DGWin16A	Agent Started	
03-31-2022 10:41:10	Info	Heartbeat	Reconnect	DGWin16A	Connection status changed from Disconnected to Connected	
03-31-2022 10:38:59	Warning	Connection	Shutdown	DGWin16A	Agent Shutdown	
03-28-2022 15:05:59	Info	Connection	Startup	DGWin16A	Agent Started	
03-28-2022 15:05:59	Info	Heartbeat	Reconnect	DGWin16A	Connection status changed from Disconnected to Connected	
03-28-2022 15:05:53	Info	Connection	Startup	DGWin16B	Agent Started	
03-28-2022 15:05:53	Info	Heartbeat	Reconnect	DGWin16B	Connection status changed from Disconnected to Connected	
03-28-2022 15:05:44	Info	Connection	Startup	DGWin16D	Agent Started	

4. Select the namespace in the **Namespace** tab and then select the namespace folder to view its folder targets.

The folder targets appear in the panel below.

The screenshot shows the Peer Management Center Client interface with the 'Namespace Summary' for '\\PeerTest.local\Documentation'. The 'Jobs' pane is the same as in the previous screenshot. The 'Agents' pane is also the same. The 'Folder Targets' table is now populated with three entries:

Folder Target	Linked to Agent	Status	Reason	AD Site	Replication Status
\\DGWIN16B\User Guides-DC	-	Active	-	US-HQ	Replication not configured
\\DGWIN16D\User Guides-Cape Town	-	Active	-	US-HQ	Replication not configured
\\DGWIN16C\User Guides-Munch	-	Active	-	US-HQ	Replication not configured

The 'Alerts' pane remains the same as in the previous screenshot, showing a summary of 0 errors, 9 warnings, and 22 others, with a detailed list of alerts below it.

Importing an Existing Namespace

If you have an existing namespace that you want to use in in a File Collaboration or File Synchronization job, you can import the namespace. Importing the namespace automatically creates a new DFS-N Management job with the same name as the imported namespace.

You can then either [link the namespace to an existing File Collaboration or File Synchronization job](#) or [create a new File Collaboration or File Synchronization job](#) that uses the namespace.

To import an existing namespace:

1. Right-click anywhere in the **Runtime Summary** tab of the **Namespace Summary** view, and then select **Import Existing Namespaces** (or right-click the DFS-N Management job type in the **Jobs** view).

The screenshot shows the Peer Management Center Client interface. The main window is titled 'Namespace Summary' and contains a table with the following data:

Namespace Path/Folders	Management Status	State	Errors	Servers	Total Folders/Targets
> \\PeerTest.local\Documentation	Monitoring	Online	0	peertestdc1, peertestdc2	1
> \\PeerTest.local\DG	Monitoring	Online	0	peertestdc2, peertestdc1	1
> \\PeerTest.local\Technical Support	Monitoring	Online	0	peertestdc1, peertestdc2	2


In the center of the table, there is a button labeled 'Import Existing Namespaces'.

The interface also shows a 'Jobs' view on the left with a tree structure of jobs, and an 'Agents' view at the bottom left showing a list of agents. At the bottom right, there is an 'Alerts' section with a table of alerts:

Received Date	Severity	Type	Name	Host	Message	Exception
05-04-2022 22:55:21	Info	Connection	Startup	DGWin16A	Agent Started	
05-04-2022 22:55:20	Info	Heartbeat	Reconnect	DGWin16A	Connection status changed from Disconnected to Connected	
05-04-2022 22:55:06	Info	Connection	Startup	DGWin16B	Agent Started	
05-04-2022 22:54:57	Info	Connection	Startup	DGWin16D	Agent Started	
05-04-2022 22:54:57	Info	Connection	Startup	DGWin16C	Agent Started	
05-04-2022 22:54:20	Warning	Connection	Shutdown	DGWin16A	Agent Shutdown	
05-04-2022 22:54:16	Warning	Connection	Shutdown	DGWin16C	Agent Shutdown	
05-04-2022 22:54:16	Warning	Connection	Shutdown	DGWin16D	Agent Shutdown	


The **Import Existing Namespace** wizard appears.

2. Select a Management Agent, and then click **Next**.



- If the DFS PowerShell Management toolkit is not installed, click the **Install** button that will appear next to **Verify DFS PowerShell Management Toolkit Installed**.

After the toolkit is installed, the verification continues. A green dot signifies that the verification of that element was successful.



5. After the verification has successfully completed, click **Next**.

The **Target Namespace** page appears. You have two options for selecting the namespace to import: either by entering its name or by selecting it from a list of namespaces.

6. If you choose **Select By Name**, enter the namespace name, and then click **Validate**. After the namespace is validated, skip to Step 8.

Import Existing Namespaces

Target Namespace

Select an existing namespace to import.

Management Agent
Agent Verification
Target Namespace
Email Alerts
SNMP Notifications
Confirmation
Results

Select By Name

*Namespace Name: \\PeerTest\local\ Development Validate

List All Namespaces


< Back Next > Cancel

7. If you choose **List All Namespaces**, click **Next**.

The **Existing Namespace** page appears; it displays a table listing the existing namespaces.


Note: It may take a few minutes for existing namespaces to appear in the table.

8. Select one or more existing namespaces from the table, and then click **Next**.



The **Email Alerts** page appears.

9. (Optional) [Select or create email alerts](#) to apply to the job, and then click **Next**.



The **SNMP Notifications** page appears.

10. (Optional) [Select or create an SNMP notification](#) to apply to the job, and then click **Next**.

Import Existing Namespaces

SNMP Notifications
Select a SMNP notification.

Management Agent
Agent Verification
Target Namespace
Email Alerts
SNMP Notifications
Confirmation
Results

[Edit SNMP Notifications](#)


SNMP Notification: None - Disabled

Selected SNMP Notification Information

No SNMP Notification Selected
SNMP notifications disabled for this job

< Back Next > Cancel

The **Confirmation** page appears.




11. Review the configuration.

12. If you need to modify the job configuration after reviewing it, click **Back** until you reach the appropriate page and make your changes.


13. Once you are satisfied with the job configuration, click **Import**.

The **Results** page appears.



14. Review the results, and then click **Close**.

A DFS-N Namespace job is created for each namespace you added. The new job(s) are displayed in the **Jobs** view. Runtime views for the jobs are also displayed. The jobs automatically start running. The namespaces can now be [linked to File Collaboration and File Synchronization jobs](#).



Running a DFS-N Management Job


This section describes:

- [Starting a DFS-N Management Job](#)
- [Stopping a DFS-N Management Job](#)


Starting a DFS-N Management Job

To manually start a DFS-N Management job:

1. Choose one of these options:
 - Right-click the job name in the **Jobs** view, and then select **Start**.




- Open the job and then click the **Start/Stop** button in the bottom left corner of the job's **Namespace** tab in the [DFS-N Management runtime view](#). You may need to scroll to the bottom of the tab to see the **Start/Stop** button.



2. Click **Yes** in the confirmation dialog.

After the job initialization has completed, the job will run. Once the job starts, the icon next to the job name in the **Jobs** view changes from gray to green.



Stopping a DFS-N Management Job

You can stop a DFS-N Management job at any time. Note that you cannot edit a DFS-N Management job while it is stopped.

To stop a DFS-N Management job:

1. Right-click the job name in the **Jobs** view, and then choose **Stop** from the context menu.

Or open the job and click the **Start/Stop** button in the bottom left corner of the job's **Namespace** tab in the runtime view.

2. Click **Yes** in the confirmation dialog.

The icon next to the job name in the **Jobs** view changes from green to red.

Managing DFS Namespaces

This section describes:

- [Adding a Namespace Server](#)
- [Adding a Namespace Folder](#)
- [Adding a Namespace Folder Target](#)

Adding a Namespace Server

You can add a namespace server to a namespace.

To add a namespace server:


1. Double-click the name of a DFS-N Management job in the **Jobs** view or in the **Namespace Summary** view to open the [runtime view](#) for the job.

The screenshot shows the Peer Management Center Client interface. The main window displays the 'Runtime Summary' for a job. The left sidebar shows a tree view of the file service structure, including 'File Collaboration (2)' with sub-items 'FC-1' and 'FC-2'. The main area contains a table with the following columns: Name, Overall Status, Job Type, Failed H..., Quar..., Retries, Errors, Warnin..., Open Files, Pending B..., Queued It..., Background S..., Scan St..., Elapsed Ti..., Session Structure, and Synchronization P. The table shows two rows for 'FC-1' and 'FC-2', both with an overall status of 'Stopped' and a job type of 'File Collaborat...'. Below the table, there is a summary bar indicating 'Active Jobs -> Failed Participants: 0 of 0 | Bytes Pending: 0 bytes | Bytes Transferred: 0 bytes | Opens: 0 | Initial Scans Completed: 0 of 0 | Total Size: 0 bytes | Total Files: 0 | Total Directories: 0'. At the bottom, there is an 'Alerts' section showing '0 errors, 8 warnings, 17 others' and a 'Filter by:' field.


The runtime view for the job is displayed.

The screenshot shows the Peer Management Center Client interface with the 'Namespace Servers' tab selected. The left sidebar is the same as in the previous screenshot. The main area displays a tree view of the namespace structure, including 'QA'. Below the tree view is a table with the following columns: Folder Target, Linked to Participant, Status, Reason, AD Site, and Replication Status. The table is currently empty. At the bottom, there is a 'Status: Monitoring' indicator and an 'Alerts' section showing '0 errors, 8 warnings, 17 others' and a 'Filter by:' field.

2. Click the **Namespace Servers** tab.




3. Right-click anywhere in the **Namespace Servers** tab, and then select **Add Servers**.




The **Add DFS Namespace Server** wizard appears.

4. Enter the fully qualified domain name (FQDN) of a namespace server in the **Server Name** field, and then click **Add**.



The screenshot shows the 'Add DFS Namespace Server' wizard at the 'Namespace Servers' step. The window title is 'Add DFS Namespace Server'. The main heading is 'Namespace Servers' with the instruction: 'Select one or more servers to host this namespace. The servers you select will be known as namespace servers.' On the left, a navigation pane shows 'Namespace Servers' selected, with other options: 'Namespace Settings', 'Confirmation', and 'Results'. The main area contains a text box for 'Server Name' with the value 'peertestdc2.peertest.local' and an 'Add' button. Below it is a 'Servers:' list box containing the same server name and a 'Delete' button. At the bottom, there are '< Back', 'Next >', and 'Cancel' buttons.


The server FQDN is listed in the area below.



This screenshot is identical to the previous one, but the 'Next >' button at the bottom is highlighted with a blue border, indicating it is the next step in the process.

5. Add additional servers if desired.
6. Click **Next**.

The **Namespace Settings** page is displayed.




7. (Optional) Edit the namespace server settings: **DFS Root Share Path** and **Permissions**.

- To modify the local path to the DFS root share for the namespace, type a new path in the **DFS Root Local Path** column. The default location of the DFS root share is under C:\DFSRoots\ and is specified in [DFS-N Management Job Preferences](#).
- To modify the access permissions, select a new set using the drop-down menu in the **Permissions** column.

8. Click **Next**.


The **Confirmation** page is displayed.



9. Review the namespace server configuration.


10. Click **Add** if the configuration is correct; otherwise, click **Back** and correct the configuration.

The **Results** page is displayed.



11. Click **OK**.

The newly added server is listed in the **Namespace Servers** tab.



Adding a Namespace Folder

You can add a namespace folder to a namespace. At the same time, you can its folder targets or you can [add folder targets](#) later.

Note that PeerGFS does not currently support creation of nested namespace folders. In other words, you cannot add a namespace folder that is a subfolder of a namespace folder, although this can be done when using the Microsoft DFS Management Tool.

A DFS-N Namespace job must be running before you can edit it.

To add a namespace folder to a namespace:


1. Double-click the DFS-N Management job name in the **Jobs** view or in the [Namespace Summary view](#) to open the runtime view for the job.

The screenshot displays the Peer Management Center Client interface. The main window is titled 'Namespace Summary' and shows a table of namespace folders. The table has columns for Namespace Path/Folders, Management Status, State, Errors, Servers, and Total Folders/Targets. The selected row is '\PeerTest.local\Technical Support' with a Management Status of 'Monitoring', State of 'Online', 0 errors, and 1 server (peertestdc1, peertestdc2).


Namespace Path/Folders	Management Status	State	Errors	Servers	Total Folders/Targets
\PeerTest.local\Documentation	Monitoring	Online	0	peertestdc1, peertestdc2	1
User Guides					3
\PeerTest.local\DG	Monitoring	Online	0	peertestdc2, peertestdc1	1
DGNFS					2
\PeerTest.local\Technical Support	Monitoring	Online	0	peertestdc1, peertestdc2	1
QA					0

Below the table, there is an 'Alerts' section showing a list of alerts with columns for Received Date, Severity, Type, Name, Host, Message, and Exception. The alerts include connection startup and shutdown events for agents DGWin16A, DGWin16B, DGWin16C, and DGWin16D.

The runtime view for the job is displayed.



2. Right-click anywhere in the **Namespace** tab, and then select **Add Folder**.



The **New Folder** wizard appears.

3. Enter a name for the namespace folder in the **Folder Name** field.

New Folder

Folder Name

Folder name cannot be empty.

Folder Name

Folder Targets

Confirmation

Results

Folder Name: \\PeerTest.local\\Technical Support\\

Preview of folder:

\\PeerTest.local\\Technical Support\\

< Back Next > Cancel

As you enter the folder name, a preview of the folder name and path appear below.

New Folder

Folder Name

Enter a name for the folder.

Folder Name

Folder Targets

Confirmation

Results

Folder Name: \\PeerTest.local\\Technical Support\\ Support Tickets


Preview of folder:

\\PeerTest.local\\Technical Support\\Support Tickets

< Back Next > Cancel


4. Click **Next**.

The **Folder Targets** page is displayed. It is optional to add folder targets for the namespace folder at this point. You can [add them later](#) if you wish. If you choose to add the folder targets now, they must already exist and be shared.



The screenshot shows the 'New Folder' dialog box with the 'Folder Targets' step selected. The dialog has a title bar with 'New Folder' and standard window controls. Below the title bar, the text 'Folder Targets' is displayed, followed by the instruction 'Select one or more folder targets for this folder.' On the left side, there is a vertical list of steps: 'Folder Name', 'Folder Targets' (highlighted), 'Confirmation', and 'Results'. The main area contains the following text: 'Enter the UNC path to an existing folder. If the folder is not shared, you must share it first.' Below this is a text input field labeled 'Path to folder target:' with the example text '\\Server\Shared Folder\Folder Target' and an 'Add' button to its right. Underneath is a larger text area labeled 'Folder targets:' with a 'Delete' button to its right. At the bottom of the dialog, there are three buttons: '< Back', 'Next >' (highlighted with a blue border), and 'Cancel'.

5. Click **Next** if you do not want to add folder targets at this point and continue with Step 9.
6. (Optional) Enter the UNC path to the shared folder you want to be a folder target.



This screenshot is similar to the previous one, but the 'Path to folder target:' text input field now contains the UNC path '\\DGWin16B\Support Tickets'. The 'Add' button is still present to the right of the input field. The 'Folder targets:' text area and the 'Delete' button are also visible. The 'Next >' button at the bottom is still highlighted with a blue border.

7. Click **Add**.

The folder target is added to the **Folder targets** section.

The screenshot shows the 'New Folder' dialog box with the 'Folder Targets' step selected. The dialog has a title bar with a minimize, maximize, and close button. Below the title bar, the text 'Folder Targets' is displayed, followed by the instruction 'Select one or more folder targets for this folder.' On the left side, there is a vertical list of steps: 'Folder Name', 'Folder Targets' (highlighted), 'Confirmation', and 'Results'. The main area contains the following text: 'Enter the UNC path to an existing folder. If the folder is not shared, you must share it first.' Below this is a text input field labeled 'Path to folder target:' with the example '\\Server\Shared Folder\Folder Target' and an 'Add' button. Underneath is a list box labeled 'Folder targets:' containing the entry '\\DGWin16B\Support Tickets' and a 'Delete' button. At the bottom of the dialog are three buttons: '< Back', 'Next >' (highlighted), and 'Cancel'.

- Repeat Steps 6-7 to add additional folder targets if desired.
- Click **Next**.


The **Confirmation** page is displayed.

The screenshot shows the 'New Folder' dialog box with the 'Confirmation' step selected. The dialog has a title bar with a minimize, maximize, and close button. Below the title bar, the text 'Confirmation' is displayed, followed by the question 'Do you want to add the following folder and folder targets?'. On the left side, there is a vertical list of steps: 'Folder Name', 'Folder Targets', 'Confirmation' (highlighted), and 'Results'. The main area contains the following text: 'Folder: \\PeerTest.local\Technical Support\Support Tickets'. Below this is the text 'Folder Targets:' followed by two entries: '\\DGWin16B\Support Tickets' and '\\DGWin16C\Support Tickets'. At the bottom of the dialog are three buttons: '< Back', 'Add' (highlighted), and 'Cancel'.

- Review the folders and folder targets.


11. Click **Add** if the configuration is correct; otherwise, click **Back** and correct the configuration.

The **Results** page is displayed.




12. Click **Close**.

The runtime view for the job is displayed. The newly added folders are listed in the job's **Namespace** tab.



13. Click the folder you just added.

The newly added folder targets are listed in the **Folder Target** section of the tab. (Depending on how many namespace folders you have, you may need to scroll to view the **Folder Target** section.)




Adding a Namespace Folder Target

You can add a folder target for a namespace folder.


Note: A DFS-N Namespace job must be running before you can edit it.

To add a folder target for a namespace folder:


1. Double-click the job name in the **Jobs** view or the [Namespace Summary view](#) to open the runtime view for the job.



The runtime view for the job is displayed.




2. Right-click the folder you want to add a folder target to, and then select **Add Folder Target**.




The **New Folder Target** wizard appears.

3. Enter the UNC path to a shared folder.



4. Click **Add**.


The folder target is added to the **Folder targets** section



The screenshot shows the 'New Folder Target' dialog box with the 'Folder Targets' tab selected. The dialog has a title bar with a minimize, maximize, and close button. Below the title bar, the text reads 'Folder Targets' and 'Select one or more folder targets for this folder.' On the left, there is a vertical navigation pane with 'Folder Targets', 'Confirmation', and 'Results' options. The main area contains instructions: 'Enter the UNC path to an existing folder. If the folder is not shared, you must share it first.' Below this is a text input field labeled 'Path to folder target:' with the example '\\Server\Shared Folder\Folder Target' and an 'Add' button. Underneath is a list box labeled 'Folder targets:' containing '\\DGWin16B\Tests' and a 'Delete' button. At the bottom, there are three buttons: '< Back', 'Next >', and 'Cancel'.

5. Repeat Steps 3-4 to add additional folder targets if desired.
6. Click **Next**.


The **Confirmation** page is displayed.



The screenshot shows the 'New Folder Target' dialog box with the 'Confirmation' tab selected. The dialog has the same title bar as the previous screenshot. Below the title bar, the text reads 'Confirmation' and 'Do you want to add the following folder targets to: QA ?'. On the left, the vertical navigation pane now has 'Confirmation' selected. The main area contains the text 'Add Folder Targets:' followed by a list of two folder targets: '\\DGWin16B\Tests' and '\\DGWin16C\Tests'. At the bottom, there are three buttons: '< Back', 'Create', and 'Cancel'.


7. Review the folder targets.
8. Click **Create** if the configuration is correct; otherwise, click **Back** and correct the configuration.

The **Results** page is displayed.




9. Click **Close**.

The runtime view for the job is displayed.



10. Click the folder you just added.

The newly added folder targets are listed in the **Folder Target** section of the job's **Namespace** tab. (Depending on how many namespace folders you have, you may need to scroll to view the **Folder Target** section.)



Linking a DFS Namespace to File Collaboration and File Synchronization Jobs

The primary benefit of using PeerGFS's ability to manage DFS namespaces is that PeerGFS can be configured to automatically disable and enable folder targets when they become unavailable, helping to control [failover and failback](#). This is a manual process using Microsoft DFS Namespaces but PeerGFS can automatically disable or enable targets based on the state of a linked collaboration/synchronization job. This ensures a folder target is not available to users until a failed server has come back online and is in sync again.

To take advantage of the failover and failback capabilities, the File Collaboration or File Synchronization job must be linked to the DFS-N Management job that manages the namespace.

There are various ways to link a File Collaboration or File Synchronization job to a DFS-N Management job, including:

- If the File Collaboration or File Synchronization job does not yet exist, you can:
 - Create a File Collaboration or File Synchronization job and link it to a namespace while you are creating the job. When creating the job, you are given the option to create a new namespace, import one, or use an existing one. The DFS-N Management job is automatically created when using this method. See [Step 8: DFS Management](#) in Creating a File Collaboration job or in Creating a File Synchronization job for more information.

- Create one from the DFS namespace folder. See [Create a File Collaboration or Synchronization Job from a Namespace Folder](#) for step-by-step instructions.
- If the File Collaboration or File Synchronization job already exists, edit the job and link it to the DFS-N Management job. Use the [DFS-N settings page in the Edit File Collaboration Job wizard](#) and [DFS-N settings page in the Edit File Synchronization Job wizard](#) to link them. See [Linking a Namespace with an Existing File Collaboration or Synchronization Job](#) for step-by-step instructions.

Note: Currently, only File Collaboration and File Synchronization jobs can be linked to a DFS-N Management job.

Creating a File Collaboration or File Synchronization Job from a Namespace Folder

You can create a File Collaboration or File Synchronization job from a DFS namespace folder. These steps require that the DFS namespace has been already created and is being managed by Peer Management Center.

To create a File Collaboration or File Synchronization job from a namespace folder:


1. From the **Jobs** view, open the DFS-N Management job managing the namespace.

The screenshot shows the Peer Management Center Client interface. The 'Jobs' view is active, displaying a table of jobs. The 'Alerts' pane is also visible, showing a list of alerts.


Name	Overall Status	Job Type	Failed Hosts	Quara...	Retries	Errors	Warnin...	Open Files	Pending B...	Queued It...	Background S...	Scan St...	Elapsed T...	Ses
Development Projects	Stopped	File Collaboration	0	0	0	0	0	0	0 bytes	0	0	Stopped	00:00:00	Siz
FC-1	Stopped	File Collaboration	0	0	0	0	0	0	0 bytes	0	0	Stopped	00:00:00	Siz
FC-2	Stopped	File Collaboration	0	0	0	0	0	0	0 bytes	0	0	Stopped	00:00:00	Siz
FC-3	Stopped	File Collaboration	0	0	0	0	0	0	0 bytes	0	0	Stopped	00:00:00	Siz
FC-4	Stopped	File Collaboration	0	0	0	0	0	0	0 bytes	0	0	Stopped	00:00:00	Siz
FR-1	Stopped	File Replication	0	0	0	0	0	0	0 bytes	0	0	Stopped	00:00:00	Siz
FS-1	Stopped	File Synchronization	0	0	0	0	0	0	0 bytes	0	0	Stopped	00:00:00	Siz

The [DFS-N Management Job runtime view](#) is displayed.


2. Open the **Namespace** tab if it is not already displayed.



- In the **Namespace** tab, right-click the desired namespace folder and select **Create New Job**.



The **Create New Job** wizard displays a list of job types you can create: File Collaboration and File Synchronization. The other job types are not supported for use with DFS namespace management.




4. Select a job type and click **Create**:
 - Select **File Collaboration** if locking is required in addition to replication (for example, for data sets with shared project files).
 - Select **File Synchronization** if no locking is required (for example, with home directory and user profile datasets).
5. Follow the wizard prompts as it walks you through creating the job:
 - Naming the job
 - Adding the participants
 - Choosing File Metadata options
 - Choosing Application Support options.
 - Selecting email alerts

The process is the same as described in [Creating a File Collaboration Job](#) and [Creating a File Synchronization Job](#).

Once you have selected your email alerts, the **DFS Namespace** page is displayed.

The **Enable DFS Linking** checkbox is preselected and the **Select Existing DFS Namespace** option is selected.




6. Click **Next** if you want to create folder targets; otherwise click **Finish** and continue with Step 9.

You can create folder targets later if you wish. See [Adding a Namespace Folder Target](#) for step-by-step instructions.

If you clicked **Next**, the **DFS Link** page appears. The purpose of this page is to link the watch path of each participant of a collaboration/synchronization job (specified in the **Path** page) to the appropriate folder target.


Initially, the **Folder Target** column in the **Linked Participants and Folder Targets** table will not contain any folder targets. After linking, a folder target should be listed in this column for each participant.



7. Link the participants to folder targets using one or more of the following methods:

- Click **Auto Select Targets** to have PeerGFS select the targets for you. If you use this method, PeerGFS will try to match the watch path specified for each participant. It will populate the **Folder Target** column with its matches.
- Manually link the participants by typing a path in the **Folder Target** column.
- Use a combination of auto select and manually select. For example, you can use auto select, and if the correct targets are not selected, you can manually enter the folder target path in the Folder Target column.
- If an incorrect target appears in the **Folder Target** column, you can select the incorrect target, and then click **Remove Selected Target**.


After linking targets, the **Linked Participants and Folder Targets** table should contain a folder target for each participant.



8. If the **Link Enabled** column is blank, select **Yes** for each participant.

9. Click **Finish**.

The [runtime view](#) for the newly created File Collaboration or File Synchronization job is displayed.



10. Click the DFS-N Management job tab to display its runtime view.

The **Linked to Participant** column is now populated.

The screenshot shows the Peer Management Center Client interface. The main window displays a 'Namespace Summary' table for the namespace '\\PeerTestLocal\Documentation'. The table has columns for Folder Target, Linked to Participant, Status, Reason, AD Site, and Replication Status. A red box highlights the 'Linked to Participant' column, which contains the values 'DGWin16B', 'DGWin16D', and 'DGWin16C'. The 'Status' column shows 'Active' for all three entries. The 'Replication Status' column shows 'Inactive - Not Participating' for all three entries.

Folder Target	Linked to Participant	Status	Reason	AD Site	Replication Status
\\DGWIN16B\User Guides-DC	DGWin16B	Active	-	US-HQ	Inactive - Not Participating
\\DGWIN16D\User Guides-Cape Town	DGWin16D	Active	-	US-HQ	Inactive - Not Participating
\\DGWIN16C\User Guides-Munich	DGWin16C	Active	-	US-HQ	Inactive - Not Participating


Below the table, there is an 'Alerts' section showing a list of alerts with columns for Received Date, Severity, Type, Name, Host, Message, and Exception. The alerts are filtered by 'Host' and show various connection and startup events for hosts DGWin16A, DGWin16B, and DGWin16C.

Linking an Existing Namespace Folder to an Existing File Collaboration or File Synchronization Job

You can link an existing DFS namespace folder with an existing File Collaboration or File Synchronization job. These steps require that the DFS namespace has been already created and is being managed by a DFS-N Management job.


To link a namespace folder with an existing File Collaboration or File Synchronization job:

1. Select the File Collaboration or File Synchronization job in the **Jobs** view.




2. Right-click and select **Edit Job**.

The **Edit Job** wizard appears.




3. Select **DFS-N** in the navigation tree on the left.

The DFS-N page is displayed.




4. In the **DFS Namespace Folder** area, select the namespace you want to link to from the first drop-down list.




Once you've selected a namespace, a list of available namespace folders appears in the **Folder** drop-down list.

5. Select the namespace folder from **Folder**.




Once you've selected a namespace and a folder, you need to link each participant to a folder target.




- Click **Auto Select Targets** to have PeerGFS attempt to automatically map the participants with folder target.

After auto selection, the linked participants and folder targets are displayed in the **Linked Participants and Folder Targets** table.



Tip: In most cases, clicking the **Auto Select Targets** button, PeerGFS will be able to automatically link a folder target with the appropriate participant. However, if a folder does not have the appropriate folder targets, click the **Auto Create Targets** button. The wizard that appears will use the paths configured in your File Collaboration or File Synchronization job and try to automatically create folder targets for you.



- Review the values in the **Link Enabled** column; if **No** appears, select **Yes** from the drop-down list.
- Once all participants are linked to the appropriate folder targets, click **OK** to save your changes.

The runtime window appears. From this point forward, if this collaboration or synchronization job is running along with its paired DFS-N Management job, Peer Management Center will automatically [failover and failback](#) folder targets.

File Collaboration Jobs

This section provides information about creating, editing, running, and managing a File Collaboration job:

- [Overview](#)
- [Before You Create Your First File Collaboration Job](#)
- [Creating a File Collaboration Job](#)
- [Editing a File Collaboration Job](#)
- [Running and Managing a File Collaboration Job](#)
- [Runtime Job Views](#)

Overview

A File Collaboration job provides distributed teams a fast and efficient way to collaborate with shared project files. Unlike other file collaboration solutions that centralize files into a single data repository that cause slow file access across a WAN, a File Collaboration job replicates shared project files to each office site in a distributed environment so that end users are guaranteed high-speed LAN access to shared files no matter their file size. Version conflicts are prevented through integrated distributed file locking.

By keeping hot data local, File Collaboration maximizes end user productivity. Because files are close to the users, their applications, and their compute resources, the actual performance is as fast as possible from a physical view. At the same time File Collaboration ensures version conflicts are eliminated with file locking.

Before You Create Your First File Collaboration Job

We strongly recommend that you configure the File Collaboration settings (e.g., SMTP notifications), as well as other [global settings](#) such as SMTP email settings, email alerts, and file filters before configuring your first File Collaboration job. See [Preferences](#) for details on these settings.

Creating a File Collaboration Job

The **Create Job** wizard walks you through the process of creating a File Collaboration job. The process consists of the following steps:

[Step 1: Job Type and Name](#)

[Step 2: Participants](#)

[Step 3: File Metadata](#)

[Step 4: Application Support](#)

[Step 5: Email Alerts](#)


[Step 6: Save Job](#)

Additional configuration options, such as applying [file filters](#) and specifying [delta level replication](#), are available when [editing a File Collaboration job](#).

Step 1: Job Type and Name


1. Open Peer Management Center.
2. From the **File** menu, select **New Job** (or click the **New Job** button on the toolbar).

The **Create New Job** wizard displays a list of job types you can create.



3. Click **File Collaboration**, and then click **Create**.
4. Enter a name for the job in the dialog that appears.

The job name must be unique.



5. Click **OK**.

The [Participants](#) page appears.

Step 2: Participants

After selecting the job type and naming the job, the **Participants** page is displayed. It contains a table that will display the job [participants](#) once you have added them. A File Collaboration job must have two or more participants. A **participant** consists of an Agent and the volume/share/folder to be replicated. A File Collaboration job synchronizes the files of participants in real-time and adds distributed locking to avoid version conflicts.

1. Click the **Add** button to start the process of adding a participant.

Agent	Computer Description	Directory	Enabled	Storage Platform	Seeding Target	DSU Role

The **Add New Participant** wizard opens; it walks you through the steps for adding a participant:

- a. [Selecting a Management Agent](#), which is the Agent that will manage the storage device that hosts data you want to replicate.
- b. [Selecting the type of storage platform](#) that hosts data you want to replicate.
- c. [Entering the credentials needed to access a specific storage device and providing other storage information.](#)
- d. [Entering the path](#) to the [watch set](#) (the data that you want to replicate) and selecting whether participant will be a [seeding target](#).
- e. (Optional) [Enabling Dynamic Storage Utilization](#) for the participant.

Once you have added a participant, it is listed in the **Participants** table.

The screenshot shows the 'Create File Collaboration Job Wizard' window. The title bar reads 'Create File Collaboration Job Wizard'. Below the title bar, the text 'Participants' is followed by the instruction 'Add two or more participants to this File Collaboration job.' On the left side, there is a list of options: 'Participants', 'Master-Edge Assignment', 'File Metadata', 'Application Support', 'Email Alerts', and 'DFS Namespace'. The 'Participants' option is selected. The main area contains a table with the following columns: Agent, OS, Description, Directory, Enabled, Storage Platform, Seeding Target, and DSU Role. The table has one row with the following data: Agent: DGWin168, OS: Microsoft Windows, Description: (empty), Directory: C:\Users\debrag, Enabled: Yes, Storage Platform: Windows Driver, Seeding Target: No, DSU Role: Master. To the right of the table are three buttons: 'Add', 'Edit', and 'Delete'. At the bottom of the window are three buttons: '< Back', 'Next >', and 'Cancel'.

Agent	OS	Description	Directory	Enabled	Storage Platform	Seeding Target	DSU Role
DGWin168	Microsoft Windows		C:\Users\debrag	Yes	Windows Driver	No	Master

2. To add more participants, click **Add** and repeat the steps for each participant you want to add to the job.
3. Once you have added all the participants, click **Next**.

The screenshot shows the 'Create File Collaboration Job Wizard' window. The title bar reads 'Create File Collaboration Job Wizard'. Below the title bar, the text 'Participants' is followed by the instruction 'Add two or more participants to this File Collaboration job.' On the left side, there is a list of options: 'Participants', 'Master-Edge Assignment', 'File Metadata', 'Application Support', 'Email Alerts', and 'DFS Namespace'. The 'Participants' option is selected. The main area contains a table with the following columns: Agent, OS, Description, Directory, Enabled, Storage Platform, Seeding Target, and DSU Role. The table has three rows with the following data: Row 1: Agent: DGWin168, OS: Microsoft Windows, Description: (empty), Directory: C:\Users\debrag, Enabled: Yes, Storage Platform: Windows Driver, Seeding Target: No, DSU Role: Master; Row 2: Agent: DGWin16C, OS: Microsoft Windows, Description: (empty), Directory: C:\Users\debrag, Enabled: Yes, Storage Platform: Windows Driver, Seeding Target: No, DSU Role: Master; Row 3: Agent: DGWin16D, OS: Microsoft Windows, Description: (empty), Directory: C:\Users\debrag, Enabled: Yes, Storage Platform: Windows Driver, Seeding Target: No, DSU Role: Edge. To the right of the table are three buttons: 'Add', 'Edit', and 'Delete'. At the bottom of the window are three buttons: '< Back', 'Next >', and 'Cancel'.


Agent	OS	Description	Directory	Enabled	Storage Platform	Seeding Target	DSU Role
DGWin168	Microsoft Windows		C:\Users\debrag	Yes	Windows Driver	No	Master
DGWin16C	Microsoft Windows		C:\Users\debrag	Yes	Windows Driver	No	Master
DGWin16D	Microsoft Windows		C:\Users\debrag	Yes	Windows Driver	No	Edge

The page that appears next depends on options you selected when adding a participant:

- if you have enabled Dynamic Storage Utilization for a participant, the [Master-Edge Assignment](#) page appears.
- Otherwise, the [File Metadata](#) page appears.

The **Storage Platform** page lists the types of storage platforms that File Collaboration supports.

1. Select the type of storage platform that hosts the data you want to replicate.



The screenshot shows a dialog box titled "Add New Participant" with a "Storage Platform" section. The instruction "Select the type of storage platform." is displayed. On the left, a sidebar lists navigation options: "Management Agent", "Storage Platform" (highlighted), "Storage Information", "Path", and "Dynamic Storage Utilization". The main area contains a list of storage platform options, each with a radio button and a logo:

- Windows File Server
- NetApp ONTAP | Clustered Data ONTAP
- NetApp Data ONTAP 7-Mode
- FSx Amazon FSxN
- Dell PowerScale | EMC Isilon
- Dell EMC Unity
- Dell EMC Celerra | VNX | VNX 2
- Nutanix Files

At the bottom, there are four buttons: "< Back" (highlighted with a blue border), "Next >", "Finish", and "Cancel".

2. Click **Next**.

The [Storage Information](#) page is displayed.

On the **Storage Information** page, you will select the storage device containing data that you want to replicate and enter other information about the storage device. The contents of the **Storage Information** page varies, depending on your selection in the [Storage Platform](#) page:

- If you selected **Windows File Server**, you are prompted for configuration information relating to Windows File Server. Continue with the [Windows File Server](#) page.
- If you selected any other type of storage device other than Windows File Server, the **Storage Information** page requests the credentials necessary to connect to that storage device. Continue with the steps below.

For storage platforms other than Windows File Server:

1. Select **New Credentials** or **Existing Credentials**.
2. If you selected **Existing Credentials**, select a credential from the drop-down list, and then click **Next** to continue to the [Path](#) page.

If you selected **New Credentials**, enter the credentials for connecting to the storage device. The information you are prompted to enter varies, depending on the type of storage platform:

[Amazon FSxN](#)

[Dell EMC Unity](#)

[Dell EMC Celerra | VNX | VNX 2](#)

[Dell PowerScale | EMC Isilon](#)

[NetApp Data ONTAP 7-ModeNetApp ONTAP | Clustered Data ONTAP](#)

[Nutanix Files](#)

3. Click **Validate** to test the credentials.

After the credentials are validated, a success message appears.

4. Click **Next**.

The [Path](#) page is displayed.

Amazon FSxN

1. Select **New Credentials** or **Existing Credentials** to enter the credentials to connect to the Storage Virtual Machine hosting the data to be replicated.

The screenshot shows a window titled "Add New Participant" with a "Storage Information" tab selected. The window contains a sidebar with navigation options: "Management Agent", "Storage Platform", "Storage Information" (highlighted), "Path", and "Dynamic Storage Utilization". The main area is titled "Storage Information" and contains the instruction "Enter the information required to connect to the storage device." Below this, there are two radio button options under the heading "Credentials": "New Credentials" (selected) and "Existing Credentials". The "New Credentials" section includes five input fields: "*SVM Name:", "*SVM User Name:", "*SVM Password:", "SVM Management IP:", and "*Peer Agent IP:". An "Advanced" button is located to the right of the "*Peer Agent IP" field. Below the "Existing Credentials" radio button is a drop-down menu. At the bottom of the main area is a "Validate" button. A note at the bottom of the main area reads: "Having trouble connecting? Please verify that all [prerequisites](#) are met for Amazon FsxN environments." At the very bottom of the window are four buttons: "< Back", "Next >", "Finish", and "Cancel".

2. If you selected **Existing Credentials**, select a credential from the drop-down list, and then click **Next** to continue to the [Path](#) page.

If you selected **New Credentials**, supply the required information.

Field	Description
SVM Name	Enter the name, FQDN, or IP address of the Storage Virtual Machine hosting the data to be replicated.
SVM User Name	Enter the user name for the account managing the Storage Virtual Machine. This must not be a cluster management account.
SVM Password	Enter the password for the account managing the Storage Virtual Machine. This must not be a cluster management account.
SVM Management IP	(Optional) Enter the IP address used to access the management API of the Storage Virtual Machine. If the data LIFs (Logical Interfaces) corresponding to the SVM Name above already allow management access, this field is not required.
Peer Agent IP	Select the IP address of the server hosting the Agent that manages the Storage Virtual Machine. The Storage Virtual Machine must be able to route traffic to this IP address. If the IP address you want does not appear, manually enter the address.

3. Click **Advanced** if you want to set [advanced options](#).
4. Click **Validate** to test the credentials.

After the credentials are validated, a success message appears.

5. Click **Next**.

The [Path](#) page is displayed.

Dell EMC Celerra | VNX | VNX 2

1. Select **New Credentials** or **Existing Credentials** to enter the credentials to connect to the CIFS Server hosting the data to be replicated or select existing credentials.

The screenshot shows a window titled "Add New Participant" with a close button in the top right corner. The main heading is "Storage Information" with a sub-heading "Enter the information required to connect to the storage device." On the left is a sidebar with a tree view containing "Management Agent", "Storage Platform", "Storage Information" (highlighted), "Path", and "Dynamic Storage Utilization". The main area is divided into two sections: "Credentials" and "Existing Credentials". The "Credentials" section has a radio button selected for "New Credentials" and four text input fields: "*CIFS Server Name:", "*Control Station Username:", "*Control Station Password:", and "*Control Station IP:". An "Advanced" button is located to the right of these fields. The "Existing Credentials" section has a radio button and a drop-down menu. At the bottom left is a "Validate" button. Below the form is a note: "Having trouble connecting? Please verify that all [prerequisites](#) are met for Dell EMC VNX/Celerra environments." At the bottom right are three buttons: "< Back", "Next >", and "Cancel".

2. If you selected **Existing Credentials**, select a credential from the drop-down list, and then click **Next** to continue to the [Path](#) page.

If you selected **New Credentials**, supply the required information.

Field	Description
CIFS Server Name	Enter the name of the CIFS Server hosting the data to be replicated.
Control Station Username	Enter the user name for the Control Station account managing the Celerra/VNX storage device.
Control Station Password	Enter the password for the Control Station account managing the Celerra/VNX storage device.
Control Station IP	Enter the IP address of the Control Station system used to manage the Celerra/VNX storage device. This should not point to the CIFS Server.

3. Click **Advanced** if you want to set [advanced options](#).
4. Click **Validate** to test the credentials.

After the credentials are validated, a success message appears.

5. Click **Next**.

The [Path](#) page is displayed.

Dell EMC Unity

1. Select **New Credentials** or **Existing Credentials** to enter the credentials to connect to the NAS server hosting the data to be replicated.

The screenshot shows a window titled "Add New Participant" with a close button in the top right corner. The main heading is "Storage Information" with a sub-heading "Enter the information required to connect to the storage device." On the left is a sidebar menu with "Storage Information" selected. The main area contains a "Credentials" section with two radio buttons: "New Credentials" (selected) and "Existing Credentials". Under "New Credentials" are four text input fields: "*CIFS Server Name:", "*Unisphere Username:", "*Unisphere Password:", and "*Unisphere Management IP:". An "Advanced" button is to the right of these fields. Below the "Existing Credentials" radio button is a drop-down menu. A "Validate" button is at the bottom left of the form area. A note at the bottom reads: "Having trouble connecting? Please verify that all [prerequisites](#) are met for Dell EMC Unity environments." At the bottom of the window are three buttons: "< Back", "Next >", and "Cancel".

2. If you selected **Existing Credentials**, select a credential from the drop-down list, and then click **Next** to continue to the [Path](#) page.

If you selected **New Credentials**, supply the required information.

Field	Description
CIFS Server Name	Enter the name of the NAS server hosting the data to be replicated.
Unisphere Username	Enter the user name for the Unisphere account managing the Unity storage device.
Unisphere Password	Enter the password for the Unisphere account managing the Unity storage device.
Unisphere Management IP	Enter the IP address of the Unisphere system used to manage the Unity storage device. This should not point to the NAS server.

3. Click **Advanced** if you want to set [advanced options](#).

4. Click **Validate** to test the credentials.

After the credentials are validated, a success message appears..

5. Click **Next**.

The [Path](#) page is displayed.

Dell PowerScale | EMC Isilon

1. Select **New Credentials** or **Existing Credentials** to enter the credentials to connect the PowerScale or Isilon cluster hosting the data to be replicated.

The screenshot shows a window titled "Add New Participant" with a "Storage Information" section. The instruction reads: "Enter the information required to connect to the storage device." On the left, a sidebar lists "Management Agent", "Storage Platform", "Storage Information" (highlighted), "Path", and "Dynamic Storage Utilization". The main area is titled "Credentials" and has two radio buttons: "New Credentials" (selected) and "Existing Credentials". Under "New Credentials", there are five text input fields: "*Cluster Name:", "*Cluster Username:", "*Cluster Password:", "Cluster Management IP:", and "Nodes:". An "Advanced" button is located to the right of the "Nodes" field. Below the "Existing Credentials" radio button is a dropdown menu. A "Validate" button is positioned below the dropdown. At the bottom of the main area, a note says: "Having trouble connecting? Please verify that all [prerequisites](#) are met for Dell PowerScale | EMC Isilon environments." The bottom of the window features four buttons: "< Back", "Next >", "Finish", and "Cancel".

2. If you selected **Existing Credentials**, select a credential from the drop-down list, and then click **Next** to continue to the [Path](#) page.

If you selected **New Credentials**, supply the required information.

Field	Description
Cluster Name	Enter the name of the PowerScale or Isilon cluster hosting the data to be replicated.
Cluster Username	Enter the user name for the account managing the PowerScale or Isilon cluster.
Cluster Password	Enter the password for account managing the PowerScale or Isilon cluster.
Cluster Management IP	(Optional) Enter the IP address of the system used to manage the PowerScale or Isilon cluster. Required only if multiple Access Zones are in use on the cluster.
Nodes	(Optional) Enter one IP from each node in the cluster that the Agent can access to perform open file lookups. Use commas to separate nodes.

3. Click **Advanced** if you want to set [advanced options](#).
4. Click **Validate** to test the credentials.

After the credentials are validated, a success message appears.

5. Click **Next**.

The [Path](#) page is displayed.

NetApp ONTAP 7-Mode

1. Select **New Credentials** or **Existing Credentials** to enter the credentials to connect to the NetApp 7-Mode filer or vFiler hosting the data to be replicated.

Add New Participant

Storage Information
Enter the information required to connect to the storage device.

Management Agent
Storage Platform
Storage Information
Path
Dynamic Storage Utilization

Credentials
 New Credentials
 Existing Credentials

*Filer Name:

Advanced

Validate

Having trouble connecting? Please verify that all [prerequisites](#) are met for NetApp 7-Mode environments.

< Back Next > Cancel

- If you selected **Existing Credentials**, select a credential from the drop-down list, and then click **Next** to continue to the [Path](#) page.

If you selected **New Credentials**, supply the required information.

Field	Description
Filer Name	Enter the name of the NetApp 7-Mode filer or vFiler hosting the data to be replicated.

- Click **Advanced** if you want to set [advanced options](#).
- Click **Validate** to test the credentials.

After the credentials are validated, a success message appears.

- Click **Next**.

The [Path](#) page is displayed.

NetApp ONTAP | Clustered Data ONTAP

1. Select **New Credentials** or **Existing Credentials** to enter the credentials to connect to the Storage Virtual Machine hosting the data to be replicated.

The screenshot shows a window titled "Add New Participant" with a close button in the top right corner. The main heading is "Storage Information" with a sub-heading "Enter the information required to connect to the storage device." On the left is a navigation pane with options: "Management Agent", "Storage Platform", "Storage Information" (selected), "Path", and "Dynamic Storage Utilization". The main area is divided into two sections under the heading "Credentials". The first section, "New Credentials", is selected with a radio button and contains five input fields: "*SVM Name:", "*SVM User Name:", "*SVM Password:", "SVM Management IP:", and "*Peer Agent IP:". An "Advanced" button is located to the right of the "*Peer Agent IP" field. The second section, "Existing Credentials", is unselected and contains a drop-down menu. At the bottom left is a "Validate" button. At the bottom right are three buttons: "< Back", "Next >", and "Cancel". A footer note reads: "Having trouble connecting? Please verify that all [prerequisites](#) are met for NetApp ONTAP/cDOT environments."

2. If you selected **Existing Credentials**, select a credential from the drop-down list, and then click **Next** to continue to the [Path](#) page.

If you selected **New Credentials**, supply the required information.

Field	Description
SVM Name	Enter the name, FQDN, or IP address of the Storage Virtual Machine hosting the data to be replicated.
SVM User Name	Enter the user name for the account managing the Storage Virtual Machine. This must not be a cluster management account.
SVM Password	Enter the password for the account managing the Storage Virtual Machine. This must not be a cluster management account.
SVM Management IP	(Optional) Enter the IP address used to access the management API of the Storage Virtual Machine. If the data LIFs (Logical Interfaces) corresponding to the SVM Name above already allow management access, this field is not required.
Peer Agent IP	Select the IP address of the server hosting the Agent that manages the Storage Virtual Machine. The Storage Virtual Machine must be able to route traffic to this IP address. If the IP address you want does not appear, manually enter the address.

3. Click **Advanced** if you want to set [advanced options](#).
4. Click **Validate** to test the credentials.

After the credentials are validated, a success message appears.

5. Click **Next**.

The [Path](#) page is displayed.

Nutanix Files

1. Select **New Credentials** or **Existing Credentials** to enter the credentials to connect to the Nutanix Files cluster hosting the data to be replicated.

The screenshot shows a window titled "Add New Participant" with a close button in the top right corner. The main heading is "Storage Information" with a sub-heading "Enter the information required to connect to the storage device." On the left is a sidebar with a tree view containing "Management Agent", "Storage Platform", "Storage Information" (highlighted), "Path", and "Dynamic Storage Utilization". The main area is divided into two sections: "Credentials" and "Existing Credentials". Under "Credentials", there is a radio button for "New Credentials" (which is selected) and four input fields: "*Nutanix File Server Name:", "*Username:", "*Password:", and "*Peer Agent IP:". An "Advanced" button is located to the right of the "*Peer Agent IP:" field. Below this is a radio button for "Existing Credentials" and a corresponding drop-down menu. At the bottom left of the main area is a "Validate" button. Below the main area is a note: "Having trouble connecting? Please verify that all [prerequisites](#) are met for Nutanix Files environments." At the bottom of the window are three buttons: "< Back", "Next >", and "Cancel".

2. If you selected **Existing Credentials**, select a credential from the drop-down list, and then click **Next** to continue to the [Path](#) page.

If you selected **New Credentials**, supply the required information.

Field	Description
Nutanix File Server Name	Enter the name of the Nutanix Files cluster hosting the data to be replicated.
Username	Enter the user name for the account managing the Nutanix Files cluster via its management APIs.
Password	Enter the password for the account managing the Nutanix Files cluster via its management APIs.
Peer Agent IP	Select the IP address of the server hosting the Agent that manages the Nutanix Files cluster. The Files cluster must be able to route traffic to this IP address. If the IP address you want does not appear, manually enter the address. The address should not point to the Files cluster itself.

3. Click **Advanced** if you want to set [advanced options](#).
4. Click **Validate** to test the credentials.

After the credentials are validated, a success message appears.

5. Click **Next**.

The [Path](#) page is displayed.

Windows File Server

1. Select the **Detector Type**:
 - Select **Windows Driver** for more robust logging and better performance (Recommended).
 - Select **Windows** if suggested by Peer Technical Support.

The screenshot shows a window titled "Add New Participant" with a close button in the top right corner. Below the title bar, the text "Storage Information" is displayed, followed by the instruction "Enter the information required to connect to the storage device." On the left side, there is a vertical list of options: "Management Agent", "Storage Platform", "Storage Information" (which is highlighted), "Path", and "Dynamic Storage Utilization". The main area of the dialog is a large, empty light gray space. At the top of this area, there is a label "Detector Type:" followed by a dropdown menu showing "Windows Driver". To the right of the main area is a button labeled "Advanced". At the bottom of the dialog, there are three buttons: "< Back", "Next >" (which is highlighted with a blue border), and "Cancel".


2. Click **Advanced** if you want to set [advanced options](#).
3. Click **Next**.

The [Path](#) page is displayed.

1. Modify the options as desired.

The available options depend on the detector type selected: **Windows** or **Windows Driver**.

Windows



Windows Driver

The screenshot shows a dialog box titled "Windows Driver Detector Options". It contains several configuration options:

- Filter open/close events from these users: [Empty text box]
- Filter all events from these users: [Empty text box]
- Filter events from these IP Addresses: [Empty text box]
- Filter events from these local processes: [Empty text box]
- Access Event Suppression Time: [Spin box with value -1]
- Enable Local Access Events:
- Enable Remote IP Address Logging:
- Enable Close Modify:
- Close Modify Extension Override: [Empty text box]

Below these options is a section titled "Reparsing Point Options" containing three checked checkboxes:

- Follow Junction Points
- Follow Mount Points
- Follow Symbolic Links

At the bottom right of the dialog are two buttons: "OK" and "Cancel".

Option	Description
Filter open/close events from these users	Enter a comma-separated list of user account names from which all file opens and closes will be ignored. This option can be used to filter out events from backup and/or archival services by filtering on the user name under which a backup and/or archival service is running.
Filter all events from these users	Enter a comma-separated list of user account names from which all file activities will be ignored. This option can be used to filter out events from backup and/or archival services by filtering on the user name under which a backup and/or archival service is running.
Filter events from these IP Addresses	Enter a comma-separated list of client IP addresses from which all file activities will be ignored. This option can be used to filter out events from backup and/or archival services by filtering on the IP addresses on which a backup and/or archival service is running.
Filter events from these local processes	Enter a comma-separated list of local process names on the Agent server from which all file activities will be ignored. This option can be used to filter out events from backup and/or archival services by filtering on the specific process names under which a backup and/or archival service is running.
Access Event Suppression Time	Enter the number of seconds to delay an open event before being processed. Use this option to help reduce the amount of chatter generated by Windows clients when mousing over files in Windows Explorer. The default value is -1, which will use a globally set value. A value of 0 will allow for dynamic changes to the amount of time an open event will be delayed based on the load of the system.
Enable Local Access Events	Enable tracking of opens and closes that are performed locally on the Agent server.
Enable Remote IP Logging	Enable logging of client IP addresses for all real-time activity.
Enable Close Modify	When enabled, no modify or write events will be detected. Instead, replication of a modified file will be performed when the file is closed.
Close Modify Extension Override	Enter a comma-separated list of exclusions for the Enable Close Modify option. All modify/write events will be detected for these files. This is important for those who rely on sync-on-save functionality.

For more information about junction points or symbolic links, contact [<%
SUPPORT_EMAIL%](#)

2. Click **OK**.


The **Path** page is where you specify the path to the volume/share/folder you want to replicate. This volume/share/folder is referred to as the [watch set](#). The watch set can contain only a single volume/share/folder. If you want to replicate multiple volumes/shares/folders, you need to create a separate job for each one.

1. Browse to or enter the path to the watch set.

The screenshot shows a dialog box titled "Add New Participant" with a "Path" tab selected in the left-hand navigation pane. The main content area displays an "Enter Path" text input field followed by a "Browse" button. Below this is a "Seeding Target" checkbox, which is currently unchecked. A red error message at the top of the dialog reads "You must enter a valid path." At the bottom of the dialog, there are three buttons: "< Back", "Next >", and "Cancel".

2. (Optional) Select the **Seeding Target** checkbox, and then click **OK** in the dialog that appears.

If you select this option, a message describing seeding behavior is displayed. Multiple participants in a File Collaboration job can be set as smart data seeding targets; however, at least one participant should not be set as a smart data seeding target. All participants that are not set as seeding targets will become sources for the smart data seeding targets. For more information about smart data seeding, see [Smart Data Seeding](#) or contact support@peersoftware.com.



3. Click **Next** if you want this participant to use [Dynamic Storage Utilization](#); otherwise, click **Finish** to complete the wizard for this participant.

If you click **Finish**, return to [Step 2: Participants](#) to add more participants, if applicable. A File Collaboration job must have at least two participants.

Dynamic Storage Utilization (DSU) is a method for conserving space on storage devices by caching files until needed. DSU saves space by stubbing files and rehydrating them as needed. DSU is optional; if you don't need to conserve space on the storage device managed by the Agent, then you do not need to select this option.

If you enable [Dynamic Storage Utilization](#) (DSU) for a participant, you must designate the participant as either a **master** or **edge** participant.

- **Master participant** - A master participant always has complete set of files for that job. None of the files are stubbed; they are stored physically on that device.
- **Edge participant** - A subset of the files stored on a master participant are physically stored on an edge participant; the rest of the files on an edge participant are stub files that take up minimal space. DSU allows users to seamlessly retrieve stubbed files directly from a master participant as needed; when retrieved, the local stub file is rehydrated so that the full file is stored locally on the edge participant.

A job can have master and edge participants, as well as participants that don't have either role. If you do not choose to enable DSU for a participant, it will always have a full set of files like a master participant but will not be used to serve file content to any edge participants.

Notes:

- A participant can be a master participant for some jobs and an edge participant for other jobs.
- A job needs at least one master participant that isn't a seeding target. If there is only one master participant for the job, it should not be a seeding target.

For more information about DSU, see [Dynamic Storage Utilization](#) in [Advanced Topics](#).

1. Select the **Enable Dynamic Storage Utilization** checkbox if you want this participant to be able to use Dynamic Storage Utilization; otherwise, click **Finish**.

The screenshot shows a window titled "Add New Participant" with a subtitle "Dynamic Storage Utilization". Below the subtitle is the instruction "Enable Dynamic Storage Utilization and select role." The main area is split into two panes. The left pane contains a list of roles: "Management Agent", "Storage Platform", "Storage Information", "Path", and "Dynamic Storage Utilization". The "Dynamic Storage Utilization" role is highlighted with a grey background. The right pane contains a checkbox labeled "Enable Dynamic Storage Utilization" which is currently unchecked. At the bottom of the window, there are four buttons: "< Back", "Next >", "Finish", and "Cancel".

If you enable DSU, the DSU role options are displayed; the **Master** role is selected by default.

2. Choose a DSU role for the participant:

- Choose **Master** if the storage device managed by the Agent will contain complete copies of all files for this job. Any type of storage platform can be a master participant.

Dynamic Storage Utilization
Enable Dynamic Storage Utilization and select role.

Management Agent Storage Platform Storage Information Path ▼ Dynamic Storage Utilization Master Data Service	<input checked="" type="checkbox"/> Enable Dynamic Storage Utilization Select Dynamic Storage Utilization role: <input checked="" type="radio"/> Master <input type="radio"/> Edge
---	---

< Back Next > Cancel

- Choose **Edge** if you want to conserve space on the storage device managed by the Agent. Only Windows File Servers can be an edge participant.

The screenshot shows a window titled "Add New Participant" with a close button in the top right. The main heading is "Dynamic Storage Utilization" with the instruction "Enable Dynamic Storage Utilization and select role." On the left is a tree view with the following items: "Management Agent", "Storage Platform", "Storage Information", "Path", "Dynamic Storage Utilization" (expanded), "Volume Policy", "Utilization Policy", and "Pinning Filter". The "Dynamic Storage Utilization" section is active and contains a checked checkbox for "Enable Dynamic Storage Utilization" and a radio button selection for "Select Dynamic Storage Utilization role:" with "Edge" selected and "Master" unselected. At the bottom are three buttons: "< Back", "Next >" (highlighted with a blue border), and "Cancel".

3. Click **Next**.

- If you selected **Master**, continue with the [Master Data Service](#) page.
- If you selected **Edge**, continue with the [Volume Policy](#) page.

Master Data Service

The **Master Data Service** page appears if you chose the master role for the participant. The Master Data Service handles requests from edge participants for files on a master participant. The Master Data Service is installed on the Agent server as part of the Peer Agent installation process.

The first two fields on this page are automatically populated:

- **Protocol:** This field lists the protocol that will be used to transfer file content between master participants and edge participants. HTTPS is currently the only available option as

it requires only a single open firewall port on each master participant and does a better job of handling latency over WAN-based connections.

- **Agent Name:** This field lists the name of the Management Agent that you selected at the beginning of Step 2.
1. (Optional) Enter a value for **Agent Alias**. The value can be a hostname, FDQN, or IP address.

A value for this field is required only if the name of the Agent cannot be converted to an IP address via DNS. If an alias is entered, it will be used by the Edge Service on edge participants to connect with the Master Data Service. If no alias is entered, the Agent's name will be used.

2. (Optional) Modify the port number that the Master Data Service will listen on for this master participant.

A default value for the port number, 8446, is set when the Agent is installed. If you modify the port number, the Master Data Service is started with the new port number.

The screenshot shows a window titled "Add New Participant" with a sub-header "Master Data Service" and the instruction "Configure access to the Master Data Service." On the left is a tree view with categories: Management Agent, Storage Platform, Storage Information, Path, Dynamic Storage Utilization (expanded), and Master Data Service (selected). On the right are four input fields: Protocol (HTTPS), Agent Name (DGWin16B), Agent Alias (empty), and Port (8446). At the bottom are four buttons: < Back, Next >, Finish, and Cancel.

Note: If the Agent you selected is already being used as a master participant in another job utilizing DSU, then the existing Master Data Service parameters will be displayed. You can edit the values by clicking the **Edit Master Data Service** link. If you modify the

port number, the Master Data Service will be restarted and the new port number will take effect immediately. Any modifications you apply will be applied to every other job that use this Agent as a master participant.

The screenshot shows a window titled "Add New Participant" with a sub-header "Master Data Service". Below the sub-header is the instruction "Configure access to the Master Data Service." On the left side, there is a vertical navigation menu with the following items: "Management Agent", "Storage Platform", "Storage Information", "Path", and "Master Data Service" (which is highlighted). The main area of the window is titled "Edit Master Data Service" and contains a form with the following fields:

- Master Data Service (DGWin16B)
- Protocol: HTTPS
- Agent Name: DGWin16B
- Port: 8446
- DNS Name: DGWin16B

At the bottom of the window, there are four buttons: "< Back", "Next >", "Finish", and "Cancel".

3. Click **Finish**.

The **Participants** page reappears. The participant is listed in the **Participants** table with the **Master** role.

Agent	OS	Description	Directory	Enabled	Storage Platform	Seeding Target	DSU Role
DGWin168	Microsoft Windows		C:\Users\debrag	Yes	Windows Driver	No	Master

4. Continue adding more participants if applicable or continue with [Step 4: Master-Edge Assignment](#).

Volume Policy

The **Volume Policy** page appears if you chose the edge role for the participant.

A volume policy is applied when a caching scan is run. The primary purpose of a **volume policy** is to specify how much space is available to DSU on a specific volume (or drive letter), i.e, to define the **cache size**. The cache size specifies the maximum amount of disk space you want to allocate to DSU for fully hydrated files on the volume specified by the path on the **Path** page. For example, if the participant is configured to monitor D:\Data, the volume policy for this participant would apply to the D volume.

The cache size can be specified as a percentage of the volume disk space or as a fixed size. For example, if an edge participant is configured to monitor a volume that has 1 TB of disk space, and you tell DSU to use 75% of that volume, then up to 750 GB of files could be locally available on the volume monitored by that edge participant. For optimal performance, we recommend that this cache be dedicated to DSU's use on this volume.

A volume policy applies to each job where the following three elements are true:

- DSU is enabled for the job.
- The participant is an edge participant.
- The paths specified for each job share the same volume.

To create a volume policy:

1. In the **Cache Size** section, choose an option for setting the cache size:
 - Use up to X % of this volume
 - Use up to X size of this volume

Add New Participant

Volume Policy
Create a new policy.

Management Agent
Storage Platform
Storage Information
Path
Dynamic Storage Utilization
Volume Policy
Utilization Policy
Pinning Filter

Cache Size:

Use up to 75 % of this volume

Use up to 10 GB of this volume

Cache Threshold Alerts

Send alerts when:

Disk space is less than 512 MB

Cache usage exceeds 80 % of the cache size

Caching Scan Schedule:

Scan every 1 day(s) at 10:00:00 PM

Define schedule

Temporary Storage Path: C:\ Browse

C:\PeerTempPath

< Back Next > Cancel

2. In the **Cache Threshold Alerts** section, set threshold values for automatic alerts about free disk space and cache usage.

Peer Management Center will automatically display alerts in the **Alerts** tab:

- The amount of free disk space on the volume falls below the specified value. For example, if a 1 TB volume has 500 MB of free space and the threshold is set to 512 MB, an alert will be sent.
- Cache usage on the volume exceeds the specified percentage of the cache size. For example, if the cache size is set to 80%, equating to 750 GB, DSU will start sending alerts when it has used 600 GB.

You can also send cache threshold alerts via [email alerts](#) and [SNMP notifications](#). You configure these in [Dynamic Storage Utilization](#) preferences for File Collaboration and File Synchronization jobs.

3. In the **Caching Scan Schedule**, set the frequency that the volume should be scanned to optimize the balance of fully hydrated vs stubbed files.

This scan can be run daily at a specified time or you can define a more customized schedule.

4. In the **Temporary Storage Path** field, enter a path or browse to the location you want to be used as temporary storage space.


The temporary storage space will be used to store the content of stub files as they are being rehydrated. The content of files undergoing rehydration are referred to as **file blocks**. File blocks are fixed-length chunks of data that are read into memory when requested by an application. DSU will create a subfolder named **.PeerTempPath** under the location that you specify and temporarily store the file blocks in that subfolder.

For optimal performance, we recommend that the temporary storage space be on the same volume as the watch set. If that is not possible, it should be on a high performance disk.

5. Click **Next**.

The [Utilization Policy](#) page appears.

Note: If the Agent you selected is already being used as an edge participant in another job utilizing DSU, the existing volume policy will be displayed on this page. You can edit the existing volume policy; however, be aware that any modifications to the volume policy will be applied to every other job that uses this Agent as an edge participant and "touches" the same volume.



Utilization Policy

The **Utilization Policy** page appears if you chose the edge role for the participant. The primary purpose of a **utilization policy** is to specify the parameters that govern when files on this edge participant should be stubbed or fully hydrated. Whereas the volume policy controls how much space is available to DSU on a specific volume (or drive letter), the utilization policy controls whether to stub or hydrate a file.

Utilization policy parameters are based on the size of the files to be potentially stubbed and when they were last accessed and modified. A utilization policy enables you to balance getting the best performance while keeping the cache as full as possible.

You can select an existing utilization policy to apply to the job or create a new utilization policy. Whereas a volume policy is specific to a volume, a utilization policy can be reused for multiple jobs.

1. Select **New Policy** or **Existing Policy**.

- If you selected **Existing Policy**, select the policy, and then click **Next**.

If you selected **New Policy**, enter a name for the policy.

- (Optional) In the **File Size** section, select one or both options:

Field	Description
Keep files local if less than X size	Select this option if you want files under a specified size to remain local.
Stub files if greater than X size	Select this option if you want files over a specified size to be stubbed.

- (Optional) In the **Time Period** section, select one of the options:

Field	Description
Keep recently used files local based on a dynamic set of rules	Select this option if you want DSU to control when to stub files based on last accessed and last modified times. DSU dynamically adjusts the accessed and modified time periods it uses based on the total amount of space that DSU is actively using on a volume.
Keep recently used files local based on the following rules	Select this option if you want to specify the dates used when stubbing files based on the last accessed and last modified.

5. If you selected the **Keep recently used files local based on the following rules** option in **Time Period**, two additional options are enabled; select the options to be used and specify the time periods to be used:

Field	Description
Stub files if not modified within the past X time period	Select this option and specify a time range to use the last modified date of a file to determine if it should be kept local or stubbed.
Stub files is not accessed within the past X time period	Select this option and specify a time range to use the last accessed date of a file to determine if it should be kept local or stubbed.

6. (Optional) In the **Stubbing Override** section, select the checkbox and a time period if you want to use the last accessed date of all recently hydrated files to determine if they should be kept local or re-stubbed.
7. Click **Next** or **Finish**.

If you click **Next**, the [Pinning Filter](#) page appears.

Pinning Filter

The **Pinning Filter** page allows you to create a new pinning filter or select an existing pinning filter to apply to the job. A **pinning filter** specifies whether specific files or files in a particular


directory are always stubbed or always local on an edge participant. A pinning filter similar is to a utilization policy—it can be applied to multiple jobs. If there is a conflict between a pinning filter and utilization policy (where, for example, you might have something set to be always stubbed), the pinning filter will take precedence. Pinning filters are optional.

1. Select one of the options: **No Filter**, **New Filter**, or **Existing Filter**.

The screenshot shows a window titled "Add New Participant" with a "Pinning Filter" section. The section contains the instruction "Create a new pinning filter or select an existing one." Below this, there is a tree view on the left with "Pinning Filter" selected. To the right, under "Edit Pinning Filters", there are three radio button options: "No Filter" (selected), "New Filter", and "Existing Filter". Below these options is a dropdown menu. At the bottom of the window, there are four buttons: "< Back", "Next >", "Finish" (highlighted with a blue border), and "Cancel".

2. If you selected **No Filter**, click **Finish**; if you selected **Existing Filter**, select the filter, and then click **Finish**.


If you selected **New Filter**, enter a name for the filter.



t

3. Enter a name for the filter.
4. Click **Create**.

The **Create Pinning Rule** dialog appears.



5. Enter a file name or path in the **Pattern** field and then choose a pinning state: **Local at Edge** or **Stubbed at Edge**.

6. Click **OK**.

The rule appears in the filter table.

The screenshot shows the 'Add New Participant' dialog box with the 'Pinning Filter' section active. The dialog has a title bar with a close button and a maximize button. The main content area is titled 'Pinning Filter' and contains the instruction 'Create a new pinning filter or select an existing one.' On the left, a tree view shows the navigation structure: Management Agent, Storage Platform, Storage Information, Path, Dynamic Storage Utilization (expanded), Volume Policy, Utilization Policy, and Pinning Filter (selected). The main area is titled 'Edit Pinning Filters' and contains two radio buttons: 'No Filter' and 'New Filter' (selected). Below the 'New Filter' radio button is a text input field for '*Name:' containing 'Outlook files'. Underneath is a table for 'Pinning Rules' with two columns: 'Path' and 'Pinning State'. The first row contains '*.pst' and 'Local at Edge'. To the right of the table are three buttons: 'Create' (highlighted in blue), 'Edit', and 'Delete'. Below the table is an 'Existing Filter' radio button and a dropdown menu. At the bottom of the dialog are four buttons: '< Back', 'Next >', 'Finish', and 'Cancel'.

Path	Pinning State
*.pst	Local at Edge

7. (Optional) Create additional pinning rules.

8. Click **Finish**.

The **Participants** page reappears. The participant is listed in the **Participants** table with the **Edge** role.

Create File Collaboration Job Wizard

Participants
Add two or more participants to this File Collaboration job.

Participants	Agent	OS	Description	Directory	Enabled	Storage Platform	Seeding Target	DSU Role
Master-Edge Assignment	DGWin168	Microsoft Windows		C:\Users\debrag	Yes	Windows Driver	No	Master
File Metadata	DGWin16C	Microsoft Windows		C:\Users\debrag	Yes	Windows Driver	No	Master
Application Support	DGWin16D	Microsoft Windows		C:\Users\debrag	Yes	Windows Driver	No	Edge
Email Alerts								
DFS Namespace								

< Back Next > Cancel

- Continue adding more participants if applicable or continue with [Step 3: Master-Edge Assignment](#)

Step 3: Master-Edge Assignment

This step is optional.


The **Master-Edge Assignment** page appears only if you enabled Dynamic Storage Utilization for one or more participants in Step 2. The purpose of this page is to allow you to assign one or more master participants to each edge participant.

Every edge participant must have at least one master participant assigned to it, so that DSU will know which master participants to use when reading or rehydrating a stub file on an edge participant. For each edge participant, you want to assign the master participant that is the fastest and closest to it. This will increase the speed of rehydrating a stub file.


It is highly recommended that you assign, if possible, more than one master participant to an edge participant, so that if one master participant is not available, another master participant is able to provide the file content to the edge participant. You can set the order in which the master participants are consulted.

If you have only one edge participant and one master participant, the master participant is automatically assigned to the edge participant and listed in the Master Participants column. If you have multiple master participants, you need to explicitly assign master participants to each edge participant and then set the failover order.

- Select an edge participant in the **Assignment** table.



- (Optional) Change the failover order by selecting a master participant and using the **Move Up** and **Move Down** buttons.



to the selected security descriptor components (Owner, DACL, and SACL) will be synchronized to all participants as they occur.

- **Enable synchronizing NTFS security descriptors (ACLs) with master host during initial scan** - Select this option if you want the metadata synchronized during the initial scan. If enabled, changes to the selected security descriptor components (Owner, DACL, and SACL) will be synchronized during the initial scan.

2. Click **OK** in the message that appears after selecting a metadata option.
3. If you selected either of the first two options in the **Synchronize Security Descriptor Options** section, select the security descriptor components (Owner, DACL, and SACL) to be synchronized.
4. If you selected the option for metadata synchronization during the initial scan, select the host to be used as the [master host](#) in case of metadata conflict.

If a master host is not selected, then no metadata synchronization will be performed during the initial scan. If one or more security descriptors do not match across participants during the initial scan, [conflict resolution](#) will use permissions from the designated master host as the winner. If the file does not exist on the designated master host, a winner will be randomly picked from the other participants.

5. Click **Next**.

The [Application Support](#) page is displayed.

Step 5: Application Support

This step is optional.

A File Collaboration job can be automatically optimized to work with specific applications. Optimization is performed automatically for all watch sets of all participants in the job.

The **Application Support** page lists the file types for which Peer Software has known best practices, which include filtering recommendations, the prioritization of certain file types, and the enabling or disabling of file locking. However, if an application is not listed, this does not mean that the application is not supported.

For details about how an application is optimized, contact support@peersoftware.com.

1. Select the applications that have files in the job's watch set.

The screenshot shows a window titled "Create File Collaboration Job Wizard" with a sub-header "Application Support". Below the sub-header is the instruction: "Select the applications that will be used with the data that is managed by this job." On the left side, there is a vertical list of navigation options: "Participants", "Master-Edge Assignment", "File Metadata", "Application Support" (which is highlighted), "Email Alerts", and "DFS Namespace". The main area of the dialog is titled "Select below to optimize this job for any of the following file types:" and contains three sections of checkboxes:

- Adobe Products:**
 - Adobe Illustrator
 - Adobe InDesign
 - Adobe Photoshop
- Autodesk Products:**
 - Autodesk AutoCAD
 - Autodesk Revit
 - Autodesk Civil 3D
 - Autodesk Sheet Set Manager (for AutoCAD or Civil 3D)
 - Autodesk Inventor
- Other:**
 - ArcGIS
 - Microsystems Allegro
 - Dassault Systems CATIA
 - Newforma Project Center
 - Microsoft Office
 - Rhinoceros Rhino3D

At the bottom right of the dialog, there are four buttons: "< Back", "Next >" (highlighted with a blue border), "Finish", and "Cancel".

2. Click **Next**.

The [Email Alerts](#) page is displayed.

Step 6: Email Alerts

This step is optional.


An email alert notifies recipients when a certain type of event occurs, for example, session abort, host failure, system alert. The **Email Alerts** page displays a list of email alerts that have been applied to the job. When you first create a job, this list is empty. Email alerts are defined in [Preferences](#) and can then be applied to multiple jobs of the same type.

Peer Software recommends that you create email alerts in advance. However, from this wizard page, you can select existing alerts to apply to the job or create new alerts to apply.

To create a new alert, see [Email Alerts](#) in the [Preferences](#) section.


To apply an existing email alert to the job.

1. Click the **Select** button.




The **Select Email Alert** dialog appears.

2. Select an alert from the **Email Alert** drop-down list.




3. Click **OK**.

The alert is listed in the **Email Alerts** page.



The three options are enabled.



2. Select one of the three options:

- **New DFS Namespace** - Select this option if you want to create a new namespace. If you select this option, the **Create DFS-N Management Job Wizard** opens. Follow these steps to [create a new namespace](#).
- **Import DFS Namespace** - Select this option if you have a namespace that was created using the Microsoft DFS Management tool and is not currently being managed by a DFS-N Management job. If you select this option, the **Import Existing Namespaces** Wizard opens. For detailed instructions, follow these steps to [import an existing namespace](#).
- **Existing DFS Namespace** - Select this option if you want to use an existing namespace that is being managed by a DFS-N Management job. If you select this option, it will display the namespace folder and folders associated with namespace.

Create File Collaboration Job Wizard

DFS Namespace

(Optional) Link a DFS namespace folder to this File Collaboration job.

Participants
Master-Edge Assignment
File Metadata
Application Support
Email Alerts
▼ **DFS Namespace**
DFS-N Link

Enable linking job to DFS namespace

New DFS Namespace
 Import DFS Namespace
 Existing DFS Namespace

Documentation

Selected DFS Namespace: Documentation


Folders:
- User Guides

Targets:
- \\DGWIN16B\User Guides-DC
- \\DGWIN16D\User Guides-Cape Town
- \\DGWIN16C\User Guides-Munich

< Back Next > **Finish** Cancel

Click **Next** if you want to link participants with folder targets on the **DFS Link** page; otherwise continue with Step 3.

For more information about linking participants to folder targets, see [Linking an Existing Namespace Folder to an Existing File Collaboration or File Synchronization Job](#).



Editing a File Collaboration Job

You can edit a File Collaboration job while it is running; however, any changes will not take effect until the job is restarted.

Overview

When you create a File Collaboration job, the **Create Job** wizard guides you through the process, presenting the most common options for configuration. When editing a job, you have access to all options, allowing you to fine-tune the job configuration. Options not included in the initial job creation include:

- [Delta Replication](#)
- [DFS-N Link](#)
- [File and Folder Filters](#)
- [File Metadata](#) - Some options are available only when editing the job.
- [File Locking](#)


- [General](#)
- [File and Folder Filters](#)
- [Scheduled Replication Filters](#)
- [Conflict Resolution](#)
- [Delta Replication](#)
- [File Metadata](#)
- [File Locking](#)
- [Application Support](#)
- [Target Protection](#)
- [Email Alerts](#)
- [SNMP Notifications](#)
- [Tags](#)
- [DFS-N Link](#)

4. Click **OK** when finished.

Participants

The **Participants** page in the **Edit File Collaboration Configuration** dialog allows you to:

- [Add and delete participants from a job.](#)
- [Edit a participant.](#)




This topic describes [adding](#) and [deleting](#) participants in a File Collaboration job.

Adding a Participant to a File Collaboration Job

To add a participant to a file collaboration job:

1. Select the job in the **Jobs** view; right-click and select **Edit Job**.


The **Edit File Collaboration** dialog open; the **Participants** page displays the current job participants.



2. Click the **Add** button.

The **Add New Participant** wizard opens; the **Management Agent** page lists the Agents available to be added.

Tip: If the Agent you want is not listed, try restarting the Peer Agent Windows Service on that host. If it successfully connects to the Peer Management Broker, then the list is updated with that Agent.



4. Select the type of storage platform that hosts the data you want to collaborate on, and then click **Next**.

The **Storage Information** page appears; the choices available depend on your selection in the **Storage Platform** page.

5. Enter the requested information.

[Windows File Server](#)

[NetApp ONTAP | Clustered Data ONTAP](#)

[NetApp Data ONTAP 7-Mode](#)

[Amazon FSxN](#)

[Dell PowerScale | EMC Isilon](#)

[Dell EMC Unity](#)

[Dell EMC Celerra | VNX | VNX 2](#)

[Nutanix Files](#)


6. Click **Next**.

The **Path** page appears.

The screenshot shows a window titled "Add New Participant" with a "Path" sub-header. A red error message states "You must enter a valid path." The left sidebar lists navigation options: Management Agent, Storage Platform, Storage Information, Path (highlighted), and Dynamic Storage Utilization. The main content area features an "Enter Path" input field, a "Browse" button, and a "Seeding Target" checkbox. At the bottom, there are three buttons: "< Back", "Next >", and "Cancel".


7. Browse to or enter the path to the [watch set](#).
8. (Optional) Select the **Seeding Target** checkbox, and then click **OK** in the dialog that appears.
9. Click **Next**.

The **Dynamic Storage Utilization** page appears.



10. (Optional) Select the **Enable Dynamic Storage Utilization** checkbox if you want this participant to be able to use Dynamic Storage Utilization; otherwise, click **Finish**.
11. If you enabled Dynamic Storage Utilization, follow the steps outlined in [Step3: Dynamic Storage Utilization](#) in [Creating a File Collaboration Job](#).
For more information about DSU, see [Dynamic Storage Utilization](#) in [Advanced Topics](#).
12. Click **Finish** to complete the wizard.

The new participant appears in the **Participants** table.




13. Click **OK** to close the Edit wizard or select another configuration item to modify.


Deleting a Participant from a File Collaboration Job

To delete a participant from a File Collaboration job:

1. In the **Edit File Collaboration** dialog, select the participant in the **Participants** table you want to remove from the job.



2. Click the **Delete** button.




3. Click **OK** in the **Delete Confirmation** dialog.

The participant is removed from the **Participants** table.

Note: A File Collaboration job must have at least two participants, so if after deleting a participant, there is only a single participant, you must add another participant to the job.

To edit a participant:

1. In the **Edit File Collaboration** dialog, select the participant in the **Participants** table you want to edit.




2. Click **Edit**.

The **Edit Participant** dialog appears.

The screenshot shows the 'Edit Participant' dialog box with the 'General' tab selected. The 'Dynamic Storage Utilization' section is active. The 'Enabled' checkbox is checked. The 'Host' field contains 'DGWin16A'. The 'Event Detector' dropdown menu is set to 'Windows', with a link to 'Edit Detector Configuration' below it. The 'Directory' field contains 'C:\User Guides-Hong Kong' and a 'Browse' button is to its right. The 'Seeding Target' checkbox is unchecked. At the bottom, there are four buttons: '< Back', 'Next >', 'Finish' (highlighted with a blue border), and 'Cancel'.

3. To enable or disable the Agent, select or deselect the **Enabled** checkbox.
4. To change the directory/folder/share that is replicated, enter the path or browse to the new watch set in the **Directory** field.
5. If the settings required to connect to the storage device have changed, click **Edit Detector Configuration**, and then make the necessary modifications.
6. To change whether the participant is a seeding target, select or deselect the **Seeding Target** checkbox.
7. Click **Next** to change Dynamic Storage Utilization options; otherwise, click **Finish**, and continue with Step 10.

If you clicked **Next**, the Dynamic Storage Utilization page appears.



8. (Optional) Select the **Enable Dynamic Storage Utilization** checkbox if you want this participant to be able to use Dynamic Storage Utilization.
9. If you enabled Dynamic Storage Utilization, follow the steps outlined in [Step 2: Dynamic Storage Utilization](#) in [Creating a File Collaboration Job](#).
10. Click **OK** to close the **Edit Participant** wizard.

Master-Edge Assignment

This page appears only when DSU is enabled for the job.

Every edge participant must have at least one master participant assigned to it, so that DSU will know which master participants to use when reading or rehydrating a stub file on an edge participant. For each edge participant, you want to assign the master participant that is the fastest and closest to it. This will increase the speed of rehydrating a stub file.

It is highly recommended that you assign, if possible, more than one master participant to an edge participant, so that if one master participant is not available, another master participant is

General

The **General** page in the **Edit File Collaboration Job** dialog presents miscellaneous settings pertaining to a File Collaboration job. You may want to consult with Peer Software's Technical Support team before modifying these values.

To modify these settings:

1. Enter the values recommended by Peer Software Support.

Option	Value
Job ID	173
Job Type	File Collaboration
Job Name	FC-1
Transfer Block Size (KB)	2048
Verify Block Checksums	<input checked="" type="checkbox"/>
Verify Full File Checksums	<input checked="" type="checkbox"/>
Enable Multipart Transfers	<input type="checkbox"/>
Synchronization Priority	2
Timeout (Seconds)	180
First Scan Mode	FOLDER_BY_FOLDER
Remove Filtered Files On Folder Delete	<input checked="" type="checkbox"/>
Require All Hosts At Start	<input type="checkbox"/>
Auto Start	<input checked="" type="checkbox"/>

Option	Description
Job ID	Unique, system-generated job identifier that cannot be edited.
Job Type	Identifies the job type. This cannot be modified.
Job Name	Name of this File Collaboration job. This name must be unique.
Transfer Block Size (KB)	The block size in Kilobytes used to transfer files to hosts. Larger sizes will yield faster transfers on fast networks but will consume more memory in the Peer Management Broker and Peer Agents .

Option	Description
Verify Block Checksums	If selected, each block sent will be checksummed at both the source and target(s) Agents.
Verify Full File Checksums	If selected, the entire file will be checksummed <i>after</i> it has been sent from the source to all target Agents. If temp files are enabled, the checksum on the target will be calculated prior to renaming the temp file to the base file's name. If the checksums between source and target(s) do not match, the file will be sent to the retry engine to reattempt the transfer.
Enable Multipart Transfers	If selected, larger files will be broken into smaller chunks and these chunks will be sent over the wire in a parallel fashion. This feature will automatically throttle itself if many other transfers are also waiting to be processed.
Synchronization Priority	Use this to increase or decrease a job's file synchronization priority relative to other configured job priorities. Jobs are serviced in a round-robin fashion, and this number determines the maximum number of synchronization tasks that will be executed sequentially before yielding to another job.
Timeout (Seconds)	Number of seconds to wait for a response from any host before performing retry logic.
First Scan Mode	Determines which scan type will be used when the job is first started. For environments where most data is NOT seeded, the FOLDER_BY_FOLDER method will be best. For environments where most data is seeded, the BULK_CHECKSUM method will result in a faster first scan.
Remove Filtered Files On Folder Delete	If selected, then all child files on target hosts will be deleted when its parent folder is deleted on another source host. Otherwise, filtered files will be left intact on targets when a parent folder is deleted on another source host.
Require All Hosts At Start	If selected, requires all participating hosts to be online and available at the start of the File Collaboration job in order for the job to successfully start.

Option	Description
Auto Start	If selected, then this file collaboration session will automatically be started when the Peer Management Center Service is started.


2. Click **OK** to close the Edit wizard or select another configuration item to modify.

File and Folder Filters

The **File and Folder Filters** page in the **Edit File Collaboration Job** dialog displays a list of [file and folder filters](#). A file or folder filter enables you to exclude and/or include files and folders from the job based on file type, extension, name, or directory path. Any file or folder that matches the filter is excluded or included from replication, depending on the filter's definition. By default, all files and folders selected in the **Source Paths** page will be replicated.

1. Select the file and folder filters you want to apply to the job.

If you want to create a new file or folder filter or modify an existing one, click **Edit File Filters**. See [File and Folder Filters](#) in the [Preferences](#) section for information about creating or modifying a file filter.




2. Click **OK** to close the Edit wizard or select another configuration item to modify.

Scheduled Replication Filters

The **Scheduled Replication Filters** page in the **Edit File Collaboration Job** dialog displays a list of [scheduled replication filters](#). A scheduled replication filter enables you to identify files and folders that you don't want replicated in real-time.

1. Select the scheduled replication filters you want to apply to the job.

If you want to create a new filter or modify an existing one, click **Edit Scheduled Replication Filters**. See [Scheduled Replication Filters](#) in the [Preferences](#) section for information about creating or modifying a scheduled replication filter.



2. Click **OK** to close the Edit wizard or select another configuration item to modify.

Conflict Resolution

By default, any file conflicts that are encountered during the [initial synchronization process](#) are automatically resolved by Peer Management Center. Peer Management Center resolves the conflict by selecting the file with the most recent modification time. Conflicts that cannot automatically be resolved result in the files being quarantined. The **Conflict Resolution** page in the **Edit File Collaboration Job** allows you to select options for resolving file conflicts and quarantines.


However, if you want to resolve the conflicts yourself, you can contact Peer Software to enable manual resolution. With manual resolution, you can select the host with the correct version of the file.

For more information about the cause of file conflicts, see [Conflicts, Retries, and Quarantines](#).

To modify conflict resolution settings for the File Collaboration job:

1. In the **File Conflict Resolution** section, select the **Truncate Milliseconds** option if you want the millisecond value truncated from each time stamp when comparing the time stamps of a file on two or more hosts.

As some storage platforms and applications track milliseconds slightly differently, selecting this option will prevent subtle millisecond differences from causing an otherwise in-sync file to be replicated or quarantined.



2. Select the **Advanced File Conflict Resolution** options you want applied:

Option	Description
Quarantine Offline Version Conflicts	Select this option if you want Peer Management Center to quarantine a file that was updated in two or more locations while the collaboration session was not running. If it is not selected, the file with the most recent last modified time will be replicated to all other participants.
Enable Deletion of Quarantined Files	Select this option if you want Peer Management Center to process a delete event for a quarantined file. If it is not selected, the quarantined file is not deleted and remains quarantined.
Offline Delete Detection During Scan	Select this option (and enable target protection), if you want any files or folders that were deleted while the job was stopped to be deleted from all participants when the job is restarted. If it is not selected, then the deleted file or folder is restored from a participant with the file or folder to any participant where it no longer exists.

3. Click **OK** to close the Edit wizard or select another configuration item to modify.

Delta Replication

The **Delta Replication** page in the **Edit File Collaboration Job** dialog allows you to specify the delta-replication options to use for the selected File Collaboration job. Delta-level replication is a byte replication technology that enables block/byte level synchronization for a File Collaboration job. Through this feature, Peer Management Center is able to transmit only the bytes/blocks of a file that have changed instead of transferring the entire file. This results in much lower network bandwidth utilization, which can be an enormous benefit if you are transferring files across a slow WAN or VPN, as well as across a high-volume LAN.

Delta-level replication is enabled on a per File Collaboration job basis and generally affects all files in the [watch set](#). You will only benefit from delta-level replication for files that do not change much between file modifications, which includes most document editing programs.

To modify delta-level replication options:

1. Modify the following the fields as necessary.

Edit File Collaboration Job

Participants
Master-Edge Assignment
General
File and Folder Filters
Scheduled Replication Filters
Conflict Resolution
Delta Replication
File Metadata
File Locking
Application Support
Target Protection
Email Alerts
SNMP Notifications
Tags
DFS-N Link

Delta Replication

Enable Delta-level Replication:

Checksum Transfer Size (KB): 256

Delta Block Transfer Size (KB): 1024

Minimum File Size (KB): 2048

Minimum File Size Percentage Target/Source: 0.30

Excluded File Extensions

- zip
- jpg
- jpeg
- png
- gif
- tiff
- tif
- Z
- tgz
- gz
- gzip
- rar
- 7z
- bz
- bz2
- bzip2
- mp3

Excluded File Name Patterns

OK Cancel

Field	Description
Enable Delta-Level Replication	Select to enable delta encoded file transfers which only sends the file blocks that are different between source and target(s). If this is disabled, the standard file copy method will be used to synchronize files.
Checksum Transfer Size (KB)	Enter the block in kilobytes used to transfer checksums from target to source at one time. Larger sizes will result in faster checksum transfer, but will consume more memory on the Peer Agents
Delta Block Transfer Size (KB)	Enter the block size in kilobytes used to transfer delta encoded data from source to target at one time. Larger sizes will result in faster overall file transfers but will consume more memory on the Peer Agents.
Minimum File Size (KB)	Enter the minimum size of files in kilobytes to perform delta encoding for. If a file is less than this size, then delta encoding will not be performed.

Field	Description
Minimum File Size Percentage Target/Source	Enter the minimum allowed file size difference between source and target, as a percentage, to perform delta encoding. If the target file size is less than this percentage of the source file size, then delta encoding will not be performed.
Excluded File Extensions	Enter a comma-separated list of file extension patterns to be excluded from delta encoding, e.g., zip, jpg, png. In general, compressed files should be excluded from delta encoding and the most popular compressed file formats are excluded by default.
Excluded File Name Patterns	Enter a list of file name patterns to be excluded from delta encoding. If a file name matches any pattern in this list, then it will be excluded from delta encoding transfers and a regular file transfer will be performed. See File and Folder Filters for more information on specifying wildcard expressions.


2. Click **OK** to close the Edit wizard or select another configuration item to modify.

File Metadata

The **File Metadata** page in the **Edit File Collaboration Job** dialog allows you to modify your file metadata synchronization settings and provides some additional options not available when creating the job. See [File Metadata Synchronization](#) in [Advanced Topics](#) for more information about file metadata replication.

To enable file metadata synchronization:

1. Select when you want the metadata synchronized (you can select one or both options):
 - **Enable synchronizing NTFS security descriptors (ACLs) in real-time** - Select this option if you want the metadata replicated in real-time. If enabled, changes to the selected security descriptor components (Owner, DACL, and SACL) will be transferred to the target host file(s) as they occur.
 - **Enable synchronizing NTFS security descriptors (ACLs) with master host during initial scan** - Select this option if you want the metadata replicated during the initial scan. If enabled, changes to the selected security descriptor components (Owner, DACL, and SACL) will be synchronized during the initial scan.



2. Click **OK** in the message that appears after selecting a metadata option.
3. If you selected either of the first two options in the **Synchronize Security Descriptor (ACLs)** section, select the security descriptor components (**Owner**, **DACL**, and **SACL**) to be synchronized.
4. If you selected the option for metadata synchronization during the initial scan (second option in the **Synchronize Security Descriptor (ACLs)** section, select the host to be used as the [master host](#) in case of file metadata conflict.

If a master host is not selected, then no metadata synchronization will be performed during the initial scan. If one or more security descriptors do not match across participants during the initial scan, [conflict resolution](#) will use permissions from the designated master host as the winner. If the file does not exist on the designated master host, a winner will be randomly picked from the other participants.

5. (Optional) Select the **Enable enhanced metadata conflict resolution** checkbox.

This option is only available when both of the first two options in the **Synchronize Security Descriptor (ACLs)** section are enabled, and **Owner** is selected under **Synchronize Security Descriptor Options**.

If you select **Enable enhanced metadata conflict resolution**, this will prevent the Peer Agent service account from being assigned as the owner of that file or folder when a metadata conflict occurs, and a file or folder is written to a target. If the Peer Agent service account were to be assigned as the owner, the user may not have permission to access the file or folder.

Note: The Peer Agent service account cannot be a local or system administrator. As described in [Peer Global File Service - Environmental Requirements](#), the Peer agent service account should be an actual user.

6. (Optional) Enter values for one or both file reparse point data synchronization options:

- **Reparse Tag Name** - Enter a single numerical value. Must be either blank (if blank, reparse synchronization will be disabled) or greater than or equal to 0. The default for Symantec Enterprise Vault is 16. A value of 0 enables reparse point synchronization for all reparse file types. If you are unsure as to what value to use, then contact Peer Software technical support, or you can use a value of 0 if you are sure that you are only utilizing one vendor's reparse point functionality.
- **Reparse Master Host** - Select a master host. If a master host is selected, then when the last modified times and file sizes match on all hosts, but the file reparse attribute differs (e.g., archived/offline versus unarchived on file server), then the file reparse data will be synchronized to match the file located on the master host. For Enterprise Vault, this should be the server where you run the archiving task on. If the value is left blank, then no reparse data synchronization will be performed, and the files will be left in their current state.

Note: Use this option only if you are utilizing archiving or hierarchical storage solutions that make use of NTFS file reparse points to access data in a remote location, such as Symantec's Enterprise Vault. Enabling this option allows synchronization of a file's reparse data, and not the actual offline content, to target hosts, and prevents the offline file from being recalled from the remote storage device.

7. (Optional) Select the **Enable transfer of file Alternate Data Stream (ADS)** checkbox.

If enabled, Alternate Data Streams (ADS) of updated files will be transferred to the corresponding files on target participants as a post process of the normal file synchronization.

Known limitation: ADS information is transferred only when a modification on the actual file itself is detected. ADS will not be compared between participants. The updated file's ADS will be applied to the corresponding files on target participants.


8. Click **OK** to close the Edit wizard or select another configuration item to modify.

File Locking

The **File Locking** page in the **Edit File Collaboration Job** dialog presents options pertaining to how source and target files are locked by Peer Management Center.

To modify file locking options:

1. Modify these fields as needed:



2. Click **OK** to close the Edit wizard or select another configuration item to modify.

Locking Options

Option	Description
Exclusive Target Lock	If enabled, then whenever possible, an exclusive lock will be obtained on target file handles, which will prevent users from opening the file (even in read-only mode) while a user has the file opened on the source host. When this option is disabled, then users will be allowed to open files for read-only if the application allows for this.
Include MS Office User Lock Information	If enabled, user lock information (if available) will be propagated to target locks for supported Microsoft Office files (e.g., Word, Excel, and PowerPoint).
Include AutoCAD User Lock Information	If enabled, user lock information (if available) will be propagated to target locks for supported AutoCAD files.

Source Snapshot Synchronization Option

Option	Description
Enable Source Snapshot Copy Sync.	If enabled, a snapshot copy of the source file will be created for files that meet the snapshot configuration criteria below, and this copy will be used for synchronization purposes. In addition, no file handle will be held on the source file except while making a copy of the file.
Snapshot Copy Max File Size (MB)	The maximum file size for which source snapshot synchronization will be utilized.
Snapshot Copy File Extensions	A comma-separated list of file extensions for which source snapshot synchronization will be utilized.

Sync On Save Options


Option	Description
Exclusive Target Lock	If enabled, then whenever possible, an exclusive lock will be obtained on target file handles, which will prevent users from opening the file (even in read-only mode) while a user has the file opened on the source host. When this option is disabled, then users will be allowed to open files for read-only if the application allows for this.
Include MS Office User Lock Information	If enabled, user lock information (if available) will be propagated to target locks for supported Microsoft Office files (e.g., Word, Excel, and PowerPoint).
Include AutoCad User Lock Information	If enabled, user lock information (if available) will be propagated to target locks for supported AutoCAD files.
Enable Source Snapshot Copy Sync.	If enabled, a snapshot copy of the source file will be created for files that meet the snapshot configuration criteria below, and this copy will be used for synchronization purposes. In addition, no file handle will be held on the source file except while making a copy of the file.
Snapshot Copy Max File Size (MB)	The maximum file size for which source snapshot synchronization will be utilized.
Snapshot Copy File Extensions	A comma-separated list of file extensions for which source snapshot synchronization will be utilized.
Enable Sync. On Save	If enabled, this feature will allow supported file types to be synchronized after a user saves a file, rather than waiting for the file to close.
Included File Extensions	A comma-separated list of file extensions for which to enable the Sync. On Save feature.
Synchronization Delay (Seconds)	The number of seconds to wait after a file has been saved before initiating a synchronization of the file.

Application Support

When you create a File Collaboration job, you have the option of [selecting applications to be automatically optimized](#). When editing the job, you can modify your selections in the **Application Support** page in the **Edit File Collaboration Job** dialog.

To modify which applications are optimized:

1. Select the applications to be optimized.



2. Click **OK** to close the Edit wizard or select another configuration item to modify.

Target Protection

Target protection is used to protect files on [target hosts](#) by saving a backup copy before a file is either deleted or overwritten on the target host. If a job has target protection enabled, then whenever a file is deleted or modified on the source host but before the changes are propagated to the targets, a copy of the existing file on the target is moved to the Peer Management Center trash bin.

The trash bin is located in a hidden folder named **.pc-trash_bin** found in the root directory of the [watch set](#) of the target host. A backup file is placed in the same directory hierarchy location

as the source folder in the watch set within the recycle bin folder. If you need to restore a previous version of a file, you can copy the file from the trash bin into the corresponding location in the watch set and the changes will be propagated to all other collaboration hosts.

You can configure target protection in the **Target Protection** page in the **Edit File Collaboration Job** dialog.

The screenshot shows the 'Edit File Collaboration Job' dialog box with the 'Target Protection' tab selected. The sidebar on the left lists various configuration options, with 'Target Protection' highlighted. The main area of the dialog contains the following settings:

- Enabled:**
- # of Backup Files to Keep:** 3
- # of Days to Keep:** 30
- Trash Bin:** .pc-trash_bin


At the bottom right of the dialog, there are 'OK' and 'Cancel' buttons.

Modify the fields as needed:


Field	Description
Enabled	Enables target protection.
# of Backup Files to Keep	The maximum number of backup copies of an individual file to keep in the trash bin before purging the oldest copy.

The **Select Email Alert** dialog opens.

2. Select the email alert from the drop-down list, and then click **OK**.



The newly added email alert appears in the **Email Alerts** table.



3. Repeat to add additional alerts to the job.
4. Click **OK** to close the Edit wizard or select another configuration item to modify.

SNMP Notifications


The **SNMP Notifications** page in the **Edit File Collaboration Job** dialog allows you to apply SNMP notifications to a File Collaboration job.

SNMP notifications, like email alerts and file filters, are configured at a global level in the [Preferences](#) dialog, then applied to individual jobs. For more information about SNMP Notifications, see [SNMP Notifications](#) in the **Preferences** section.

To enable or disable SNMP notifications for a File Collaboration job:

1. To enable, select an SNMP notification from the drop-down list.


To disable, select **None - Disabled**.



2. Click **OK** to close the Edit wizard or select another configuration item to modify.


Tags

The **Tags** page in the **Edit File Collaboration Job** dialog allows you to assign existing tags and categories to the selected job. This page is not available in [Multi-Job Editing](#) mode. For more information about tags, see [Tags](#) in the [Basic Concepts](#) section.



DFS-N Link

The **DFS-N** page in the **Edit File Collaboration Job** dialog presents options for linking a DFS namespace folder to this job. See [Linking a Namespace Folder to an Existing File Collaboration or Synchronization Job](#) for more information.



Editing Multiple Jobs


Peer Management Center supports multi-job editing, allowing you to quickly and effectively manipulate multiple File Collaboration jobs simultaneously. For example, you can use this feature to change a single configuration item such as **Auto Start** for any number of already configured jobs in one operation instead of having to change the item individually for each.

While this feature does cover most of the options available on a per-job basis, certain options are unavailable in multi-job edit mode, specifically ones tied to [participants](#). Configuration of participants must be performed on a per job basis.


To edit multiple jobs simultaneously:

1. Open Peer Management Center.
2. Select the jobs you want to edit in the **Jobs** view.
3. Right-click and select **Edit Jobs**.

For the most part, the original configuration dialog remains the same with a few minor differences depending on similarities between the selected File Collaboration jobs. A sample dialog is as follows:



In this dialog, any discrepancies between multiple selected jobs will generally be illustrated by a read-only text field with the caption **Multiple Values - Click to Edit**. Clicking this field will bring up a dialog similar to the following:



This dialog gives you the option of choosing a value that is already used by one or more selected File Collaboration jobs, in addition to the ability to use your own value. Notice that variances in the look and feel of this pop-up dialog above depend on the type of information it is trying to represent (for example, text vs. a checkbox vs. a list of items).

Upon clicking **OK**, the read-only text field you originally clicked will be updated to reflect the new value. Any fields that have changed will be marked by a small caution sign. On saving in this multi-job edit dialog, the changed values will be applied to all selected jobs.

Note: Read all information on each configuration page carefully when using the multi-job edit dialog. A few pages operate in a slightly different manner than mentioned above. All the necessary information is provided at the top of these pages in bold text.

Running and Managing a File Collaboration Job

The topics in this section provide some basic information about starting, stopping, and managing File Collaboration jobs:

- [Overview](#)
- [Starting a File Collaboration Job](#)
- [Stopping a File Collaboration Job](#)
- [Auto-Restarting a File Collaboration Job](#)
- [Host Connectivity Issues](#)
- [Removing a File from Quarantine](#)
- [Manual Retries](#)

Overview

This topic describes:

- The [initialization process](#) for a File Collaboration job: What occurs the first time you run a File Collaboration job.
- The [initial synchronization process](#): How files are synchronized the first time you run a File Collaboration job.

The initialization process for a File Collaboration job consists of the following steps:

1. All participating hosts are contacted to make sure they are online and properly configured.
2. [Real-time event detection](#) is initialized on all participating hosts where file locks and changes will be propagated in real-time to all participating hosts. You can view real-time activity and history via the various [Runtime Job views](#) for the open job.
3. The [initial synchronization process](#) is started; all the configured root folders on the participating hosts are scanned in the background, and a listing of all folders and files are sent back to the running job.
4. The background directory scan results are analyzed, and directory structures compared to see which files are missing from which hosts. In addition, file conflict resolution is performed to decide which copy to use as the master for any detected file conflicts based on the [File Conflict Resolution](#) settings.
5. After the analysis is performed, all files that need to be synchronized are copied to the pertinent host(s).

Before you start a File Collaboration job for the first time, you need to decide how you would like the [initial synchronization](#) to be performed.

During the initial synchronization process:

- The watch set is recursively scanned on all participating hosts.
- File conflict resolution is performed.
- Any files that require updating are synchronized with the most current copy of the file.

The two primary options are:

- Have the File Collaboration job perform the initial synchronization based on the [Conflict Resolution](#) settings.
- [Pre-seed](#) all [participating hosts](#) with the correct folder and file hierarchy for the configured root folders before starting the session.

If you have a large data set, we strongly recommend that you perform the initial synchronization manually by copying the data from a host with the most current copy to all other participating hosts. This needs to be done only once--before the first time that you run the File Collaboration job.

If you choose the first option, click the **Start** button to begin [collaboration session initialization](#). Otherwise, pre-seed each participating host with the necessary data, then click the **Start** button.

Starting a File Collaboration Job


Before starting a File Collaboration job for the first time, make sure that you have decided how you want the [initial synchronization](#) to be performed.

When running a File Collaboration job for the first time, you must manually start it. After the initial run, a job will automatically start, even when the Peer Management Center server is rebooted.

Note: You cannot run two jobs concurrently on the same volume if the [watch sets](#) contain an overlapping set of files and folders.


To manually start a job:

1. Choose one of three options:
 - Right-click the job name in the **Jobs** view.
 - Right-click the job name in the **Summary** tab of the **Collab, Sync, and Repl Summary** summary view, and then choose **Start** from the context menu.
 - Open a job and then click the **Start/Stop** button to the left of the **Status** field in the bottom left corner of the job's runtime view (shown below).



2. Click **Yes** in the confirmation dialog.

After the job initialization has completed, the job will run. Once the job starts, the icon next to the job name in the **Jobs** view changes from gray to green.



Stopping a File Collaboration Job

You can stop a File Collaboration job at any time by selecting the job in the **Jobs** view and clicking the **Stop** button. Doing this shuts down the real-time file event detection and close all running operations (e.g., file transfers).

Auto-Restarting a File Collaboration Job

Peer Management Center includes support for automatically restarting File Collaboration jobs that include [participating hosts](#) that have been disconnected, have reconnected, and are once again available.


After a host becomes unavailable and the [quorum](#) is lost on a running File Collaboration job, the job automatically stops running and enters a pending state, waiting for one or more hosts to become available again so that the quorum can be met. Once the quorum is met, the pending job will automatically be restarted, beginning with a scan of all root folders.

In a job where a host becomes unavailable but quorum is not lost, the remaining hosts will continue collaborating. If the unavailable host becomes available once again, it is brought back into the running job and a background scan begins on all participating hosts, similar in fashion to the initial background scan at the start of a job.

You can enable all File Collaboration jobs to auto-restart. You can also disable auto-restart File Collaboration jobs on a per-job and per-host instance. For more information on disabling auto-restart at the job level, see [Participants Tab](#).

To enable all File Collaboration jobs to auto-restart:

1. Select **Preferences** from the **Window** menu.
2. Select **Collab, Sync, and Repl Summary** in the navigation tree.



3. Select the **Auto Reconnect when Host Becomes Available** checkbox.
4. Enter the minimum number of minutes to wait after an Agent reconnects before re-enabling it in any associated jobs in the **Minimum Host Reconnect Time** field.
5. Click **OK**.

Host Connectivity Issues

Peer Management Center is designed to be run in an environment where all [participating hosts](#) are highly available and on highly available networks. The two primary connectivity issues result from:

- [Unavailable Hosts](#)
- [Quorum Not Met](#)


Unavailable Hosts

If a host becomes unavailable while a File Collaboration job is running and is unreachable within the configured timeout period (specified in the job's [General settings](#)), it may be removed from collaboration. If no response is received while performing a file collaboration operation within the timeout period, Peer Management Center pings the host; if still no response, the host is taken out of the running session, a FATAL event is logged, and the [Participants tab](#) for the job is updated to indicate that the host has failed. In addition, if [email alerts](#) and/or [SNMP notifications](#) are configured and enabled for **Host Timeouts**, then the appropriate message(s) are sent.

If [auto-restart](#) not enabled, you must stop and start the File Collaboration job to bring any failed hosts back into the session. As a result, all root folders on all hosts will need to be scanned again to detect any inconsistencies. Therefore, if you are operating over a WAN with low bandwidth, you will want to set the timeout to a higher value on each related job.

Quorum Not Met

For a File Collaboration job to run correctly, a quorum of available hosts must be met. When a quorum is lost, a message appears after the job name in the **Jobs** view.



Quorum is currently set to at least two hosts, and if quorum is not met, then the collaboration session is automatically terminated. If [email alerts](#) and/or [SNMP notifications](#) are configured and enabled for **Session Aborts**, then the appropriate message(s) are sent.

Removing a File from Quarantine

Quarantines are a key feature of Peer Global File Service, used for resolving version conflicts. For more detailed information on how quarantines work, see [Conflicts, Retries, and Quarantines](#) in the [Advanced Topics](#) section.

You must explicitly remove a file from quarantine in order to have it participate in the collaboration session once again.

You may also choose to perform no action, in which case, the file is removed from the **Quarantines** table but none of the file versions are modified. Therefore, if the files are not currently in-sync, then the next time the file is modified, changes will be propagated to the other hosts. If an error occurs while removing the quarantine, then the **Status** field in the **Quarantines** table is updated to reflect the error.

To remove a file (or multiple files) from quarantine:

1. Open the job.
2. The runtime view for the job appears.
3. Click the [Quarantines tab](#).
4. Select the file(s) in the **Quarantines** table.
5. Select the host with the correct version.
6. Click the **Release Conflict** button.

After doing this, all hosts are checked to make sure the file is not currently locked by anyone. If no locks are found, then locks are obtained on all versions of the file and the targets that are out-of-date are synchronized with the selected source host.

Manual Retries

Retries are a key feature of Peer Global File Service, used for automatically handling errors in the collaboration environment that would have otherwise led to a quarantine. For more detailed information on how retries work, see [Conflicts, Retries, and Quarantines](#) in the [Advanced Topics](#) section.

When a file is put in the retry list, it will be automatically retried based on the settings defined in [File Retries](#) in [Preferences](#). If need be, you can also manually force the retry of a file. This can be done from the Retries list of a specific File Collaboration job.

You may also choose to perform no action, in which case, the file is removed from the Retries list but none of the file versions are modified. Therefore, if the files are not currently in-sync, then the next time the file is modified, changes will be propagated to the other hosts. If an error occurs while forcing the retry, then the **Status** field in the **Retries** table is updated to reflect the error.

To manually force the retry of a file (or multiple files):

1. Select the file(s) in the **Retries** list.
2. Select the host with the correct version.
3. Click the **Release Conflict** button.

After doing this, all hosts are checked to make sure the file is not currently locked by anyone. If no locks are found, then locks are obtained on all versions of the file and the targets that are out-of-date are synchronized with the selected source host.

File Replication Jobs

This section provides information about creating a File Replication job.

- [Overview](#)
- [Before You Create Your First File Replication Job](#)

- [Creating a File Replication Job](#)

Overview

A File Replication job is designed to push files one way from a single file server (known as the source) to another single file server (known as the destination or target). This job type requires two Agents, although only the Agent at the source location will register with its local storage platform for real-time activity. The destination Agent will simply act as a relay to the destination file server.

Before You Create Your First File Replication Job

We strongly recommend that you configure global settings such as SMTP configuration and email alerts before configuring your first File Replication job. See [Preferences](#) for details on what and how to configure these settings.

Creating a File Replication Job

The **Create Job Wizard** walks you through the process of creating a File Replication job:

[Step 1: Job Type and Name](#)

[Step 2: Source Platform](#)

[Step 3: Source Agent](#)

[Step 4: Storage Information](#)

[Step 5: Source Path](#)

[Step 6: Destination Agent](#)

[Step 7: Destination Path](#)

[Step 8: File Metadata](#)


[Step 9: Email Alerts](#)

[Step 10: Save Job](#)

Step 1: Job Type and Name


1. Open Peer Management Center.
2. From the **File** menu, select **New Job** (or click the **New Job** button on the toolbar).

The **Create New Job** wizard displays a list of job types you can create.



3. Click **File Replication**, and then click **Create**.
4. Enter a name for the job in the dialog that appears.

The job name must be unique.



Create File Replication Job

Enter a unique name.

Job name cannot be blank.

OK Cancel


5. Click **OK**.

The [Storage Platform](#) page is displayed.

Step 2: Source Agent

The **Source Agent** page lists available Agents. You can have more than one Agent managing a storage device—however, the Agents must be managing different volumes/shares/folders. You should select the Agent that manages the volumes/shares/folders you want to replicate in this job.

1. Select the Source Agent for the volume/share/folder you want replicated.




2. Click **Next**.

The [Storage Platform](#) page is displayed.

Step 3: Storage Platform

The **Storage Platform** page lists the types of source storage platforms that File Replication supports. The source storage device hosts the data you want to replicate.

1. Select the type of storage platform you want to replicate.



2. Click **Next**.

The [Source Agent](#) page is displayed.

Step 4: Storage Information

On the **Storage Information** page, you will select the storage device containing data that you want to replicate and enter other information about the storage device. The contents of the **Storage Information** page varies, depending on your selection in the [Storage Platform](#) page:

- If you selected **Windows File Server**, you are prompted for configuration relating to Windows File Server. See [Windows File Server](#).
- If you selected any other type of storage device other than Windows File Server, the **Storage Information** page requests the credentials necessary to connect to that storage device. Continue with the steps below.

For storage platforms other than Windows File Server:

1. Select **New Credentials** or **Existing Credentials**.
2. If you selected **Existing Credentials**, select a credential from the drop-down list, and then click **Next**. Continue with [Step 5. Source Path](#).

If you selected **New Credentials**, enter the credentials for connecting to the storage platform. The information you are prompted to enter varies, depending on the type of storage platform:

[Amazon FSxN](#)

[Dell EMC Celerra | VNX | VNX 2](#)

[Dell EMC Unity](#)

[Dell PowerScale | EMC Isilon](#)

[NetApp Data ONTAP 7-Mode](#)

[NetApp ONTAP | Clustered Data ONTAP](#)

[Nutanix Files](#)

3. Click **Validate** to test the credentials.

After the credentials are validated, a success message appears.

4. Click **Next**.

The [Source Path](#) page is displayed.

1. Select **New Credentials** or **Existing Credentials** to enter the credentials to connect to the Storage Virtual Machine hosting the data to be replicated.

The screenshot shows a window titled "Create File Replication Job Wizard" with a "Storage Information" tab selected in the left-hand navigation pane. The main area contains a form for entering storage device connection details. The "Credentials" section is active, with the "New Credentials" radio button selected. Below this, there are five input fields: "*SVM Name:", "*SVM User Name:", "*SVM Password:", "SVM Management IP:", and "*Peer Agent IP:". An "Advanced" button is located to the right of the "*Peer Agent IP" field. Below the "New Credentials" section, the "Existing Credentials" radio button is unselected, followed by a drop-down menu. A "Validate" button is positioned below the "Existing Credentials" section. At the bottom of the window, there are four buttons: "< Back", "Next >", "Finish", and "Cancel". A note at the bottom of the form reads: "Having trouble connecting? Please verify that all [prerequisites](#) are met for Amazon FsxN environments."

2. If you selected **Existing Credentials**, select a credential from the drop-down list, and then click **Next** to continue to the [Source Path](#) page.

If you selected **New Credentials**, supply the required information:

Field	Description
SVM Name	Enter the name, FQDN, or IP address of the Storage Virtual Machine hosting the data to be replicated.
SVM User Name	Enter the user name for the account managing the Storage Virtual Machine. This must not be a cluster management account.
SVM Password	Enter the password for the account managing the Storage Virtual Machine. This must not be a cluster management account.
SVM Management IP	(Optional) Enter the IP address used to access the management API of the Storage Virtual Machine. If the data LIFs (Logical Interfaces) corresponding to the SVM Name above already allow management access, this field is not required.
Peer Agent IP	Select the IP address of the server hosting the Agent that manages the Storage Virtual Machine. The Storage Virtual Machine must be able to route traffic to this IP address. If the IP address you want does not appear, manually enter the address.


3. Click **Advanced** if you want to set [advanced options](#).
4. Click **Validate** to test the credentials.

After the credentials are validated, a success message appears.

5. Click **Next**.

The [Source Path](#) page is displayed.

1. Select **New Credentials** or **Existing Credentials** to enter the credentials to connect to the CIFS Server hosting the data to be replicated.



Create File Replication Job Wizard

Storage Information

Enter the information required to connect to the storage device.

Source Agent
Storage Platform
Storage Information
Source Path
Destination Agent
Destination Path
File Metadata
Email Alerts

Credentials

New Credentials

*CIFS Server Name:

*Control Station Username:

*Control Station Password:

*Control Station IP:

Advanced

Existing Credentials

Validate

Having trouble connecting? Please verify that all [prerequisites](#) are met for Dell EMC VNX/Celerra environments.

< Back Next > Finish Cancel

- If you selected **Existing Credentials**, select a credential from the drop-down list, and then click **Next** to continue to the [Source Path](#) page.

If you selected **New Credentials**, supply the required information.

Field	Description
CIFS Server Name	Enter the name of the CIFS Server hosting the data to be replicated.
Control Station Username	Enter the user name for the Control Station account managing the Celerra/VNX storage device.
Control Station Password	Enter the password for the Control Station account managing the Celerra/VNX storage device.
Control Station IP	Enter the IP address of the Control Station system used to manage the Celerra/VNX storage device. This should not point to the CIFS Server.

3. Click **Advanced** if you want to set [advanced options](#).
4. Click **Validate** to test the credentials.

After the credentials are validated, a success message appears.

5. Click **Next**.

The [Source Path](#) page is displayed.

1. Select **New Credentials** or **Existing Credentials** to enter the credentials to connect to the CIFS Server hosting the data to be replicated.

The screenshot shows a window titled "Create File Replication Job Wizard" with a "Storage Information" tab selected. The window contains a sidebar with navigation options: Source Agent, Storage Platform, Storage Information (selected), Source Path, Destination Agent, Destination Path, File Metadata, and Email Alerts. The main area is titled "Storage Information" and contains the instruction "Enter the information required to connect to the storage device." Under the "Credentials" section, there are two radio buttons: "New Credentials" (selected) and "Existing Credentials". The "New Credentials" section has four text input fields: "*CIFS Server Name:", "*Unisphere Username:", "*Unisphere Password:", and "*Unisphere Management IP:". An "Advanced" button is located to the right of these fields. Below the "Existing Credentials" radio button is a drop-down list. At the bottom of the main area is a "Validate" button. A note at the bottom of the main area reads: "Having trouble connecting? Please verify that all [prerequisites](#) are met for Dell EMC Unity environments." At the bottom of the window are four buttons: "< Back", "Next >", "Finish", and "Cancel".

2. If you selected **Existing Credentials**, select a credential from the drop-down list, and then click **Next** to continue to the [Source Path](#) page.

If you selected **New Credentials**, supply the required information.

Field	Description
CIFS Server Name	Enter the name of the NAS server hosting the data to be replicated.
Unisphere Username	Enter the user name for the Unisphere account managing the Unity storage device.
Unisphere Password	Enter the password for the Unisphere account managing the Unity storage device.
Unisphere Management IP	Enter the IP address of the Unisphere system used to manage the Unity storage device. This should not point to the NAS server.

3. Click **Advanced** if you want to set [advanced options](#).

4. Click **Validate** to test the credentials.

After the credentials are validated, a success message appears.

5. Click **Next**.

The [Source Path](#) page is displayed.

1. Select **New Credentials** or **Existing Credentials** to enter the credentials to connect to the PowerScale or Isilon cluster hosting the data to be replicated.

The screenshot shows a wizard window titled "Create File Replication Job Wizard" with a "Storage Information" step selected in the left-hand navigation pane. The main area contains a "Credentials" section with two radio button options: "New Credentials" (selected) and "Existing Credentials". Under "New Credentials", there are five text input fields labeled "*Cluster Name:", "*Cluster Username:", "*Cluster Password:", "Cluster Management IP:", and "Nodes:". An "Advanced" button is located to the right of the "Nodes" field. Below the "Existing Credentials" option is a drop-down menu. A "Validate" button is positioned at the bottom left of the main area. A note at the bottom of the main area reads: "Having trouble connecting? Please verify that all [prerequisites](#) are met for Dell PowerScale | EMC Isilon environments." At the bottom of the wizard, there are four buttons: "< Back", "Next >", "Finish", and "Cancel".

2. If you selected **Existing Credentials**, select a credential from the drop-down list, and then click **Next** to continue to the [Source Path](#) page.

If you selected **New Credentials**, supply the required information.

Field	Description
Cluster Name	Enter the name of the PowerScale or Isilon cluster hosting the data to be replicated.
Cluster Username	Enter the user name for the account managing the PowerScale or Isilon cluster.
Cluster Password	Enter the password for account managing the PowerScale or Isilon cluster.
Cluster Management IP	(Optional) Enter the IP address of the system used to manage the PowerScale or Isilon cluster. Required only if multiple Access Zones are in use on the cluster.
Nodes	(Optional) Enter one IP from each node in the cluster that the Agent can access to perform open file lookups. Use commas to separate nodes.


3. Click **Advanced** if you want to set [advanced options](#).
4. Click **Validate** to test the credentials.

After the credentials are validated, a success message appears.

5. Click **Next**.

The [Source Path](#) page is displayed.

1. Select **New Credentials** or **Existing Credentials** to enter the credentials to connect to the NetApp 7-Mode filer or vFiler hosting the data to be replicated.



- If you selected **Existing Credentials**, select a credential from the drop-down list, and then click **Next** to continue to the [Source Path](#) page.

If you selected **New Credentials**, supply the required information.

Field	Description
Filer Name	Enter the name of the NetApp 7-Mode filer or vFiler hosting the data to be replicated.

- Click **Advanced** if you want to set [advanced options](#).
- Click **Validate** to test the credentials.

After the credentials are validated, a success message appears.

- Click **Next**.

The [Source Path](#) page is displayed.

1. Select **New Credentials** or **Existing Credentials** to enter the credentials to connect to the Storage Virtual Machine hosting the data to be replicated.

The screenshot shows a window titled "Create File Replication Job Wizard" with a "Storage Information" tab selected. The window contains a sidebar with navigation options: "Source Agent", "Storage Platform", "Storage Information" (highlighted), "Source Path", "Destination Agent", "Destination Path", "File Metadata", and "Email Alerts". The main area is titled "Storage Information" and includes the instruction "Enter the information required to connect to the storage device." Under the "Credentials" section, there are two radio buttons: "New Credentials" (selected) and "Existing Credentials". The "New Credentials" section has five input fields: "*SVM Name:", "*SVM User Name:", "*SVM Password:", "SVM Management IP:", and "*Peer Agent IP:" (a dropdown menu). An "Advanced" button is located to the right of the "*Peer Agent IP:" field. Below the "Existing Credentials" radio button is a large greyed-out dropdown menu. A "Validate" button is positioned below the input fields. At the bottom of the window, there are four buttons: "< Back", "Next >", "Finish", and "Cancel". A note at the bottom of the main area reads: "Having trouble connecting? Please verify that all [prerequisites](#) are met for NetApp ONTAP/cDOT environments."

2. If you selected **Existing Credentials**, select a credential from the drop-down list, and then click **Next** to continue to the [Source Path](#) page.

If you selected **New Credentials**, supply the required information.

Field	Description
SVM Name	Enter the name, FDQN, or IP address of the Storage Virtual Machine hosting the data to be replicated.
SVM User Name	Enter the user name for the account managing the Storage Virtual Machine. This must not be a cluster management account.
SVM Password	Enter the password for the account managing the Storage Virtual Machine. This must not be a cluster management account.
SVM Management IP	(Optional) Enter the IP address used to access the management API of the NetApp Storage Virtual Machine. If the data LIFs (Logical Interfaces) corresponding to the SVM Name above already allow management access, this field is not required.
Peer Agent IP	Select the IP address of the server hosting the Agent that manages the Storage Virtual Machine. The Storage Virtual Machine must be able to route traffic to this IP address. If the IP address you want does not appear, manually enter the address.

3. Click **Advanced** if you want to set [advanced options](#).
4. Click **Validate** to test the credentials.

After the credentials are validated, a success message appears.

5. Click **Next**.

The [Source Path](#) page is displayed.

1. Select **New Credentials** or **Existing Credentials** to enter the credentials to connect to the Nutanix Files cluster hosting the data to be replicated.

The screenshot shows a window titled "Create File Replication Job Wizard" with a "Storage Information" tab selected in the left-hand navigation pane. The main area contains the following elements:

- Storage Information**: Enter the information required to connect to the storage device.
- Source Agent**
- Storage Platform**
- Storage Information** (selected)
- Source Path**
- Destination Agent**
- Destination Path**
- File Metadata**
- Email Alerts**

Credentials

- New Credentials**
- *Nutanix File Server Name:
- *Username:
- *Password:
- *Peer Agent IP:
-

Existing Credentials

Having trouble connecting? Please verify that all [prerequisites](#) are met for Nutanix Files environments.

2. If you selected **Existing Credentials**, select a credential from the drop-down list, and then click **Next** to continue to the [Source Path](#) page.

If you selected **New Credentials**, supply the required information.

Field	Description
Nutanix File Server Name	Enter the name of the Nutanix Files cluster hosting the data to be replicated.
Username	Enter the user name for the account managing the Nutanix Files cluster via its management APIs.
Password	Enter the password for the account managing the Nutanix Files cluster via its management APIs.
Peer Agent IP	Select the IP address of the server hosting the Agent that manages the Nutanix Files cluster. The Files cluster must be able to route traffic to this IP address. If the IP address you want does not appear, manually enter the address. This should not point to the Files cluster itself.


3. Click **Advanced** if you want to set [advanced options](#).
4. Click **Validate** to test the credentials.

After the credentials are validated, a success message appears.

5. Click **Next**.

The [Source Path](#) page is displayed.

1. Select the **Detector Type**.
 - Select **Windows Driver** for more robust logging and better performance (Recommended).
 - Select **Windows** if suggested by Peer Technical Support.




2. Click **Advanced** if you want to set [advanced options](#).
3. Click **Next**.

Windows File Server Advanced Options


1. Modify the options as desired.

The available options depend on the detector type selected: **Windows** or **Windows Driver**.

Windows



Windows Driver



The screenshot shows a dialog box titled "Windows Driver Detector Options". It contains several configuration options:

- Filter open/close events from these users: [Empty text box]
- Filter all events from these users: [Empty text box]
- Filter events from these IP Addresses: [Empty text box]
- Filter events from these local processes: [Empty text box]
- Access Event Suppression Time: [Spin box with value -1]
- Enable Local Access Events:
- Enable Remote IP Address Logging:
- Enable Close Modify:
- Close Modify Extension Override: [Empty text box]

Below these options is a section titled "Reparsing Point Options" containing three checked checkboxes:

- Follow Junction Points
- Follow Mount Points
- Follow Symbolic Links

At the bottom right of the dialog are "OK" and "Cancel" buttons.

Option	Description
Filter open/close events from these users	Enter a comma-separated list of user account names from which all file opens and closes will be ignored. This option can be used to filter out events from backup and/or archival services by filtering on the user name under which a backup and/or archival service is running.
Filter all events from these users	Enter a comma-separated list of user account names from which all file activities will be ignored. This option can be used to filter out events from backup and/or archival services by filtering on the user name under which a backup and/or archival service is running.
Filter events from these IP Addresses	Enter a comma-separated list of client IP addresses from which all file activities will be ignored. This option can be used to filter out events from backup and/or archival services by filtering on the IP addresses on which a backup and/or archival service is running.
Filter events from these local processes	Enter a comma-separated list of local process names on the Agent server from which all file activities will be ignored. This option can be used to filter out events from backup and/or archival services by filtering on the specific process names under which a backup and/or archival service is running.
Access Event Suppression Time	Enter the number of seconds to delay an open event before being processed. Use this option to help reduce the amount of chatter generated by Windows clients when mousing over files in Windows Explorer. The default value is -1, which will use a globally set value. A value of 0 will allow for dynamic changes to the amount of time an open event will be delayed based on the load of the system.
Enable Local Access Events	Enable tracking of opens and closes that are performed locally on the Agent server.
Enable Remote IP Logging	Enable logging of client IP addresses for all real-time activity.
Enable Close Modify	When enabled, no modify or write events will be detected. Instead, replication of a modified file will be performed when the file is closed.
Close Modify Extension Override	Enter a comma-separated list of exclusions for the Enable Close Modify option. All modify/write events will be detected for these files. This is important for those who rely on sync-on-save functionality.

For more information about junction points or symbolic links, contact [<% SUPPORT_EMAIL%](#)

2. Click **OK**.

Step 5: Source Path

The **Source Path** page is where you specify the path to the volume/share/folder you want to replicate. This volume/share/folder is referred to as the [watch set](#). The watch set can contain a single volume/share/folder. If you want to replicate multiple volumes/shares/folders, you need to create a separate job for each one.

1. Browse to or enter the path to the watch set.

The screenshot shows a window titled "Create File Replication Job Wizard" with standard Windows window controls (minimize, maximize, close). The main title is "Source Path" with the instruction "Browse to or enter a path on the storage device." On the left is a vertical list of steps: "Source Agent", "Storage Platform", "Storage Information", "Source Path" (highlighted), "Destination Agent", "Destination Path", "File Metadata", and "Email Alerts". The main area contains a text input field labeled "Enter Path" and a "Browse" button to its right. At the bottom of the window are four buttons: "< Back" (highlighted), "Next >", "Finish", and "Cancel".

2. Click **Next**.

The [Destination Agent](#) page is displayed.

Step 6: Destination Agent

The **Destination Agent** page lists available Agents, not including the Agent used as the Source Agent. This Destination Agent will be responsible for writing files and metadata to the destination storage device. No credentials are required for this Agent as it will not be monitoring anything in real-time.

1. Select the Agent that manages the destination storage device. If the destination is a Windows file server, the Agent should be installed on it.

The screenshot shows a window titled "Create File Replication Job Wizard" with a "Destination Agent" sub-header. Below the header is the instruction: "Select the server hosting the Peer Agent that manages the destination." On the left is a navigation pane with options: "Source Agent", "Storage Platform", "Storage Information", "Source Path", "Destination Agent" (highlighted), "Destination Path", "File Metadata", and "Email Alerts". The main area contains an information icon and the text: "Only Microsoft Windows Agents are available based on your previously selected Agents." Below this is a table with two columns: "Agent" and "Computer Description". The table lists three agents: DGWin16B, DGWin16C, and DGWin16D. At the bottom of the window are four buttons: "< Back", "Next >", "Finish", and "Cancel".

Agent	Computer Description
DGWin16B	
DGWin16C	
DGWin16D	

Tip: If the Agent you want is not listed, try restarting the Peer Agent Windows Service on that host. If it successfully connects to the Peer Management Broker, then the list is updated with that Agent.

2. Click **Next**.

The [Destination Path](#) page is displayed.

Step 7: Destination Path

The **Destination Path** page is where you specify the volume/share/folder that you want to replicate to. If the destination storage device is a Windows file server, this path should be a local path such as D:\Data. This path can also be the UNC path to any SMB-capable file server.

1. Browse to or enter the destination path:
 - If the path field is empty when you click **Browse**, the **Folder Browser** dialog will present a list of local drives and folders on the Agent server itself.
 - If you enter the start of a UNC path and click **Browse**, the **Folder Browser** dialog will attempt to present a list of the available shares on the file server specified in the path.

The screenshot shows a window titled "Create File Replication Job Wizard" with a "Destination Path" tab selected. The window contains a list of steps on the left: Source Agent, Storage Platform, Storage Information, Source Path, Destination Agent, Destination Path (highlighted), File Metadata, and Email Alerts. The main area has a text input field labeled "Enter Path" and a "Browse" button. At the bottom, there are four buttons: "< Back", "Next >", "Finish", and "Cancel".

2. Click **Next**.

The [File Metadata](#) page is displayed.

Step 8: File Metadata

This step is optional.

The **File Metadata** page allows you to specify whether you want to replicate NTFS security permissions metadata and the types of metadata to synchronize. It also allows you to specify which volume/share/folder's metadata should be used if there is a conflict during the [initial](#) synchronization. The volume/share/folder used if there is a conflict is referred to as the [master host](#).

For more information on synchronizing NTFS metadata, see [File Metadata Synchronization](#) in the [Advanced Topics](#) section.

To enable file metadata synchronization:

1. Select when you want the metadata replicated (you can select one or both options):
 - **Enable synchronizing NTFS security descriptors (ACLs) in real-time** - Select this option if you want the metadata synchronized in real-time. If enabled, changes to the selected security descriptor components (Owner, DACL, and SACL) will be transferred to the target host file(s) as they occur.
 - **Enable synchronizing NTFS security descriptors (ACLs) with master host during initial scan** - Select this option if you want the metadata replicated during the initial scan. If enabled, changes to the selected security descriptor components (Owner, DACL, and SACL) will be synchronized during the initial scan.

Create File Replication Job Wizard

File Metadata
Configure the replication of security permissions.

Source Agent
Storage Platform
Storage Information
Source Path
Destination Agent
Destination Path
File Metadata
Email Alerts

Synchronize File Security Information

- Enable synchronizing file security information in real-time
- Enable synchronizing file security information with master host during initial scan

Synchronize Security and ACL Options

- Owner
- DACL: Discretionary Access Control List
- SACL: System Access Control List

Metadata Conflict Resolution

Select master host for initial scan:

< Back Next > Finish Cancel

2. Click **OK** in the message that appears after selecting a metadata option.
3. If you selected either of the first two options in the **Synchronize Security Descriptor Options** section, select the security descriptor components (Owner, DACL, and SACL) to be synchronized.
4. If you selected the option for metadata synchronization during the initial scan, select the host to be used as the [master host](#) in case of file metadata conflict.

If a master host is not selected, then no metadata synchronization will be performed during the initial scan. If one or more security descriptors do not match across participants during the initial scan, [conflict resolution](#) will use permissions from the designated master host as the winner. If the file does not exist on the designated master host, a winner will be randomly picked from the other participants.

5. Click **Next**.

The [Email Alerts](#) page is displayed.

Step 9: Email Alerts

This step is optional.


An [email alert](#) notifies recipients when a certain type of event occurs, for example, session abort, host failure, system alert. The **Email Alerts** page displays a list of email alerts that have been applied to the job. When you first create a job, this list is empty. Email alerts are defined in [Preferences](#) and can then be applied to multiple jobs of the same type.

Peer Software recommends that you create email alerts in advance. However, from this wizard page, you can select existing alerts to apply to the job or create new alerts to apply.

To create a new alert, see [Email Alerts](#) in the [Preferences](#) section.


To apply an existing email alert to the job.

1. Click the **Select** button.




The **Select Email Alert** dialog appears.

2. Select an alert from the **Email Alert** drop-down list.



3. Click **OK**.

The alert is listed on the **Email Alerts** page.



4. (Optional) Repeat steps 1-3 to apply additional alerts.
5. Continue to [Step 10: Save Job](#).

Step 10: Save Job

Now that you have completed the first nine steps of the wizard, you are ready to save the job configuration.

1. If you are satisfied with your job configuration, click **Finish** to save your job. Otherwise, click the **Back** button and make any necessary changes.

Congratulations! You have created a File Replication job. A summary of the job configuration is displayed in the runtime view of the job.

The screenshot displays the Peer Management Center Client interface. The main window shows the 'Configuration Summary' for a File Replication job. The summary is divided into several sections:

- Selected Participants and Configurations:** Lists the source and target paths: DGWin16A C:\Data\Docs (Storage Platform: Windows Driver) and DGWin16C C:\Data\Docs (Storage Platform: Generic SMB).
- General Settings:**
 - Job Name: FR-3
 - Job ID: 220
 - Job Type: File Replication
 - Transfer Block Size: 2048 KB
 - Verify Checksum: true
 - Verify Full File Checksum: true
 - Use Multipart Transfers: false
 - Global Real-Time Expedited Threads: 20
 - Global Real-Time Background Threads: 20
 - Synchronization Priority: 2
 - Timeout: 180 Seconds
 - Scan Delay: 10
 - Remove Filtered Files On Folder Delete: true
 - Require All Hosts At Start: false
 - Auto Start: true
- Conflict Resolution:**
 - Latest Modified Time (Truncate Milliseconds): true
 - Quarantine Multi-edit Conflicts: true
 - Offline Folder Rename Detection: false
 - Offline Delete Detection During Scan: true
 - Delete Detection Master Host: none
- Delta Replication Settings:**
 - Enable Block/Byte Synchronization: true
 - Disable on Session Startup: false
 - Checksum Transfer Size: 256 KB
 - Delta Block Transfer Size: 1024 KB
 - Minimum File Size: 2048 KB
 - Minimum File Size Percentage Target/Source: 0.3
 - Excluded File Extensions: None
 - Excluded File Name Patterns: None
- File Metadata Settings:**
 - Enable attribute synchronization in real-time: false
 - Enable attribute synchronization with master host during initial scan: false
 - Enable ACL synchronization during real-time: false
 - Enable ACL synchronization with master host during initial scan: false
 - Prevent corrupt ACLs from being transferred: true

The job status is shown as 'Stopped'. Below the configuration summary, there is an 'Alerts' section with a table of job alerts:

Received Date	Severity	Type	Name	Host	Message	Exception
01-15-2023 03:53:34	Info	Connection	Startup	DGWin16A	Agent Started	
01-15-2023 03:53:31	Info	Heartbeat	Reconnect	DGWin16A	Connection status changed from Disconnected to Connected	

File Synchronization Jobs

This section provides information about creating a File Synchronization job:

- [Overview](#)
- [Before You Create Your First File Synchronization Job](#)

- [Creating a File Synchronization Job](#)
- [Editing a File Synchronization Job](#)
- [Running and Managing a File Synchronization Job](#)

Overview

A File Synchronization job provides real-time, multi-directional synchronization between various storage platforms and across locations. It is designed to handle non-collaborative workloads where files still need to be kept in-sync at multiple locations in real-time without locking. This job type is specifically optimized for use with user home directories and profiles.

Before You Create Your First File Synchronization Job

We strongly recommend that you configure global settings such as SMTP configuration and email alerts before configuring your first File Synchronization job. See [Preferences](#) for details on what and how to configure these settings.

Creating a File Synchronization Job

The **Create Job Wizard** walks you through the process of creating a File Synchronization job:

[Step 1: Job Type and Name](#)

[Step 2: Participants](#)

[Step 3: File Metadata](#)

[Step 4: Email Alerts](#)


[Step 5: Save Job](#)

Step 1: Job Type and Name

1. Open Peer Management Center.
2. From the **File** menu, select **New Job** (or click the **New Job** button on the toolbar).


The **Create New Job** wizard displays a list of job types you can create.

3. Click **File Synchronization**, and then click **Create**.



4. Enter a name for the job in the dialog that appears.

The job name must be unique.



The screenshot shows a dialog box titled "Create File Synchronization Job". It contains a text input field with the prompt "Enter a unique name." Below the input field is the message "Job name cannot be blank." At the bottom right, there are two buttons: "OK" and "Cancel".


5. Click **OK**.

The [Participants](#) page is displayed.

Step 2: Participants

After selecting the job type and naming the job, the **Participants** page is displayed. It contains a table that will display the job [participants](#) once you have added them. A File Synchronization job must have two or more participants. A **participant** consists of an Agent and the volume/share/folder to be replicated. A File Synchronization job synchronizes the files of participants in real-time.

1. Click the **Add** button to start the process of adding a participant.



The screenshot shows the "Create File Synchronization Job Wizard" window, specifically the "Participants" step. The title bar reads "Create File Synchronization Job Wizard". Below the title, it says "Participants" and "Add two or more participants to this File Synchronization job." On the left, there is a sidebar with "Participants" selected, and other options like "File Metadata", "Email Alerts", and "DFS Namespace". The main area contains a table with the following columns: Agent, Computer Description, Directory, Enabled, Storage Platform, Seeding Target, and DSU Role. To the right of the table are three buttons: "Add", "Edit", and "Delete". At the bottom, there are navigation buttons: "< Back", "Next >", "Finish", and "Cancel".


The **Add New Participant** wizard opens; it walks you through the steps for adding a participant:

- a. [Selecting a Management Agent](#), which is the Agent that will manage the storage device that hosts data you want to replicate.
- b. [Selecting the type of storage platform](#) that hosts data you want to replicate.
- c. [Entering the credentials needed to access a specific storage device and providing other storage information](#).
- d. [Entering the path](#) to the [watch set](#) (the data that you want to replicate) and selecting whether participant will be a [seeding target](#).
- e. (Optional) [Enabling Dynamic Storage Utilization](#) for the participant.

Once you have added a participant, it is listed in the **Participants** table.

Agent	Description	Directory	Enabled	Storage Platform	Seeding Target	DSU Role
DGWin16B		C:\64bit	Yes	Windows	No	Master

2. To add more participants, click **Add** and repeat the steps for each participant you want to add to the job.
3. Once you have added all the participants, click **Next**.




The page that appears next depends on options you selected when adding a participant:

- if you have enabled Dynamic Storage Utilization for a participant, the [Dynamic Storage Utilization](#) page appears.
- Otherwise, the [File Metadata](#) page appears.

The **Management Agent** page lists available [Agents](#). You can have more than one Agent managing a storage device—however, the Agents must be managing different volumes/shares/folders on the storage device. For your File Synchronization job, you should select a [Management Agent](#) to manages the volumes/shares/folders you want to synchronize in this job.

1. Select an Agent to manage the storage device.



2. Click **Next**.

The [Storage Information](#) page is displayed.

On the **Storage Information** page, you will select the storage device containing data that you want to synchronize and enter other information about the storage device. The contents of the **Storage Information** page varies, depending on your selection in the [Storage Platform](#) page:

- If you selected **Windows File Server**, you are prompted for configuration information relating to Windows File Server. Continue with the [Windows File Server](#) page.
- If you selected any other type of storage device other than Windows File Server, the **Storage Information** page requests the credentials necessary to connect to that storage device. Continue with the steps below.

For storage platforms other than Windows File Server:

1. Select **New Credentials** or **Existing Credentials**.
2. If you selected **Existing Credentials**, select a credential from the drop-down list, and then click **Next** to continue to the [Path](#) page.

If you selected **New Credentials**, enter the credentials for connecting to the storage device. The information you are prompted to enter varies, depending on the type of storage platform:

[Amazon FSxN](#)

[Dell EMC Unity](#)

[Dell EMC Celerra | VNX | VNX 2](#)

[Dell EMC Powerscale | Isilon](#)

[NetApp Data ONTAP 7-Mode](#)

[NetApp ONTAP | Clustered Data ONTAP](#)

[Nutanix Files](#)

3. Click **Validate** to test the credentials.

After the credentials are validated, a success message appears.

4. Click **Next**.

The [Path](#) page is displayed.

Amazon FSxN

1. Select **New Credentials** or **Existing Credentials** to enter the credentials to connect to the Storage Virtual Machine hosting the data to be synchronized.

The screenshot shows a window titled "Add New Participant" with a "Storage Information" section. The instruction reads: "Enter the information required to connect to the storage device." On the left, a sidebar lists "Management Agent", "Storage Platform", "Storage Information" (selected), "Path", and "Dynamic Storage Utilization". The main area is titled "Credentials" and has two options: "New Credentials" (selected) and "Existing Credentials". Under "New Credentials", there are five input fields: "*SVM Name:", "*SVM User Name:", "*SVM Password:", "SVM Management IP:", and "*Peer Agent IP:". An "Advanced" button is to the right of the last field. Under "Existing Credentials", there is a drop-down menu. A "Validate" button is at the bottom left of the main area. Below the main area, a note says: "Having trouble connecting? Please verify that all [prerequisites](#) are met for Amazon FsxN environments." At the bottom of the window, there are four buttons: "< Back", "Next >", "Finish", and "Cancel".

2. If you selected **Existing Credentials**, select a credential from the drop-down list, and then click **Next** to continue to the [Path](#) page.

If you selected **New Credentials**, supply the required information.

Field	Description
SVM Name	Enter the name, FQDN, or IP address of the Storage Virtual Machine hosting the data to be replicated.
SVM User Name	Enter the user name for the account managing the Storage Virtual Machine. This must not be a cluster management account.
SVM Password	Enter the password for the account managing the Storage Virtual Machine. This must not be a cluster management account.
SVM Management IP	(Optional) Enter the IP address used to access the management API of the Storage Virtual Machine. If the data LIFs (Logical Interfaces) corresponding to the SVM Name above already allow management access, this field is not required.
Peer Agent IP	Select the IP address of the server hosting the Agent that manages the Storage Virtual Machine. The Storage Virtual Machine must be able to route traffic to this IP address. If the IP address you want does not appear, manually enter the address.

3. Click **Advanced** if you want to set [advanced options](#).
4. Click **Validate**.

After the credentials are validated, a success message appears.

5. Click **Next**.

The [Path](#) page is displayed.

1. Select **New Credentials** or **Existing Credentials** to enter the credentials to connect to the CIFS Server hosting the data to be synchronized.

The screenshot shows a window titled "Add New Participant" with a "Storage Information" section. The instruction reads: "Enter the information required to connect to the storage device." On the left, a sidebar lists "Management Agent", "Storage Platform", "Storage Information" (highlighted), "Path", and "Dynamic Storage Utilization". The main area is titled "Credentials" and has two radio button options: "New Credentials" (selected) and "Existing Credentials". Under "New Credentials", there are four text input fields: "*CIFS Server Name:", "*Control Station Username:", "*Control Station Password:", and "*Control Station IP:". An "Advanced" button is located to the right of the IP field. Below the "Existing Credentials" option is a drop-down menu. A "Validate" button is positioned below the input fields. At the bottom of the main area, a note says: "Having trouble connecting? Please verify that all [prerequisites](#) are met for Dell EMC VNX/Celerra environments." The bottom of the window features a navigation bar with buttons: "< Back", "Next >", "Finish", and "Cancel".

2. If you selected **Existing Credentials**, select a credential from the drop-down list, and then click **Next** to continue to the [Path](#) page.

If you selected **New Credentials**, supply the required information.

Field	Description
CIFS Server Name	Enter the name of the CIFS Server hosting the data to be replicated.
Control Station Username	Enter the user name for the Control Station account managing the Celerra/VNX storage device.
Control Station Password	Enter the password for the Control Station account managing the Celerra/VNX storage device.
Control Station IP	Enter the IP address of the Control Station system used to manage the Celerra/VNX storage device. This should not point to the CIFS Server.

3. Click **Advanced** if you want to set [advanced options](#).
4. Click **Validate** to test the credentials.


After the credentials are validated, a success message appears.

5. Click **Next**.

The [Path](#) page is displayed.

Dell EMC Unity

1. Select **New Credentials** or **Existing Credentials** to enter the credentials to connect to the CIFS Server hosting the data to be synchronized.



Add New Participant

Storage Information

Enter the information required to connect to the storage device.

Management Agent
Storage Platform
Storage Information
Path
Dynamic Storage Utilization

Credentials

New Credentials

*CIFS Server Name:

*Unisphere Username:

*Unisphere Password:

*Unisphere Management IP:

Advanced

Existing Credentials

Validate

Having trouble connecting? Please verify that all [prerequisites](#) are met for Dell EMC Unity environments.

< Back Next > Finish Cancel

- If you selected **Existing Credentials**, select a credential from the drop-down list, and then click **Next** to continue to the [Path](#) page.

If you selected **New Credentials**, supply the required information.

Field	Description
CIFS Server Name	Enter the name of the NAS server hosting the data to be replicated.
Unisphere Username	Enter the user name for the Unisphere account managing the Unity storage device.
Unisphere Password	Enter the password for the Unisphere account managing the Unity storage device.
Unisphere Management IP	Enter the IP address of the Unisphere system used to manage the Unity storage device. This should not point to the NAS server.

3. Click **Advanced** if you want to set [advanced options](#).
4. Click **Validate**.

After the credentials are validated, a success message appears.

5. Click **Next**.

The [Path](#) page is displayed.

Dell PowerScale | EMC Isilon

1. Select **New Credentials** or **Existing Credentials** to enter the credentials to connect the PowerScale or Isilon cluster hosting the data to be synchronized.

The screenshot shows a window titled "Add New Participant" with a "Storage Information" tab selected. The window contains a sidebar with navigation options: Management Agent, Storage Platform, Storage Information (selected), Path, and Dynamic Storage Utilization. The main area is titled "Storage Information" and includes the instruction "Enter the information required to connect to the storage device." Under the "Credentials" section, there are two radio buttons: "New Credentials" (selected) and "Existing Credentials". The "New Credentials" section includes input fields for "*Cluster Name:", "*Cluster Username:", "*Cluster Password:", "Cluster Management IP:", and "Nodes:". An "Advanced" button is located to the right of the "Nodes" field. Below the "Existing Credentials" radio button is a drop-down menu. A "Validate" button is positioned below the "Existing Credentials" section. At the bottom of the window, there are four buttons: "< Back", "Next >", "Finish", and "Cancel". A note at the bottom of the main area reads: "Having trouble connecting? Please verify that all [prerequisites](#) are met for Dell PowerScale | EMC Isilon environments."

2. If you selected **Existing Credentials**, select a credential from the drop-down list, and then click **Next** to continue to the [Path](#) page.

If you selected **New Credentials**, supply the required information.

Field	Description
Cluster Name	Enter the name of the PowerScale or Isilon cluster hosting the data to be replicated.
Cluster Username	Enter the user name for the account managing the PowerScale or Isilon cluster.
Cluster Password	Enter the password for account managing the PowerScale or Isilon cluster.
Cluster Management IP	(Optional) Enter the IP address of the system used to manage the PowerScale or Isilon cluster. Required only if multiple Access Zones are in use on the cluster.
Nodes	(Optional) Enter one IP from each node in the cluster that the Agent can access to perform open file lookups. Use commas to separate nodes.

3. Click **Advanced** if you want to set [advanced options](#).
4. Click **Validate**.


After the credentials are validated, a success message appears.

5. Click **Next**.

The [Path](#) page is displayed.

NetApp Data ONTAP 7-Mode

1. Select **New Credentials** or **Existing Credentials** to enter the credentials to connect to the NetApp 7-Mode filer or vFiler hosting the data to be synchronized.



Add New Participant

Storage Information

Enter the information required to connect to the storage device.

Management Agent
Storage Platform
Storage Information
Path
Dynamic Storage Utilization

Credentials

New Credentials

*Filer Name:

Existing Credentials

Having trouble connecting? Please verify that all [prerequisites](#) are met for NetApp 7-Mode environments.

- If you selected **Existing Credentials**, select a credential from the drop-down list, and then click **Next** to continue to the [Path](#) page.

If you selected **New Credentials**, supply the required information.

Field	Description
Filer Name	Enter the name of the NetApp 7-Mode filer or vFiler hosting the data to be replicated.

- Click **Advanced** if you want to set [advanced options](#).
- Click **Validate**.

After the credentials are validated, a success message appears.

- Click **Next**.

The [Path](#) page is displayed.

NetApp ONTAP | Clustered Data ONTAP

1. Select **New Credentials** or **Existing Credentials** to enter the credentials to connect to the Storage Virtual Machine hosting the data to be synchronized.

Add New Participant

Storage Information
Enter the information required to connect to the storage device.

Management Agent
Storage Platform
Storage Information
Path
Dynamic Storage Utilization

Credentials

New Credentials

*SVM Name:

*SVM User Name:

*SVM Password:

SVM Management IP:

*Peer Agent IP:

Existing Credentials

Having trouble connecting? Please verify that all [prerequisites](#) are met for NetApp ONTAP/cDOT environments.

2. If you selected **Existing Credentials**, select a credential from the drop-down list, and then click **Next** to continue to the [Path](#) page.

If you selected **New Credentials**, supply the required information.

Field	Description
SVM Name	Enter the name, FDQN, or IP address of the Storage Virtual Machine hosting the data to be replicated.
SVM User Name	Enter the user name for the account managing the Storage Virtual Machine. This must not be a cluster management account.
SVM Password	Enter the password for the account managing the Storage Virtual Machine. This must not be a cluster management account.
SVM Management IP	(Optional) Enter the IP address used to access the management API of the Storage Virtual Machine. If the data LIFs (Logical Interfaces) corresponding to the SVM Name above already allow management access, this field is not required.
Peer Agent IP	Select the IP address of the server hosting the Agent that manages the Storage Virtual Machine. The Storage Virtual Machine must be able to route traffic to this IP address. If the IP address you want does not appear, manually enter the address.

3. Click **Advanced** if you want to set [advanced options](#).
4. Click **Validate**.

After the credentials are validated, a success message appears.

5. Click **Next**.

The [Path](#) page is displayed.

Nutanix Files

1. Select **New Credentials** or **Existing Credentials** to enter the credentials to connect to the Nutanix Files cluster hosting the data to be synchronized.

The screenshot shows a window titled "Add New Participant" with a "Storage Information" tab selected. The window contains a sidebar with navigation options: "Management Agent", "Storage Platform", "Storage Information" (highlighted), "Path", and "Dynamic Storage Utilization". The main area is titled "Storage Information" and contains the instruction: "Enter the information required to connect to the storage device." Under the "Credentials" section, there are two radio button options: "New Credentials" (selected) and "Existing Credentials". The "New Credentials" section includes four input fields: "*Nutanix File Server Name:", "*Username:", "*Password:", and "*Peer Agent IP:". There is an "Advanced" button to the right of the "*Peer Agent IP:" field. The "Existing Credentials" section has a drop-down menu. A "Validate" button is located below the input fields. At the bottom of the window, there is a message: "Having trouble connecting? Please verify that all [prerequisites](#) are met for Nutanix Files environments." and a set of navigation buttons: "< Back", "Next >", "Finish", and "Cancel".

2. If you selected **Existing Credentials**, select a credential from the drop-down list, and then click **Next** to continue to the [Path](#) page.

If you selected **New Credentials**, supply the required information.

Field	Description
Nutanix File Server Name	Enter the name of the Nutanix Files cluster hosting the data to be replicated.
Username	Enter the user name for the account managing the Nutanix Files cluster via its management APIs.
Password	Enter the password for the account managing the Nutanix Files cluster via its management APIs.
Peer Agent IP	Select the IP address of the server hosting the Agent that manages the Nutanix Files cluster. The Files cluster must be able to route traffic to this IP address. If the IP address you want does not appear, manually enter the address. This should not point to the Files cluster itself.

3. Click **Advanced** if you want to set [advanced options](#).
4. Click **Validate**.


After the credentials are validated, a success message appears.

5. Click **Next**.

The [Path](#) page is displayed.

Windows File Server

1. Select the **Detector Type**.
 - Select **Windows Driver** for more robust logging and better performance (Recommended).
 - Select **Windows** if suggested by Peer Technical Support.




2. Click **Advanced** if you want to set [advanced options](#).
3. Click **Next**.

The [Path](#) page is displayed.

1. Modify the options as desired.

The available options depend on the detector type selected: **Windows** or **Windows Driver**.

Windows



Windows Driver

The image shows a Windows dialog box titled "Windows Driver Detector Options". The dialog has a standard Windows window title bar with minimize, maximize, and close buttons. The main content area contains several configuration options:

- Filter open/close events from these users: [Empty text box]
- Filter all events from these users: [Empty text box]
- Filter events from these IP Addresses: [Empty text box]
- Filter events from these local processes: [Empty text box]
- Access Event Suppression Time: [Spin box with value -1]
- Enable Local Access Events:
- Enable Remote IP Address Logging:
- Enable Close Modify:
- Close Modify Extension Override: [Empty text box]

Below these options is a section titled "Reparsing Point Options" which contains three checked checkboxes:

- Follow Junction Points
- Follow Mount Points
- Follow Symbolic Links

At the bottom right of the dialog are two buttons: "OK" and "Cancel".

Option	Description
Filter open/close events from these users	A comma-separated list of user account names from which all opens and closes will be ignored. Ideal for filtering out events from backup and/or archival services by filtering on the username under which a backup and/or archival service is running.
Access Event Suppression Time	Represents number of seconds an open event will be delayed before being processed. Used to help reduce the amount of chatter generated by Windows 7 clients when mousing over files in Windows Explorer. The default value is -1, which will use a globally set value. A value of 0 will allow for dynamic changes to the amount of time an open event will be delayed based on the load of the system.
Follow Junction Points	Enables junction point support for the selected Windows File Server.
Follow Mount Points	Enables mount point support for the selected Windows File Server.
Follow Symbolic Links	Enables symbolic link support for the selected Windows File Server.

For more information about junction points or symbolic links, contact [<% SUPPORT_EMAIL%](#)

2. Click **OK**.


The **Path** page is where you specify the path to the volume/share/folder you want to replicate. This volume/share/folder is referred to as the [watch set](#). The watch set can contain a single volume/share/folder. If you want to replicate multiple volumes/shares/folders, you need to create a separate job for each one.

1. Browse to or enter the path to the watch set.

The screenshot shows a dialog box titled "Add New Participant" with a close button in the top right. The "Path" section is selected in a left-hand menu. A red error icon and the message "You must enter a valid path." are displayed above the "Enter Path" text box. To the right of the text box is a "Browse" button. Below the text box is an unchecked checkbox labeled "Seeding Target". At the bottom of the dialog, there are four buttons: "< Back" (highlighted with a blue border), "Next >", "Finish", and "Cancel".

2. (Optional) Select the **Seeding Target** checkbox, and then click **OK** in the dialog that appears.

If you select this option, a message describing seeding behavior is displayed. Multiple participants in a File Synchronization job can be set as smart data seeding targets; however, at least one participant should not be set as a smart data seeding target. This participant will be acting as the "master" source for the smart data seeding targets. For more information about smart data seeding, see [Smart Data Seeding](#) or contact support@peersoftware.com.



3. Click **Finish** to complete the wizard for this participant.
4. Return to [Step 2: Participants](#) to add more participants, if applicable. A File Synchronization job must have at least two participants. If you have added all the participants, continue with [Step 4: File Metadata](#).

Dynamic Storage Utilization (DSU) is a method for conserving space on storage devices by caching files until needed. DSU saves space by stubbing files and rehydrating them as needed. DSU is optional; if you don't need to conserve space on the storage device managed by the Agent, then you do not need to select this option.

If you enable [Dynamic Storage Utilization](#) (DSU) for a participant, you must designate the participant as either a **master** or **edge** participant.

- **Master participant** - A master participant always has complete set of files for that job. None of the files are stubbed; they are stored physically on that device.
- **Edge participant** - A subset of the files stored on a master participant are physically stored on an edge participant; the rest of the files on an edge participant are stub files that take up minimal space. DSU allows users to seamlessly retrieve stubbed files directly from a master participant as needed; when retrieved, the local stub file is rehydrated so that the full file is stored locally on the edge participant.


A job can have master and edge participants, as well as participants that don't have either role. If you do not choose to enable DSU for a participant, it will always have a full set of files like a master participant but will not be used to serve file content to any edge participants.

Notes:

- A participant can be a master participant for some jobs and an edge participant for other jobs.
- A job needs at least one master participant that isn't a seeding target. If there is only one master participant for the job, it should not be a seeding target.

For more information about DSU, see [Dynamic Storage Utilization](#) in [Advanced Topics](#).

1. Select the **Enable Dynamic Storage Utilization** checkbox if you want this participant to be able to use Dynamic Storage Utilization; otherwise, click **Finish**.




The screenshot shows a dialog box titled "Add New Participant" with a sub-header "Dynamic Storage Utilization". Below the sub-header is the instruction "Enable Dynamic Storage Utilization and select role." The main area is split into two panes. The left pane is a list of options: "Management Agent", "Storage Platform", "Storage Information", "Path", and "Dynamic Storage Utilization". The right pane contains a checkbox labeled "Enable Dynamic Storage Utilization". At the bottom of the dialog are four buttons: "< Back", "Next >", "Finish", and "Cancel".

If you enable DSU, the DSU role options are displayed; the **Master** role is selected by default.

2. Choose a DSU role for the participant:

- Choose **Master** if the storage device managed by the Agent will contain complete copies of all files for this job. Any type of storage platform can be a master participant.



- Choose **Edge** if you want to conserve space on the storage device managed by the Agent. Only Windows File Servers can be an edge participant.

The screenshot shows a window titled "Add New Participant" with a sub-header "Dynamic Storage Utilization". Below the sub-header is the instruction "Enable Dynamic Storage Utilization and select role." The window is divided into two main sections. On the left is a navigation pane with a tree view containing the following items: "Management Agent", "Storage Platform", "Storage Information", "Path", "Dynamic Storage Utilization" (which is expanded to show "Volume Policy", "Utilization Policy", and "Pinning Filter"), and "Volume Policy". On the right is the main configuration area. It contains a checked checkbox labeled "Enable Dynamic Storage Utilization". Below this is the label "Select Dynamic Storage Utilization role:" followed by two radio button options: "Master" (which is unselected) and "Edge" (which is selected). At the bottom of the window are three buttons: "< Back", "Next >" (which is highlighted with a blue border), and "Cancel".

3. Click **Next**.

- If you selected **Master**, continue with the [Master Data Service](#) page.
- If you selected **Edge**, continue with the [Volume Policy](#) page.

Master Data Service

The **Master Data Service** page appears if you chose the master role for the participant. The Master Data Service handles requests from edge participants for files on a master participant. The Master Data Service is installed on the Agent server as part of the Peer Agent installation process.

The first two fields on this page are automatically populated:

- **Protocol:** This field lists the protocol that will be used to transfer file content between master participants and edge participants. HTTPS is currently the only available option as

it requires only a single open firewall port on each master participant and does a better job of handling latency over WAN-based connections.

- **Agent Name:** This field lists the name of the Management Agent that you selected at the beginning of Step 2.
1. (Optional) Enter a value for **Agent Alias**. The value can be a hostname, FDQN, or IP address.

A value for this field is required only if the name of the Agent cannot be converted to an IP address via DNS. If an alias is entered, it will be used by the Edge Service on edge participants to connect with the Master Data Service. If no alias is entered, the name in the Agent Name will be used.


2. (Optional) Modify the port number that the Master Data Service will listen on for this master participant.

A default value for the port number, 8446, is set when the Agent is installed. If you modify the port number, the Master Data Service is started with the new port number.

The screenshot shows a window titled "Add New Participant" with a sub-header "Master Data Service" and the instruction "Configure access to the Master Data Service." On the left is a tree view with categories: Management Agent, Storage Platform, Storage Information, Path, Dynamic Storage Utilization (expanded), and Master Data Service (selected). On the right are four input fields: Protocol (HTTPS), Agent Name (DGWin16B), Agent Alias (empty), and Port (8446). At the bottom are four buttons: "< Back" (highlighted), "Next >", "Finish", and "Cancel".

Note: If the Agent you selected is already being used as a master participant in another job utilizing DSU, then the existing Master Data Service parameters will be displayed. You can edit the values by clicking the **Edit Master Data Service** link. If you modify the

port number, the Master Data Service will be restarted and the new port number will take effect immediately. Any modifications you apply will be applied to every other job that use this Agent as a master participant.



3. Click **Finish**.

The **Participants** page reappears. The participant is listed in the **Participants** table with the **Master** role.

To create a volume policy:

1. In the **Cache Size** section, choose an option for setting the cache size:
 - Use up to X % of this volume
 - Use up to X size of this volume

The screenshot shows the 'Add New Participant' dialog box with the 'Volume Policy' section selected. The 'Cache Size' section has two radio buttons: 'Use up to 75 % of this volume' (selected) and 'Use up to 10 GB of this volume'. The 'Cache Threshold Alerts' section has two rows: 'Disk space is less than 512 MB' and 'Cache usage exceeds 80 % of the cache size'. The 'Caching Scan Schedule' section has two radio buttons: 'Scan every 1 day(s) at 10:00:00 PM' (selected) and 'Define schedule'. The 'Temporary Storage Path' is set to 'C:\' with a 'Browse' button. At the bottom, there are '< Back', 'Next >', and 'Cancel' buttons.

2. In the **Cache Threshold Alerts** section, set threshold values for automatic alerts about free disk space and cache usage.

Peer Management Center will automatically display alerts in the **Alerts** tab when:

- The amount of free disk space on the volume falls below the specified value. For example, if a 1 TB volume has 500 MB of free space and the threshold is set to 512 MB, an alert will be sent.
- Cache usage on the volume exceeds the specified percentage of the cache size. For example, if the cache size is set to 80%, equating to 750 GB, DSU will start sending alerts when it has used 600 GB.

You can also send cache threshold alerts via [email alerts](#) and [SNMP notifications](#). You configure these in [Dynamic Storage Utilization](#) preferences for File Collaboration and File Synchronization jobs.

3. In the **Caching Scan Schedule**, set the frequency that the volume should be scanned to optimize the balance of fully hydrated vs stubbed files.

This scan can be run daily at a specified time or you can define a more customized schedule.

4. In the **Temporary Storage Path** field, enter a path or browse to the location you want to be used as temporary storage space.


The temporary storage space will be used to store the content of stub files as they are being rehydrated. The content of files undergoing rehydration are referred to as **file blocks**. File blocks are fixed-length chunks of data that are read into memory when requested by an application. DSU will create a subfolder named **.PeerTempPath** under the location that you specify and temporarily store the file blocks in that subfolder.

For optimal performance, we recommend that the temporary storage space be on the same volume as the watch set. If that is not possible, it should be on a high performance disk.

5. Click **Next**.

The [Utilization Policy](#) page appears.

Note: If the Agent you selected is already being used as an edge participant in another job utilizing DSU, the existing volume policy will be displayed on this page. You can edit the existing volume policy; however, be aware that any modifications to the volume policy will be applied to every other job that uses this Agent as an edge participant and "touches" the same volume.



Utilization Policy

The **Utilization Policy** page appears if you chose the edge role for the participant. The primary purpose of a **utilization policy** is to specify the parameters that govern when files on this edge participant should be stubbed or fully hydrated. Whereas the volume policy controls how much space is available to DSU on a specific volume (or drive letter), the utilization policy controls whether to stub or hydrate a file.

Utilization policy parameters are based on the size of the files to be potentially stubbed and when they were last accessed and modified. A utilization policy enables you to balance getting the best performance while keeping the cache as full as possible.

You can select an existing utilization policy to apply to the job or create a new utilization policy. Whereas a volume policy is specific to a volume, a utilization policy can be reused for multiple jobs.

1. Select **New Policy** or **Existing Policy**.

- If you selected **Existing Policy**, select the policy, and then click **Next**.

If you selected **New Policy**, enter a name for the policy.

- (Optional) In the **File Size** section, select one or both options:

Field	Description
Keep files local if less than X size	Select this option if you want files under a specified size to remain local.
Stub files if greater than X size	Select this option if you want files over a specified size to be stubbed.

- (Optional) In the **Time Period** section, select one of the options:

Field	Description
Keep recently used files local based on a dynamic set of rules	Select this option if you want DSU to control when to stub files based on last accessed and last modified times. DSU dynamically adjusts the accessed and modified time periods it uses based on the total amount of space that DSU is actively using on a volume.
Keep recently used files local based on the following rules	Select this option if you want to specify the dates used when stubbing files based on the last accessed and last modified.

5. If you selected the **Keep recently used files local based on the following rules** option in **Time Period**, two additional options are enabled; select the options to be used and specify the time periods to be used:

Field	Description
Stub files if not modified within the past X time period	Select this option and specify a time range to use the last modified date of a file to determine if it should be kept local or stubbed.
Stub files is not accessed within the past X time period	Select this option and specify a time range to use the last accessed date of a file to determine if it should be kept local or stubbed.

6. (Optional) In the **Stubbing Override** section, select the checkbox and a time period if you want to use the last accessed date of all recently hydrated files to determine if they should be kept local or re-stubbed.

7. Click **Next** or **Finish**.

If you click **Next**, the [Pinning Filter](#) page appears.

Pinning Filter

The **Pinning Filter** page allows you to create a new pinning filter or select an existing pinning filter to apply to the job. A **pinning filter** specifies whether specific files or files in a particular

directory are always stubbed or always local on an edge participant. A pinning filter similar is to a utilization policy—it can be applied to multiple jobs. If there is a conflict between a pinning filter and utilization policy (where, for example, you might have something set to be always stubbed), the pinning filter will take precedence. Pinning filters are optional.

1. Select one of the options: **No Filter**, **New Filter**, or **Existing Filter**.

The screenshot shows a window titled "Add New Participant" with a "Pinning Filter" section. The section contains the instruction "Create a new pinning filter or select an existing one." Below this, there is a tree view on the left with "Pinning Filter" selected. To the right, under "Edit Pinning Filters", there are three radio button options: "No Filter" (selected), "New Filter", and "Existing Filter". Below these options is a dropdown menu. At the bottom of the window, there are four buttons: "< Back", "Next >", "Finish", and "Cancel".

2. If you selected **No Filter**, click **Finish**; if you selected **Existing Filter**, select the filter, and then click **Finish**.

If you selected **New Filter**, enter a name for the filter.

The screenshot shows the 'Add New Participant' dialog box with the 'Pinning Filter' section active. A red error message at the top states 'Name should not be empty.' The left sidebar contains a tree view with 'Pinning Filter' selected. The main area has an 'Edit Pinning Filters' section with radio buttons for 'No Filter' and 'New Filter' (selected). Below this is a text field for '*Name:'. A 'Pinning Rules' table is shown with two columns: 'Path' and 'Pinning State'. To the right of the table are 'Create', 'Edit', and 'Delete' buttons. Below the table is an 'Existing Filter' section with a dropdown menu. At the bottom of the dialog are '< Back', 'Next >', and 'Cancel' buttons.

Path	Pinning State

3. Enter a name for the filter.
4. Click **Create**.

The **Create Pinning Rule** dialog appears.

The screenshot shows the 'Create Pinning Rule' dialog box. It has a title bar with a close button. The main text says 'Enter a file name or path and choose pinning state.' There is a text field labeled 'Pattern:' and a dropdown menu labeled 'Pinning State:' with 'Local at Edge' selected. At the bottom are 'OK' and 'Cancel' buttons.

5. Enter a file name or path in the **Pattern** field and then choose a pinning state: **Local at Edge** or **Stubbed at Edge**.

- Click **OK**.

The rule appears in the filter table.

Add New Participant

Pinning Filter
Create a new pinning filter or select an existing one.

Management Agent
Storage Platform
Storage Information
Path
Dynamic Storage Utilization
Volume Policy
Utilization Policy
Pinning Filter

Edit Pinning Filters

No Filter
 New Filter

*Name: Outlook files

Pinning Rules:

Path	Pinning State
*.pst	Local at Edge

Existing Filter


Create
Edit
Delete

< Back Next > Finish Cancel

- (Optional) Create additional pinning rules.

- Click **Finish**.

The **Participants** page reappears. The participant is listed in the **Participants** table with the **Edge** role.



- Continue adding more participants if applicable or continue with [Step 3: Master-Edge Assignment](#)

Step 3: Master-Edge Assignment

This step is optional.


The **Master-Edge Assignment** page appears only if you enabled Dynamic Storage Utilization for one or more participants in Step 2. The purpose of this page is to allow you to assign one or more master participants to each edge participant.

Every edge participant must have at least one master participant assigned to it, so that DSU will know which master participants to use when reading or rehydrating a stub file on an edge participant. For each edge participant, you want to assign the master participant that is the fastest and closest to it. This will increase the speed of rehydrating a stub file.


It is highly recommended that you assign, if possible, more than one master participant to an edge participant, so that if one master participant is not available, another master participant is able to provide the file content to the edge participant. You can set the order in which the master participants are consulted.

If you have only one edge participant and one master participant, the master participant is automatically assigned to the edge participant and listed in the Master Participants column. If you have multiple master participants, you need to explicitly assign master participants to each edge participant and then set the failover order.

- Select an edge participant in the **Assignment** table.



- (Optional) Change the failover order by selecting a master participant and using the **Move Up** and **Move Down** buttons.



- **Enable synchronizing NTFS security descriptors (ACLs) in real-time** - Select this option if you want the metadata synchronized in real-time. If enabled, changes to the selected security descriptor components (Owner, DACL, and SACL) will be synchronized to all participants as they occur.
- **Enable synchronizing NTFS security descriptors (ACLs) with master host during initial scan** - Select this option if you want the metadata replicated during the initial scan. If enabled, changes to the selected security descriptor components (Owner, DACL, and SACL) will be synchronized during the initial scan.

Participants
Master-Edge Assignment
File Metadata
Email Alerts
DFS Namespace

Synchronize File Security Information

Enable synchronizing file security information in real-time

Enable synchronizing file security information with master host during initial scan

Synchronize Security and ACL Options

Owner

DACL: Discretionary Access Control List

SACL: System Access Control List

Metadata Conflict Resolution

Select master host for initial scan:

< Back Next > Finish Cancel

2. Click **OK** in the message that appears after selecting a metadata option.
3. If you selected either of the first two options in the **Synchronize Security Descriptor Options** section, select the security descriptor components (Owner, DACL, and SACL) to be synchronized.
4. If you selected the option for metadata synchronization during the initial scan, select the host to be used as the [master host](#) in case of file metadata conflict.

If a master host is not selected, then no metadata synchronization will be performed during the initial scan. If one or more security descriptors do not match across participants during the initial scan, [conflict resolution](#) will use permissions from the designated master host as the winner. If the file does not exist on the designated master host, a winner will be randomly picked from the other participants.

5. Click **Next**.

The [Email Alerts](#) page is displayed.

Step 5: Email Alerts

This step is optional.


An email alert notifies recipients when a certain type of event occurs, for example, session abort, host failure, or system alert. The **Email Alerts** page displays a list of email alerts that have been applied to the job. When you first create a job, this list is empty. Email alerts are defined in [Preferences](#) and can then be applied to multiple jobs of the same type.

Peer Software recommends that you create email alerts in advance. However, from this wizard page, you can select existing alerts to apply to the job or create new alerts to apply.

To create a new alert, see [Email Alerts](#) in the [Preferences](#) section.


To apply an existing email alert to the job.

1. Click the **Select** button.




The **Select Email Alert** dialog appears.

2. Select an alert from the **Email Alert** drop-down list.



3. Click **OK**.

The alert is listed on the **Email Alerts** page.



4. (Optional) Repeat steps 1-3 to apply additional alerts.
5. Continue to [Step 6: DFS Namespace](#).


Step 6: DFS Namespace

This step is optional.


The **DFS Namespace** page presents three options for linking a DFS namespace folder to this File Synchronization job.

To link a namespace to this job:

1. Click the **Enable linking job to DFS Namespace** checkbox.



The three options are enabled.



2. Select one of the three options:

- **New DFS Namespace** - Select this option if you want to [create](#) a new namespace that will automatically be linked to this job. If you select this option, the **Create DFS-N Management Job Wizard** opens. Follow these steps to [create a new namespace](#).
- **Import DFS Namespace** - Select this option if you have a namespace that was created using the Microsoft DFS Management tool and is not currently being managed by a DFS-N Management job. If you select this option, the **Import Existing Namespaces** wizard opens. For detailed instructions, follow these steps to [import an existing namespace](#).
- **Existing DFS Namespace** - Select this option if you want to use an existing namespace that is being managed by a DFS-N Management job. If you select this option, it will display the namespace folder and folders associated with namespace. If you want to make changes to the namespace, you can edit the DFS-N Management job managing that namespace.

The screenshot shows the 'Create File Synchronization Job Wizard' window at the 'DFS Namespace' step. The left sidebar contains a tree view with 'DFS Namespace' selected. The main area has a checkbox for 'Enable DFS Linking' which is checked. Below it are three radio buttons: 'New DFS Namespace', 'Import DFS Namespace', and 'Existing DFS Namespace', with the last one selected. A dropdown menu shows 'DG' as the selected namespace. Below this, it says 'Selected DFS Namespace: DG'. Under 'Folders:', there is '- DGNSF'. Under 'Targets:', there are '- \\DGWin16B\US' and '- \\DGWin16C\USA'. At the bottom, there are four buttons: '< Back', 'Next >', 'Finish', and 'Cancel'.

Click **Next** if you want to link participants to folder targets on the **DFS Link** page; otherwise continue with Step 3.

For more information about linking participants to folder targets, see [Linking a Namespace Folder to an Existing File Collaboration or Synchronization Job](#).

The screenshot shows the 'Create File Synchronization Job Wizard' window at the 'DFS Link' step. The left sidebar has 'DFS Link' selected. The main area has the text 'Link each participant's watch set to a folder target.' Below this are fields for 'Namespace: DG' and 'Folder:' with an 'Edit' button. A table titled 'Linked Participants and Folder Targets' has four columns: 'Agent', 'Directory', 'Folder Target', and 'Link Enabled'. The table contains three rows of data:

Agent	Directory	Folder Target	Link Enabled
DGWin16B	C:\64bit		
DGWin16C	C:\64bit		
DGWin16D	C:\64bit		

 To the right of the table are two buttons: 'Auto Select Targets' and 'Remove Selected Target'. At the bottom, there are four buttons: '< Back', 'Next >', 'Finish', and 'Cancel'.

3. Continue to [Step 7: Save Job](#).


Step 7: Save Job

You are now ready to save the job configuration.

1. If you are satisfied with your job configuration, click **Finish** to save your job. Otherwise, click the **Back** button and make any necessary changes.

Congratulations! You have created a File Synchronization job. A summary of the job configuration is displayed in the runtime view of the job.

See [Running and Managing a File Synchronization Job Running](#) for more information.



The screenshot displays the Peer Management Center Client interface. The main window shows the configuration summary for a File Synchronization job. The left sidebar contains a tree view of the system hierarchy, including Cloud Backup and Replication, DFS-N Management, File Collaboration, File Replication, and File Synchronization. The right pane shows the configuration details for the selected job, including the selected participants and configurations, DSU configuration, and general settings. The status of the job is shown as Stopped.

Configuration Summary

Selected Participants and Configurations

- DGWin16A C:\Data\Docs (Storage Platform: Windows Driver)
- DGWin16B C:\Data (Storage Platform: Windows Driver)
- DGWin16C C:\Data (Storage Platform: Windows Driver)

DSU Configuration

- Agent: DGWin16A
- Role: Master
- Agent: DGWin16B
- Role: Master
- Agent: DGWin16C
- Role: Edge
- Volume Policy: [DGWin16C - C:](#)
- Utilization Policy: [Dynamic Utilization Policy](#)
- Dynamic Rules: Enabled
- Pinning Filter: None
- Masters: [DGWin16A, DGWin16B]

General Settings

- Job Name: FS-3
- Job ID: 222
- Job Type: File Synchronization

Status: Stopped

Alerts

Received Date	Severity	Type	Name	Host	Message
01-15-2023 03:53:34	Info	Connection	Startup	DGWin16A	Agent Started
01-15-2023 03:53:31	Info	Heartbeat	Reconnect	DGWin16A	Connection status changed from Disconnected to Connected

Editing a File Synchronization Job

You can edit a File Synchronization job while it is running; however, any changes will not take effect until the job is restarted.

Overview

When you create a File Synchronization job, the **Create Job** wizard guides you through the process, presenting the most common options for configuration. When editing a job, you have access to all options, allowing you to fine-tune the job configuration. Options not included in the initial job creation include:

- [Application Support](#)
- [Conflict Resolution](#)
- [Delta Replication](#)
- [DFS-N Link](#)
- [File and Folder Filters](#)
- [File Locking](#)
- [General](#)
- [Scheduled Replication Filters](#)
- [SNMP Notifications](#)
- [Target Protection](#)
- [Tags](#)


You can edit multiple File Synchronization jobs simultaneously. For information about simultaneously editing multiple jobs, see [Editing Multiple Jobs](#).

Editing a Job

To edit a File Synchronization job:

1. Select the job in the **Jobs** view.
2. Right-click and select **Edit Job**.

The **Edit File Synchronization Configuration** dialog appears.



3. Select a configuration item in the navigation tree and make the desired changes:

- [Participants](#)
- [General](#)
- [File and Folder Filters](#)
- [Scheduled Replication Filters](#)
- [File Conflict Resolution](#)
- [Delta Replication](#)
- [File Metadata](#)
- [File Locking](#)
- [Application Support](#)
- [Target Protection](#)
- [Email Alerts](#)


This topic describes [adding](#) and [deleting](#) participants in a File Synchronization job.

Adding a Participant to a File Synchronization Job

To add a participant to a File Synchronization job:

1. Select the job in the **Jobs** view; right click and select **Edit Job**.


The **Edit File Synchronization** dialog opens; the **Participants** page displays the current job participants.



2. Click the **Add** button.

The **Add New Participant** wizard opens; the **Management Agent** page lists the Agents available to be added.

Tip: If the Agent you want is not listed, try restarting the Peer Agent Windows Service on that host. If it successfully connects to the Peer Management Broker, then the list is updated with that Agent.



The **Storage Information** page appears; the choices available depend on your selection in the **Storage Platform** page.

5. Enter the requested information.

[Windows File Server](#)

[NetApp ONTAP | Clustered Data ONTAP](#)

[NetApp Data ONTAP 7-Mode](#)

[Amazon FSxN](#)

[Dell PowerScale | EMC Isilon](#)

[Dell EMC Unity](#)

[Dell EMC Celerra | VNX | VNX 2](#)

[Nutanix Files](#)


6. Click **Next**.

The **Path** page appears.

The screenshot shows a window titled "Add New Participant" with a "Path" sub-header. A red error message states "You must enter a valid path." The left sidebar lists navigation options: Management Agent, Storage Platform, Storage Information, Path (selected), and Dynamic Storage Utilization. The main content area features an "Enter Path" text input field, a "Browse" button, and a "Seeding Target" checkbox. At the bottom, there are four buttons: "< Back", "Next >", "Finish", and "Cancel".

7. Browse to or enter the path to the [watch set](#).
8. (Optional) Select the **Seeding Target** checkbox, and then click **OK** in the dialog that appears.
9. Click **Next**.

The **Dynamic Storage Utilization** page appears.




10. (Optional) Select the **Enable Dynamic Storage Utilization** checkbox if you want this participant to be able to use Dynamic Storage Utilization; otherwise, click **Finish**.
11. If you enabled Dynamic Storage Utilization, follow the steps outlined in [Step 2: Dynamic Storage Utilization](#) in [Creating a File Synchronization Job](#).

For more information about DSU, see [Dynamic Storage Utilization](#) in [Advanced Topics](#).

12. Click **Finish** to complete the wizard.


The new participant appears in the **Participants** table.



Deleting a Participant from a File Synchronization Job

To delete a participant from a File Synchronization job:

1. In the **Edit File Synchronization** dialog, select the participant in the **Participants** table you want to remove from the job.




2. Click the **Delete** button
3. Click **OK** in the **Delete Confirmation** dialog.

The participant is removed from the **Participants** table.

Note: A File Synchronization job must have at least two participants, so if after deleting a participant, there is only a single participant, you must add another participant to the job.

To edit a participant:

1. In the **Edit File Synchronization** dialog, select the participant in the **Participants** table you want to edit.



2. Click **Edit**.

The **Edit Participant** dialog appears.

The image shows a screenshot of a software window titled "Edit Participant". The window has a standard Windows-style title bar with minimize, maximize, and close buttons. The main content area is divided into two panes. The left pane is titled "General" and contains a sub-section "Dynamic Storage Utilization". The right pane contains the following configuration options:

- Enabled:** A checked checkbox.
- Host:** A text input field containing "DGWin16D".
- Event Detector:** A dropdown menu currently set to "Windows". To the right of the dropdown is a link labeled "Edit Detector Configuration".
- Directory:** A text input field containing "C:\Users\debrag". To the right of the field is a "Browse" button.
- Seeding Target:** An unchecked checkbox.

At the bottom of the window, there is a navigation bar with four buttons: "< Back", "Next >", "Finish", and "Cancel". The "Finish" button is highlighted with a blue border.


The screenshot shows the 'Edit Participant' dialog box with the 'General' tab selected. The 'Dynamic Storage Utilization' section is expanded, showing the following settings:


- Enabled:**
- Host:** DGWin16A
- Event Detector:** Windows Driver (with a dropdown arrow and a link to [Edit Detector Configuration](#))
- Directory:** C:\Data\Docs (with a [Browse](#) button)
- Seeding Target:**

At the bottom of the dialog, there are four buttons: '< Back', 'Next >', 'Finish', and 'Cancel'. The 'Next >' button is highlighted with a blue border.

3. To enable or disable the agent, select or deselect the **Enabled** checkbox.
4. To change the directory/folder/share that is replicated, enter the path or browse to the new watch set in the **Directory** field.
5. If the storage device that the agent is managing has changed to a different storage platform, click **Edit Detector Configuration**, and then make the necessary modifications.
6. To change whether the participant is a seeding target, select or deselect the **Seeding Target** checkbox.
7. Click **Next** to edit Dynamic Storage Utilization options; otherwise, click **Finish**, and continue with Step 10.

If you clicked **Next**, the Dynamic Storage Utilization page appears.





8. If you enabled Dynamic Storage Utilization, follow the steps outlined in [Step 2: Dynamic Storage Utilization](#) in [Creating a File Synchronization Job](#).
9. Click **OK** to close the Edit wizard or select another configuration item to modify.

Master-Edge Assignment

This page appears only when DSU is enabled for the job.


Every edge participant must have at least one master participant assigned to it, so that DSU will know which master participants to use when reading or rehydrating a stub file on an edge participant. For each edge participant, you want to assign the master participant that is the fastest and closest to it. This will increase the speed of rehydrating a stub file.

It is highly recommended that you assign, if possible, more than one master participant to an edge participant, so that if one master participant is not available, another master participant is

able to provide the file content to the edge participant. You can set the order in which the master participants are consulted.

If you have only one edge participant and one master participant, the master participant is automatically assigned to the edge participant and listed in the Master Participants column. If you have multiple master participants, you need to explicitly assign master participants to each edge participant and then set the failover order.

1. Select an edge participant in the **Assignment** table.



2. Click the **Assign** button.

The **Assign Master Participants** dialog appears.

3. Select the master participants you want to assign to the edge participant.
4. (Optional) Change the failover order by selecting a master participant and using the **Move Up** and **Move Down** buttons.
5. Click **OK**.

The **Master Participants** column has been updated for that participant.

6. Repeat Steps 1-5 for each edge participant.
7. Click **OK**.

General

The **General** page in the **Edit File Synchronization Job** dialog presents miscellaneous settings pertaining to a File Synchronization job. You may want to consult with Peer Software's Technical Support team before modifying these values.

To modify these settings:

1. Enter the values recommended by Peer Software Support.

Option	Value
Job ID	209
Job Type	File Synchronization
Job Name	FS-2
Transfer Block Size (KB)	2048
Verify Block Checksums	<input checked="" type="checkbox"/>
Verify Full File Checksums	<input checked="" type="checkbox"/>
Enable Multipart Transfers	<input type="checkbox"/>
Synchronization Priority	2
Timeout (Seconds)	180
First Scan Mode	FOLDER_BY_FOLDER
Remove Filtered Files On Folder Delete	<input checked="" type="checkbox"/>
Require All Hosts At Start	<input type="checkbox"/>
Auto Start	<input checked="" type="checkbox"/>

Option	Description
Job ID	Unique, system-generated job identifier that cannot be edited.
Job Type	Identifies the job type. This cannot be modified.
Job Name	Name of this File Synchronization job. This name must be unique.
Transfer Block Size (KB)	The block size in Kilobytes used to transfer files to hosts. Larger sizes will yield faster transfers on fast networks but will consume more memory in the Peer Management Broker and Peer Agents .

Option	Description
Verify Block Checksums	If selected, each block sent will be checksummed at both the source and target(s) Agents.
Verify Full File Checksums	If selected, the entire file will be checksummed after it has been sent from the source to target Agents. If temp files are enabled, the checksum on the target will be calculated prior to renaming the temp file to the base file's name. If the checksums between source and target(s) do not match, the file will be sent to the retry engine to reattempt the transfer.
Enable Multipart Transfers	If selected, larger files will be broken into smaller chunks and these chunks will be sent over the wire in a parallel fashion. This feature will automatically throttle itself if many other transfers are also waiting to be processed.
Synchronization Priority	Use this to increase or decrease a job's file synchronization priority relative to other configured job priorities. Jobs are serviced in a round-robin fashion, and this number determines the maximum number of synchronization tasks that will be executed sequentially before yielding to another job.
Timeout (Seconds)	Number of seconds to wait for a response from any host before performing retry logic.
First Scan Mode	Determines which scan type will be used when the job is first started. For environments where most data is NOT seeded, the FOLDER_BY_FOLDER method will be best. For environments where most data is seeded, the BULK_CHECKSUM method will result in a faster first scan.
Remove Filtered Files On Folder Delete	If selected, then all child files on target hosts will be deleted when its parent folder is deleted on another source host. Otherwise, filtered files will be left intact on targets when a parent folder is deleted on another source host.
Require All Hosts At Start	If selected, requires all participating hosts to be online and available at the start of the File Synchronization job in order for the job to successfully start.


Option	Description
Auto Start	If selected, then this file synchronization session will automatically be started when the Peer Management Center Service is started.

- Click **OK** to close the Edit wizard or select another configuration item to modify.

File and Folder Filters


The **File and Folder Filters** page in the **Edit File Synchronization Job** dialog displays a list of [file and folder filters](#). A file or folder filter enables you to exclude and/or include files and folders from the job based on file type, extension, name, or directory path. Any file or folder that matches the filter is excluded or included from replication, depending on the filter's definition. By default, all files and folders selected in the **Source Paths** page will be replicated.

- Select the file and folder filters you want to apply to the job.



- If you want to create a new file or folder filter, modify an existing one, or update a filter, click **Edit File Filters**.

The **File and Folder Filters** dialog appears. You cannot edit predefined filters. See [File Filters](#) in the [Preferences](#) section for information about creating or modifying a file filter.



3. Select the **Include Files Without Extensions** checkbox if you want to replicate file that do not have extensions.


Note: Files without extensions are ignored during replication unless you select this checkbox.

4. Click **OK** to close the Edit wizard or select another configuration item to modify.

Scheduled Replication Filters


The **Scheduled Replication** page in the **Edit File Synchronization Job** dialog displays a list of [scheduled replication filters](#). A scheduled replication filter enables you to identify files and folders that you don't want replicated in real-time.

1. Select the scheduled replication filters you want to apply to the job.



2. If you want to create a new filter, modify an existing one, or update a filter, click **Edit File Scheduled Replication Filters**.

The **File and Folder Filters** dialog appears. You cannot edit predefined filters. See [Scheduled Replication Filters](#) in the [Preferences](#) section for information about creating or modifying a scheduled replication filter.



3. Click **OK** to close the Edit wizard or select another configuration item to modify.

Conflict Resolution

By default, any file conflicts that are encountered during the [initial synchronization process](#) are automatically resolved by Peer Management Center. Peer Management Center resolves the conflict by selecting the file with the most recent modification time. Conflicts that cannot be automatically resolved result in the files being quarantined. The **Conflict Resolution** page in the **Edit File Synchronization Job** allows you to select options for resolving file conflicts and quarantines.


However, if you want to resolve the conflicts yourself, you can contact Peer Software to enable manual resolution. With manual resolution, you can select the host with the correct version of the file.

For more information about the cause of file conflicts, see [Conflicts, Retries, and Quarantines](#).

To modify conflict resolution settings for the File Synchronization job:

1. In the **File Conflict Resolution** section, select the **Truncate Milliseconds** option if you want the millisecond value truncated from each time stamp when comparing the time stamps of a file on two or more hosts.

As some storage platforms and applications track milliseconds slightly differently, selecting this option will prevent subtle millisecond differences from causing an otherwise in-sync file to be replicated or quarantined.



2. Select the **Advanced File Conflict Resolution** options you want applied:

Option	Description
Quarantine Offline Version Conflicts	Select this option if you want Peer Management Center to quarantine a file that was updated in two or more locations while the collaboration session was not running. If it is not selected, the file with the most recent last modified time will be replicated to all other participants.
Enable Deletion of Quarantined Files	Select this option if you want Peer Management Center to process a delete event for a quarantined file. If it is not selected, the quarantined file is not deleted and remains quarantined.
Offline Delete Detection During Scan	Select this option (and enabled target protection), if you want any files or folders that were deleted while the job was stopped to be deleted from all participants when the job is restarted. If it is not selected, then the deleted file or folder is restored from a participant with the file or folder to any participant where it no longer exists.

3. Select an option for automatically resolving quarantines (this option is intended to be used in environments where a single file server is active for a job):

Option	Description
Disable Automatic Resolution of Quarantines	Select this option if you want to manually resolve quarantines. For more information, see Removing a File from Quarantine .
Last Modified Time	Select this option if you want quarantines automatically resolved by selecting the file with the latest modification time.
Use Master Host	Select this option if you want quarantines automatically resolved by selecting the file on the Master Host.

4. Click **OK** to close the Edit wizard or select another configuration item to modify.

Delta Replication

The **Delta Replication** page in the **Edit File Synchronization Job** dialog allows you to specify the delta-replication options to use for the selected File Synchronization job. Delta-level replication is a byte replication technology that enables block/byte level synchronization for a File Synchronization job. Through this feature, Peer Management Center is able to transmit only the bytes/blocks of a file that have changed instead of transferring the entire file. This results in much lower network bandwidth utilization, which can be an enormous benefit if you are transferring files across a slow WAN or VPN, as well as across a high-volume LAN.

Delta-level replication is enabled on a per File Synchronization job basis and generally affects all files in the [watch set](#). You will only benefit from delta-level replication for files that do not change much between file modifications, which includes most document editing programs.

To modify delta-level replication options:

1. Modify the following the fields as necessary.

The screenshot shows the 'Edit File Synchronization Job' dialog box with the 'Delta Replication' tab selected. The left sidebar contains a list of configuration categories: Participants, Master-Edge Assignment, General, File and Folder Filters, Scheduled Replication Filters, Conflict Resolution, Delta Replication (highlighted), File Metadata, File Locking, Application Support, Target Protection, Email Alerts, SNMP Notifications, Tags, and DFS-N Link. The main area is titled 'Delta Replication' and contains the following settings:

- Enable Delta-level Replication:
- Checksum Transfer Size (KB): 256
- Delta Block Transfer Size (KB): 1024
- Minimum File Size (KB): 2048
- Minimum File Size Percentage Target/Source: 0,30

Below these settings are two lists for excluded files:

- Excluded File Extensions:** A list box containing zip, jpg, jpeg, png, gif, tiff, tif, Z, tgz, gz, gzip, rar, 7z, bz, bz2, bzip2, and mp3. It has 'Add' and 'Delete' buttons.
- Excluded File Name Patterns:** An empty list box with 'Add' and 'Delete' buttons.

At the bottom right of the dialog are 'OK' and 'Cancel' buttons.

Field	Description
Enable Delta-Level Replication	Select to enable delta encoded file transfers which only sends the file blocks that are different between source and target(s). If this is disabled, the standard file copy method will be used to synchronize files.
Checksum Transfer Size (KB)	Enter the block in kilobytes used to transfer checksums from target to source at one time. Larger sizes will result in faster checksum transfer, but will consume more memory on the Peer Agents
Delta Block Transfer Size (KB)	Enter the block size in kilobytes used to transfer delta encoded data from source to target at one time. Larger sizes will result in faster overall file transfers but will consume more memory on the Peer Agents.
Minimum File Size (KB)	Enter the minimum size of files in kilobytes to perform delta encoding for. If a file is less than this size, then delta encoding will not be performed.
Minimum File Size Percentage Target/Source	Enter the minimum allowed file size difference between source and target, as a percentage, to perform delta encoding. If the target file size is less than this percentage of the source file size, then delta encoding will not be performed.
Excluded File Extensions	Enter a comma-separated list of file extension patterns to be excluded from delta encoding, e.g., zip, jpg, png. In general, compressed files should be excluded from delta encoding and the most popular compressed file formats are excluded by default.
Excluded File Name Patterns	Enter a list of file name patterns to be excluded from delta encoding. If a file name matches any pattern in this list, then it will be excluded from delta encoding transfers and a regular file transfer will be performed. See File and Folder Filters for more information on specifying wildcard expressions.

- Click **OK** to close the Edit wizard or select another configuration item to modify.

File Metadata

The **File Metadata** page in the **Edit File Synchronization Job** dialog allows you to modify your file metadata synchronization settings and provides some additional options not available when creating the job. See [File Metadata Synchronization](#) in [Advanced Topics](#) for more information about file metadata replication.

To enable file metadata synchronization:

1. Select when you want the metadata synchronized (you can select one or both options):
 - **Enable synchronizing NTFS security descriptors (ACLs) in real-time** - Select this option if you want the metadata replicated in real-time. If enabled, changes to the selected security descriptor components (Owner, DACL, and SACL) will be transferred to the target host file(s) as they occur.
 - **Enable synchronizing NTFS security descriptors (ACLs) with master host during initial scan** - Select this option if you want the metadata replicated during the initial scan. If enabled, changes to the selected security descriptor components (Owner, DACL, and SACL) will be synchronized during the initial scan.

The screenshot shows the 'Edit File Synchronization Job' dialog box with the 'File Metadata' tab selected. The left sidebar lists various settings categories, with 'File Metadata' highlighted. The main panel contains the following sections:

- Synchronize File Security Information**
 - Enable synchronizing file security information in real-time
 - Enable synchronizing file security information with master host during initial scan
 - Enable prevention of corrupt or blank Owner or ACLs on source or master host from being applied to any target host
- Synchronize Security and ACL Options**
 - Owner
 - DACL: Discretionary Access Control List
 - SACL: System Access Control List
- Metadata Conflict Resolution**
 - Select a master host for initial scan: [Dropdown menu]
 - Enable enhanced metadata conflict resolution
- File Reparse Point Synchronization**
 - Reparse Tag Name (numerical value only): [Text input field]
 - Reparse Master Host: [Dropdown menu]
- Alternate Data Streams Transfer**
 - Enable transfer of file Alternate Data Streams (ADS)

At the bottom right, there are 'OK' and 'Cancel' buttons.

2. Click **OK** in the message that appears after selecting a metadata option.
3. If you selected either of the first two options in the **Synchronize Security Descriptor Options** section, select the security descriptor components (Owner, DACL, and SACL) to be synchronized.

Note: To synchronize SACLs or Owner, the user that a [Peer Agent](#) service is run under on each participating host must have permission to read and write Owner and SACLs.

4. If you selected the option for metadata synchronization during the initial scan, select the host to be used as the [master host](#) in case of file metadata conflict.

If a master host is not selected, then no metadata synchronization will be performed during the initial scan. If one or more security descriptors do not match across participants during the initial scan, [conflict resolution](#) will use permissions from the designated master host as the winner. If the file does not exist on the designated master host, a winner will be randomly picked from the other participants.

5. This option is only available when both of the first two options in the **Synchronize Security Descriptor (ACLs)** section are enabled, and **Owner** is selected under **Synchronize Security Descriptor Options**.

If you select **Enable enhanced metadata conflict resolution**, this will prevent the Peer Agent service account from being assigned as the owner of that file or folder when a metadata conflict occurs and a file or folder is written to a target. If the Peer Agent service account were to be assigned as the owner, the user may not have permission to access the file or folder.

Note: The Peer Agent service account cannot be a local or system administrator. As described in [Peer Global File Service - Environmental Requirements](#), the Peer agent service account should be an actual user.

6. (Optional) Enter values for one or both file reparse point data synchronization options:
 - **Reparse Tag Name** - Enter a single numerical value. Must be either blank (if blank, reparse synchronization will be disabled) or greater than or equal to 0. The default for Symantec Enterprise Vault is 16. A value of 0 enables reparse point synchronization for all reparse file types. If you are unsure as to what value to use, then contact Peer Software technical support, or you can use a value of 0 if you are sure that you are only utilizing one vendor's reparse point functionality.
 - **Reparse Master Host** - Select a master host. If a master host is selected, then when the last modified times and file sizes match on all hosts, but the file reparse attribute differs (e.g., archived/offline versus unarchived on file server), then the file reparse data will be synchronized to match the file located on the master host. For Enterprise Vault, this should be the server where you run the archiving task on. If the value is left blank, then no reparse data synchronization will be performed, and the files will be left in their current state.

Note: Use this option only if you are utilizing archiving or hierarchical storage solutions that make use of NTFS file reparse points to access data in a remote location, such as Symantec's Enterprise Vault. Enabling this option allows synchronization of a file's reparse data, and not the actual offline content, to target hosts, and prevents the offline file from being recalled from the remote storage device.

7. (Optional) Select the **Enable transfer of file Alternate Data Stream (ADS)** checkbox.

If enabled, Alternate Data Streams (ADS) of updated files will be transferred to the corresponding files on target participants as a post process of the normal file synchronization.

Known limitation: ADS information is transferred only when a modification on the actual file itself is detected. ADS will not be compared between participants. The updated file's ADS will be applied to the corresponding files on target participants.

8. Click **OK** to close the Edit wizard or select another configuration item to modify.

File Locking

The **File Locking** page in the **Edit File Synchronization Job** dialog presents options for managing how source and target files are locked by Peer Management Center.

To modify file locking options:

1. Modify the fields in the **Source Snapshot Synchronization** section as needed:

The screenshot shows the 'Edit File Synchronization Job' dialog box with the 'File Locking' tab selected. The left sidebar lists various configuration options, with 'File Locking' highlighted. The main area is divided into two sections: 'Source Snapshot Synchronization' and 'Sync. On Save'. In the 'Source Snapshot Synchronization' section, 'Enable Source Snapshot Copy Sync.' is checked, 'Snapshot Copy Max File Size (MB)' is set to 512, 'Snapshot Copy File Extensions' is 'mdb,accdb,zip,psd,ai,indd', and 'Use Storage Snapshots' is unchecked. In the 'Sync. On Save' section, 'Enable Sync. On Save' is checked, 'Included File Extensions' is 'xls,xlsx,doc,docx,dwg,pptx,ppt', and 'Synchronization Delay (Seconds)' is set to 20. At the bottom right, there are 'OK' and 'Cancel' buttons.

Section	Option	Value
Source Snapshot Synchronization	Enable Source Snapshot Copy Sync.	<input checked="" type="checkbox"/>
	Snapshot Copy Max File Size (MB)	512
	Snapshot Copy File Extensions	mdb,accdb,zip,psd,ai,indd
	Use Storage Snapshots	<input type="checkbox"/>
Sync. On Save	Enable Sync. On Save	<input checked="" type="checkbox"/>
	Included File Extensions	xls,xlsx,doc,docx,dwg,pptx,ppt
	Synchronization Delay (Seconds)	20

Field	Description
Enable Source Snapshot Sync.	If enabled, a snapshot copy of the source file is created for files that meet the snapshot configuration criteria below, and this copy is used for synchronization purposes. In addition, no file handle is held on the source file except while making a copy of the file.
Snapshot Copy Max File Size (MB)	The maximum file size for which source snapshot synchronization is utilized.
Snapshot Copy File Extensions	A comma-separated list of file extensions for which source snapshot synchronization is utilized.
Use Storage Snapshots	If enabled, a storage volume snapshot is created and used for synchronization purposes. As a result, no file handle is held on the source file. The snapshot is created using either VSS or storage-platform specific snapshot technologies. This option is in addition to the Enable Source Snapshot Sync. option above and will only apply to files with pst, mdf, ldf, and ndf extensions.

2. Modify the fields in the **Sync. on Save** section as needed.

Field	Description
Enable Sync. On Save	If enabled, this feature allows supported file types to be synchronized after a user saves a file, rather than waiting for the file to close.
Included File Extensions	A comma-separated list of file extensions for which to enable the Sync. On Save feature.
Synchronization Delay (Seconds)	The number of seconds to wait after a file has been saved before initiating a synchronization of the file.


3. Click **OK**.

Application Support

When you create a File Synchronization job, you have the option of [selecting applications to be automatically optimized](#). When editing the job, you can modify your selections in the **Application Support** page in the **Edit File Synchronization Job** dialog.

To modify which applications are optimized:

1. Select the applications to be optimized.



2. Click **OK** to close the Edit wizard or select another configuration item to modify.


Target Protection

Target protection is used to protect files on [target hosts](#) by saving a backup copy before a file is either deleted or overwritten on the target host. If a job has target protection enabled, then whenever a file is deleted or modified on the source host but before the changes are propagated to the targets, a copy of the existing file on the target is moved to the Peer Management Center trash bin.

The trash bin is located in a hidden folder named **.pc-trash_bin** found in the root directory of the [watch set](#) of the target host. A backup file is placed in the same directory hierarchy location


as the source folder in the watch set within the recycle bin folder. If you need to restore a previous version of a file, you can copy the file from the trash bin into the corresponding location in the watch set and the changes will be propagated to all other collaboration hosts.

Target protection configuration is available by selecting **Target Protection** from the tree node within the Edit File Synchronization Configuration dialog.




Modify the fields as needed:

Field	Description
Enabled	Enables target protection.
# of Backup Files to Keep	The maximum number of backup copies of an individual file to keep in the trash bin before purging the oldest copy.
# of Days to Keep	The number of days to keep a backup archive copy around before deleting from disk. A value of 0 will disable purging any files from archive.
Trash Bin	The trash bin folder name located in the root directory of the watch set. This is a hidden folder and the name cannot be changed by the end user.




The newly added email alert appears in the **Email Alerts** table.



2. Click **OK** to close the Edit wizard or select another configuration item to modify.


Tags

The **Tags** page in the **Edit File Synchronization Jobs** dialog allows you to assign existing tags and categories to the selected job. This page is not available in [Multi-Job Editing](#) mode. For more information about tags, see [Tags](#) in the [Basic Concepts](#) section.



DFS-N Link

The **DFS-N** page in the **Edit File Synchronization Job** dialog presents options for linking a DFS namespace folder to this job. See [Linking a Namespace Folder to an Existing File Collaboration or Synchronization Job](#) for more information.



Editing Multiple Jobs


Peer Management Center supports multi-job editing, allowing you to quickly and effectively manipulate multiple File Synchronization jobs simultaneously. For example, you can use this feature to change a single configuration item such as **Auto Start** for any number of already configured jobs in one operation instead of having to change the item individually for each.

While this feature does cover most of the options available on a per-job basis, certain options are unavailable in multi-job edit mode, specifically ones tied to [participants](#). Configuration of participants must be performed on a per job basis.


To edit multiple jobs simultaneously:

1. Open Peer Management Center.
2. Select the jobs you want to edit in the **Jobs** view.
3. Right-click and select **Edit Jobs**.

For the most part, the original configuration dialog remains the same with a few minor differences depending on similarities between the selected File Synchronization jobs. A sample dialog is as follows:



In this dialog, any discrepancies between multiple selected jobs will generally be illustrated by a read-only text field with the caption **Multiple Values - Click to Edit**. Clicking this field will bring up a dialog similar to the following:



This dialog gives you the option of choosing a value that is already used by one or more selected File Synchronization jobs, in addition to the ability to use your own value. Notice that variances in the look and feel of this pop-up dialog above depend on the type

of information it is trying to represent (for example, text vs. a checkbox vs. a list of items).

Upon clicking OK, the read-only text field you originally clicked will be updated to reflect the new value. Any fields that have changed will be marked by a small caution sign. On saving in this multi-job edit dialog, the changed values will be applied to all selected jobs.

Note: Read all information on each configuration page carefully when using the multi-job edit dialog. A few pages operate in a slightly different manner than mentioned above. All of the necessary information is provided at the top of these pages in bold text.

Running and Managing a File Synchronization Job

The topics in this section provide some basic information about starting, stopping, and managing File Synchronization jobs:

- [Overview](#)
- [Starting a File Synchronization Job](#)
- [Starting a File Synchronization Job](#)
- [Auto-Restarting a File Synchronization Job](#)
- [Host Connectivity Issues](#)
- [Removing a File from Quarantine](#)
- [Manual Retries](#)

Overview

This topic describes:

- The [initialization process](#) for a File Synchronization job: What occurs the first time you run a File Synchronization job.
- The [initial synchronization process](#): How files are synchronized the first time you run a File Synchronization job.

The initialization process for a File Synchronization job consists of the following steps:

1. All participating hosts are contacted to make sure they are online and properly configured.
2. [Real-time event detection](#) is initialized on all participating hosts where file locks and changes will be propagated in real-time to all participating hosts. You can view real-time activity and history via the various Runtime views for the open job.
3. The [initial synchronization process](#) is started; all of the configured root folders on the participating hosts are scanned in the background, and a listing of all folders and files are sent back to the running job.
4. The background directory scan results are analyzed and directory structures compared to see which files are missing from which hosts. In addition, file conflict resolution is performed to decide which copy to use as the master for any detected file conflicts based on the [File Conflict Resolution](#) settings.
5. After the analysis is performed, all files that need to be synchronized are copied to the pertinent host(s).

Before you start a File Synchronization job for the first time, you need to decide how you would like the [initial synchronization](#) to be performed. During the initial synchronization process:

- The watch set is recursively scanned on all participating hosts.
- File conflict resolution is performed.
- Any files that require updating are synchronized with the most current copy of the file.

The two primary options are:

- Have the File Synchronization job perform the initial synchronization based on the [Conflict Resolution](#) settings.

- Pre-seed all [participating hosts](#) with the correct folder and file hierarchy for the configured root folders before starting the session.

If you have a large data set, we strongly recommend that you perform the initial synchronization manually by copying the data from a host with the most current copy to all other participating hosts. This needs to be done only once--before the first time that you run the File Synchronization job.

If you choose the first option, click the **Start** button to begin [synchronization session initialization](#). Otherwise, pre-seed each participating host with the necessary data, then click the **Start** button.

Starting a File Synchronization Job


Before starting a File Synchronization job for the first time, make sure that you have decided how you want the [initial synchronization](#) to be performed.

When running a File Synchronization job for the first time, you must manually start it. After the initial run, a job will automatically start, even when the Peer Management Center server is rebooted.

Note: You cannot run two jobs concurrently on the same volume if the [watch sets](#) contain an overlapping set of files and folders.


To manually start a job:

1. Choose one of three options:
 - Right-click the job name in the **Jobs** view.
 - Right-click the job name in the **Summary** tab of the **Collab, Sync, and Repl Summary** summary view, and then choose **Start** from the pop-up menu.
 - Open a job and then click the **Start/Stop** button to the left of the **Status** field in the bottom left corner of the job's runtime view (shown below).



- Click **Yes** in the confirmation dialog.

After the job initialization has completed, the job will run. Once the job starts, the icon next to the job name in the **Jobs** view changes from gray to green.



Stopping a File Synchronization Job

You can stop a File Synchronization job at any time by clicking the **Stop** button on the **Jobs** view toolbar. Doing this shuts down the real-time file event detection and close all running operations (e.g., file transfers).

Auto-Restarting a File Synchronization Job

Peer Management Center includes support for automatically restarting File Synchronization jobs that include [participating hosts](#) that have been disconnected, have reconnected, and are once again available.


After a host becomes unavailable and the [quorum](#) is lost on a running File Synchronization job, the job automatically stops running and enters a pending state, waiting for one or more hosts to become available again so that the quorum can be met. Once the quorum is met, the pending job will automatically be restarted, beginning with a scan of all root folders.

In a job where a host becomes unavailable but quorum is not lost, the remaining hosts will continue synchronizing. If the unavailable host becomes available once again, it is brought back into the running job and a background scan begins on all participating hosts, similar in fashion to the initial background scan at the start of a job.

You can enable all File Synchronization jobs to auto-restart. You can also disable auto-restart File Synchronization jobs on a per-job and host instance.

To enable all File Synchronization jobs to auto-restart:

1. Select **Preferences** from the **Window** menu.
2. Select **Collab, Sync, and Repl Summary** in the navigation tree.



3. Select the **Auto Reconnect when Host Becomes Available** checkbox.
4. Enter the minimum number of minutes to wait after an Agent reconnects before re-enabling it in any associated jobs in the **Minimum Host Reconnect Time** field.
5. Click **OK**.

Host Connectivity Issues

Peer Management Center is designed to be run in an environment where all [participating hosts](#) are highly available and on highly available networks. The two primary connectivity issues result from:

- [Unavailable Hosts](#)
- [Quorum Not Met](#)

Unavailable Hosts

If a host becomes unavailable while a File Synchronization job is running and is unreachable within the configured timeout period (specified in the job's [General settings](#)), it may be removed from synchronization. If no response is received while performing a file synchronization operation within the timeout period, Peer Management Center pings the host; if still no response, the host is taken out of the running session, a FATAL event is logged, and the **Participants** tab for the job is updated to indicate that the host has failed. In addition, if [email alerts](#) and/or [SNMP notifications](#) are configured and enabled for **Host Timeouts**, then the appropriate message(s) are sent.

If [auto-restart](#) not enabled, you must stop and start the File Synchronization job to bring any failed hosts back into the session. As a result, all root folders on all hosts will need to be scanned again to detect any inconsistencies. Therefore, if you are operating over a WAN with low bandwidth you will want to set the timeout to a higher value on each related job.

Quorum Not Met

For a File Synchronization job to run correctly, a quorum of available hosts must be met. Quorum is currently set to at least 2 hosts, and if quorum is not met, then the synchronization session is automatically be terminated. If [email alerts](#) and/or [SNMP notifications](#) are configured and enabled for **Session Aborts**, then the appropriate message(s) are sent.

Removing a File from Quarantine

Quarantines are a key feature of Peer Global File Service, used for resolving version conflicts. For more detailed information on how quarantines work, see [Conflicts, Retries, and Quarantines](#) in the [Advanced Topics](#) section.

You must explicitly remove a file from quarantine in order to have it participate in the synchronization session once again.

You may also choose to perform no action, in which case, the file is removed from the **Quarantines** table but none of the file versions are modified. Therefore, if the files are not currently in-sync, then the next time the file is modified, changes will be propagated to the other hosts. If an error occurs while removing the quarantine, then the **Status** field in the **Quarantines** table is updated to reflect the error.

To remove a file (or multiple files) from quarantine:

1. Open the job.
2. Open the **Quarantines** tab.
3. Select the file(s) in the Quarantines table.
4. Select the host with the correct version.
5. Click the **Release Conflict** button.

After doing this, all hosts are checked to make sure the file is not currently locked by anyone. If no locks are found, then locks are obtained on all versions of the file and the targets that are out-of-date are synchronized with the selected source host.

Manual Retries

Retries are a key feature of Peer Global File Service, used for automatically handling errors in the collaboration environment that would have otherwise led to a quarantine. For more detailed information on how retries work, see [Conflicts, Retries, and Quarantines](#) in the [Advanced Topics](#) section.

When a file is put in the retry list, it will be automatically retried based on the settings defined in [File Retries](#) in [Preferences](#). If need be, you can also manually force the retry of a file. This can be done from the Retries list of a specific File Synchronization job.

You may also choose to perform no action, in which case, the file is removed from the Retries list but none of the file versions are modified. Therefore, if the files are not currently in-sync, then the next time the file is modified, changes will be propagated to the other hosts. If an error occurs while forcing the retry, then the **Status** field in the **Retries** table is updated to reflect the error.

To manually force the retry of a file (or multiple files):

1. Select the file(s) in the **Retries** list.
2. Select the host with the correct version.
3. Click the **Release Conflict** button.

After doing this, all hosts are checked to make sure the file is not currently locked by anyone. If no locks are found, then locks are obtained on all versions of the file and the targets that are out-of-date are synchronized with the selected source host.

PeerSync Management Jobs

This section provides information about creating, editing, running, and managing a PeerSync Management job:

- [Creating a PeerSync Management Job](#)
- [Running and Managing a PeerSync Management Job](#)

Creating a PeerSync Management Job

The topics in this section provide some basic information about creating and editing PeerSync Management jobs.

Integrating Existing PeerSync Instances

To integrate existing PeerSync instances in Peer Management Center, follow the [step-by-step](#) instructions.

Creating and Deploying New PeerSync Instances

To create a new job and deploy the PeerSync installation to one or more hosts, click the **Create New** button in toolbar of Peer Management Center or select **New** from the **File** menu. A list of all installed job types will be displayed. Select the PeerSync Management option to open the PeerSync Management Configuration dialog. Go to the [Step-by-Step](#) instructions for more information.

When configuring Alerts, you will want to configure global settings like SMTP configuration, which is specific to Peer Management Center. Details on what and how to configure these global options can be found in the [Before You Create Your First PeerSync Management Job](#) section.

To edit the PeerSync Management configuration, right-click on the job in the Jobs view and select **Edit Job(s)**. Within the **Edit PeerSync Management Job** dialog, select the **Associated Profile** node from the left. For step-by-step instructions, see [Running and Managing PeerSync Management Jobs](#).

- [Integrating Existing PeerSync Instances](#)

- [Deploying New PeerSync Instances](#)

Before You Create Your First PeerSync Management Job

Before creating your first PeerSync Management job, we highly recommend preconfiguring a number of global options that can be applied to all PeerSync Management jobs.

The following configuration items are not always required, but highly recommended:

- [Email Configuration](#)
- [Email Alerts](#)

Overview

The Peer Management Center supports the concept of email alerts, where a single alert (consisting of a unique name, a selection of event types along with a list of email addresses) can be applied to multiple file synchronization jobs without requiring repeat entry for each job. When an email alert is applied to a job, an email is sent to all listed recipients anytime a selected event type is triggered by that job.

To manage email alerts, right-click any file synchronization job from the Jobs view and select the **Email Alerts** node from the **Monitoring** node. Click **Edit PeerSync Email Alerts**. The following screen represents the list of defined email alerts, along with buttons to add new ones and edit, copy, and remove existing ones.

Within this dialog, you can select specific event triggers on which an email will be generated and configure the list of email recipients of the alert(s). Event types are defined below.

Event Types

Session Abort	Enables sending an alert when a session is aborted because of lack of quorum due to one or more failed host agents.
Failed Events	Enables sending an alert when a failed event is received from the PeerSync machine.
Host Failure	Enables sending an alert when a host agent timeout occurs or a PeerSync service timeout occurs.

Failed State	Enables sending an alert when the state of the File Synchronization machine changes from Active to "Failed State" indicating that either a failed scan or failed event was detected in the latest set of synchronization stats.
---------------------	---

Integrating Existing PeerSync Instances

The topics in this section provide some basic information on how to integrate existing PeerSync instances within the Peer Management Center.

- [Requirements](#)
 - [How to Integrate Existing PeerSync Instances](#)
-
- PeerSync must be installed as a Service and running version 9.3.0 or newer.
 - Peer Agent must be installed on the PeerSync machine and connected to the Peer Management Center.
-
1. Open the profile on the PeerSync machine with the PeerSync Profiler.
 2. Add the argument /LZTAI in Options/Command section.
 3. Save the profile.
 4. Restart the PeerSync Service.
 5. Install the Peer Agent.
 6. Start the Peer Agent.

Once the Peer Agent is started and connected to the Peer Management Center, PeerSync will be auto-detected, and a Peer Management Center file synchronization job will be generated with the name of the machine.

Optionally you can edit the job and add [email alerts](#) and save and restart the File Synchronization job for changes to take effect.

Deploying New PeerSync Instances

The topics in this section provide basic information on how to integrate existing PeerSync instances within the Peer Management Center:

- [Requirements](#)
- [How To](#)

- Peer Agent must be installed on the machine where PeerSync will be deployed to.
- It is recommended to run the Agent under a domain admin account or account with enough rights to modify registry and service configuration.


The topics in this section provide step-by-step instructions on how to create and deploy new PeerSync instances through Peer Management Center.

- [Step 1: General Information](#)
- [Step 2: PeerSync Profile](#)
- [Step 3: Jobs Configuration List](#)
- [Step 4: Installation Settings](#)

Step 1: General Information

Create a new PeerSync Management job by clicking the **Create New** button in the toolbar of the Peer Management Center, or by selecting the **New** from the **File** menu. A list of all available job types will be displayed. Selecting the **PeerSync Management** option will open the PeerSync Management **Configuration** dialog.

The first page of configuration will be for general information such as Host Participants and Job name tag.



The screenshot shows the 'File Synchronization Configuration' dialog box, specifically the '1 of 4 - General Information' step. The dialog has a title bar with standard window controls. Below the title bar, the text 'Generic information on this PeerSync configuration' is displayed. A text box labeled 'Name: [COMPUTERNAME] - EMEA_Region' is shown, with a callout bubble pointing to it that says 'Job Name Tag'. Below this is a section titled 'Available' containing a table with columns 'Host' and 'Computer Description'. The first row of the 'Available' table has 'Win12x64a' in the 'Host' column. Below the 'Available' table are 'Add' and 'Remove' buttons. Below that is a section titled 'Selected' containing an empty table with columns 'Host' and 'Computer Description'. At the bottom of the dialog are four buttons: '< Back', 'Next >', 'Finish', and 'Cancel'.

Host	Computer Description
Win12x64a	

Host	Computer Description

1. The job name will default to the computer name of the host participant. If you wish to group your computers, you can optionally add a name tag in the text box next to the job name (e.g., East Coast, EMEA, Region2). This will help in filtering machines by their given tag.

2. A list of all available hosts that have not yet been configured with a PeerSync installation, will appear in the **Available** table on the top of the page. Available hosts are any host with a Peer Agent installed that has successfully connected to the configured Peer Management Center Broker. The name that will be displayed is the computer name of the server that the Peer Agent is running on. If a particular host is not displayed in the list, then try restarting the Peer Agent Windows Service on that host, and if it successfully connects to Peer Management Center Broker, then the list will be updated with the computer name of that host.

Note: Computer Description is defined through Windows on a per-computer basis.

3. Select one or more hosts from the **Available** table and click the **Add** button to add the hosts to the **Selected** table. These are the hosts you wish to deploy the PeerSync configuration and installation to.

Step 2: PeerSync Profile

In the second page, choose a preconfigured profile from the available templates, or browse to load a PeerSync profile you may have configured through the PeerSync Profiler and saved as a .snc file on this system.

You may also choose to start from scratch by choosing **Other** from the drop-down menu.

Enter or update the **Profile Description** and **Performance Options**.

File Synchronization Configuration

2 of 4 - PeerSync profile
Profile Configuration

Pre-Defined Profile

Profile Description

Performance Options

Maximum number of Job Threads

Maximum number of Copy Threads

< Back Next > Finish Cancel

Profile Description	A textual description of the current profile.
Maximum number of Job Threads	Maximum number of job scans that can run parallel to one another.
Maximum number of Copy Threads	Maximum number of events that can be processed parallel to one another.

Step 4: Installation Settings

In the last page of the PeerSync Management Configuration wizard, enter the installation settings for this PeerSync instance.

Predefined Settings

A list of previously used installation settings with the Name given at the time of use.

Note: If the installation settings have the same path, service user name, license password, and installation exe, a new Installation record will not be created, regardless of whether a new name has been given to the Installation Settings.

Install Path	Path where PeerSync will be installed. When using the %ProgramFiles % variable, PeerSync will install in the x86 Program Files directory for 64-bit systems, otherwise it will install in the Program Files base directory.
Existing Exe	A list of PeerSync executables available in the template folder or used in a past installation. This is the PeerSync executable that will be used to install PeerSync.
License User Name	License information provided by Peer Software. Cut and paste the User Name section in this field.
License Company	License information provided by Peer Software. Cut and paste the Company section in this field.
License Options	License information provided by Peer Software. Cut and paste the Options section in this field.
License Password	License information provided by Peer Software. Cut and paste the Password section in this field.
Service Logon User*	This is the Service account User ID used to run the PeerSync Service (DOMAIN\USER). Note: This account must be valid on all included participants for this File Synchronization Configuration.
Service Password	PeerSync Windows Service account password.

***Note:** When using a service account that has not been granted to run as a service on the machine, PeerSync will fail to start return the following Global Alert to the Peer Management Center. This will indicate that PeerSync could not start, and you will have to log on to that machine and confirm the credentials to grant access to that account to run as a service.

Hub Alert Details ▼

Received at: 09-30-2015 13:08:52

Severity: Warning

Category: Global Resource

Host Name: Peer Management Center

Locally Generated at: 09-30-2015 13:08:52

Name: Process PeerSyncEvent

Message: pe..... Last Event=PeerSyncEvent [host=Win12x64a, eventType=SERVICE_CMD, description=The service did not start due to a logon failure., exception=null, errorCode=0, coordinationId=null, eventId=66, properties = {}] : The service did not start due to a logon failure.

Click outside of popup to close

Once the Configuration Settings have completed, click **Finish** and the installation configuration will be sent to the selected Participants.

A File Synchronization job will be auto created for each Participant and set to be in a Pending Installation state. Once the installation completes and PeerSync reports to the Peer Management Center, the state will change to Running/Active.

Synchronization Summary ✕

Runtime Summary View (auto-update enabled)

Filter by: Actions ☑ Enable Auto

Name	Overall Status	Backup Status	Failed Scans	Failed Events	Messages	Pending Events	Pending Retries	Checked	Updated
Composite4a[East_Coast]	PeerSync Service Not Avail...	N/A	0	0	0	No Pending Items	0	5738	5389
DDWin12R2a[EastCoast]	Running	Normal	0	0	8	No Pending Items	0	258	0
DDWin12R2b[WestCoast]	Running - Failed State	Target Folders ...	1	3					
VMSRV2008K32[Asia]	Stopped [Pending Installat...	N/A	0	0	0	No Pending Items	0	26880	0
Win12x64a[EMEA_Region]	Running	Normal	0	0	0	No Pending Items	0	26880	0


Install PeerSync - □ ✕

Scheduling PeerSync Operation Task

Always run in background

Logging and Alerts

Use the following dialog to enable or disable logging and alerts, including specifying event types to log.




Stats Update	Log when PeerSync Stats are received (This could generate large amount of Log Entries).
Profile Update	Log whenever the PeerSync Profile configuration is updated.
Profile Distribution	Log when the PeerSync Profile is distributed to one or more hosts.

PeerSync Service Start	Log when a user initiates a PeerSync Service Start.
PeerSync Service Stop	Log when a user initiates a PeerSync Service Stop.
Failed Events Reprocess	Log when a user initiates a Failed Event Reprocess.
Restart Detected	Log when Peer Management Center detects that the PeerSync service has been restarted by comparing known Session Id with received one.

Email Alerts

Email alerts configuration is available by selecting **Email Alerts** from the tree node within the PeerSync Management Configuration dialog.

Email alerts are configured at a global level, then applied to individual jobs. The following screen shows how this is accomplished.



To enable email alerts for this job, select an email alert from the drop-down list. To disable, select **None - Disabled**.

Running and Managing a PeerSync Management Job

This section includes topics for managing your PeerSync Management Jobs.

- [Starting and Stopping](#)
- [Synchronization Summary View](#)
- [Synchronization Dashboard Summary View](#)

- [PeerSync Profile Management](#)
- [PeerSync Service Management](#)
- [Runtime Job Views](#)
- [Upgrade/Reprocess Installation](#)

Starting and Stopping

Starting a PeerSync Management Job


A PeerSync Management job is auto-started as soon as the Agent connects to the Peer Management Center; normally you will not need to manually start the job.

Click the **Start** button to begin the session.

Stopping a PeerSync Management Job

You can stop a PeerSync Management job at any time by pressing the **Stop** button. Doing this will shut down the monitoring of the specific PeerSync host(s).

Note: If the job is stopped and the participating host is still running an instance of the PeerSync software, the job will auto start the next time that host agent is restarted or a Reconnect is detected.



PeerSync Management Summary

The **Synchronization Summary** view aggregates critical status and statistical information from all configured PeerSync Management jobs in a single table view. It is automatically displayed when the Peer Management Center client is started and can be opened at any other time by double-clicking on the **PeerSync Management** parent tree node in the Job's View or by clicking the **View Runtime Summary** icon in the toolbar of the Jobs view.

Information in this view can be sorted and filtered. Operations such as starting, stopping, and editing multiple jobs at once are available, in addition to the ability to clear Monitoring Alerts, Start PeerSync, Stop PeerSync, Reprocess Failed Events, Request Support Info File and Reprocess/Upgrade Installation.

The screenshot shows a window titled "Synchronization Summary" with a sub-header "Runtime Summary View (auto-update enabled)". It features a "Filter by:" dropdown, an "Actions" dropdown, and a checkbox for "Enable Auto-Update" with a "Refresh" button set to "10 seconds". The main content is a table with the following data:

Name	Overall Status	Backup Status	Failed Scans	Failed Events	Messages	Pending Events	Pending Retries	Checked
Composite4a	Running - Failed State	Target Folder i...	1	0	0	No Pending It...	0	0
DDWin12R2a[East...	PeerSync Service No...	Normal	0	0	0	No Pending It...	0	484
DDWin12R2b[Wes...	Running	Normal	0	0	2	No Pending It...	0	2895

Unlike other views within the Peer Management Center, the **Synchronization Summary** view is not updated in real-time. This is done for performance reasons. Instead, the table can be set to automatically update itself every few seconds. Clicking **Enable Auto-Update** enables this functionality, while the refresh interval (in seconds) can be set right beside the checkbox. Additional columns can be added to and removed from the table from the right-click context menu.

Double-clicking any item in the table will automatically open the selected PeerSync Management job in a tab within the **Runtime Summary** view, allowing you to drill down and view specific information about that single job. Items in the summary table can be filtered by job name, overall status, activity state and host participant name.


Selecting one or more items in the table, then right-clicking will bring up a context menu of available actions that can be performed on the selected jobs. The actions that are unique to this table are as follows:

Clear Monitoring Alerts	Clears all monitoring alerts for the selected jobs. This can be performed while a job is running.
--------------------------------	---

PeerSync multi-job global actions:

Clear Monitoring Alerts

Clears all monitoring alerts for the selected jobs. This can be performed while a job is running.



Start PeerSync	Send a Start command to the PeerSync service instance running on the selected jobs' participant. This can be performed while the associated File Synchronization Job is running.
Stop PeerSync	Send a Stop command to the PeerSync service instance running on the selected jobs' participant. This can be performed while the associated File Synchronization Job is running.
Reprocess Failed Events	Send a Reprocess Failed Events command to the PeerSync instance running on the selected jobs' participant. This can be performed while the associated File Synchronization Job is running.
Request Support Info File	Send a request to collect the Support info File from the PeerSync instance running on the selected jobs' participant. This can be performed while the associated File Synchronization Job is running.

Clear Monitoring Alerts	Clears all monitoring alerts for the selected jobs. This can be performed while a job is running.
Reprocess/Upgrade Installation	Deploy an upgrade or reprocess an existing installation for the selected File Synchronization Job(s). Upgrade/Reprocess Installation

Clicking the **Actions** table menu provides the following options:

Refresh View	Refresh all information provided in the table.
Copy All Filtered Statistics	Copy detailed information to the system clipboard for all items current displayed in the table, taking any filters into account. This information can then be pasted into a text editor.
Export Entire Table to File	Dump the entire contents of the table to a text file that can be viewed in any text editor.

PeerSync Management Dashboard Summary View

The **PeerSync Management Dashboard Summary** view is a view that displays metrics and key performance indicators from all running PeerSync Management jobs. It is automatically displayed when the Peer Management Center client is started and can be opened at any other time by selecting **View Dashboard** from the **Window** menu or by clicking the **View Dashboard** icon in the Peer Management Center toolbar.

The screenshot displays a web-based dashboard with the following sections:

- Dashboard Summary View:** Includes a refresh interval of 10 seconds and an 'Auto-Update' checkbox.
- Synchronization Summary View:**
 - File Synchronization:** Shows 3 PeerSync Monitoring Not Running! and Active Synchronization Statistics.

Not Running	0	Failed Scans:	0	Updated:	0 (0 bytes)
Running in a Failed State	0	Failed Events:	0	Added:	0 (0 bytes)
Not in a Synchronized State	0	Messages:	0	Deleted:	0 (0 bytes)
In a Current State	0	Pending Events:	0	Bytes Transferred:	0 bytes
PeerSync Monitoring Not Running	3	Pending Retries:	0		
- Agent Summary View:**
 - Agents:** Shows All Connected and Top Connectivity Offenders.

Disconnected	0		
Connected	12		
Needing Upgrade	0		

The Dashboard is not updated in real-time. This is done for performance reasons. Instead, the table can be set to automatically update itself every few seconds. Enabling the **Auto-Update** option will enable this functionality, while the **Refresh** interval (in seconds) can be set right beside the checkbox.

Entries in the first column of the **PeerSync Management Job** and **Agents** categories can be double-clicked, which will take the user to a filtered Runtime view of the selected item for additional details.

Managing the PeerSync Profile

The topics in this section provide some basic information about PeerSync Profile Management:

- [Updating the Profile Configuration](#)
- [Importing an Existing Profile](#)
- [Distributing a Profile](#)

This topic provides information on how to update a PeerSync profile from the Peer Management Center.

If using the Peer Management Center to manage the PeerSync instances, we recommend making changes through the Peer Management Center. If changes are made directly on the PeerSync machine, they should be [imported](#) in the Peer Management Center job manually to keep the Peer Management Center PeerSync Configuration in sync.

How to Update a PeerSync Profile through Peer Management Center

- From the **PeerSync Management Summary** runtime view (double-click the **PeerSync Management jobs** node from the left), right-click the machine you wish to modify the profile for and choose **Edit Configuration(s)**. Alternatively, you can right-click the machine job from the left menu under the **PeerSync Management** node and choose **Edit Configuration(s)**.
- You can update the Profile by importing an updated Profile through the **Import** button in the **Associated Profile** page, or manually update the configuration through **Jobs and/or Global Settings** section.
- If you wish to update the profile outside of the Peer Management Center, export the existing configuration using the **Export** button in **Associated Profile** page. Make your changes through the PeerSync Profiler and import the updated Profile back into Peer Management Center through the **Import** button.
- After having made your entire configuration changes either through Peer Management Center or by [importing](#) the updated Profile, choose **OK** and close the **Edit Configuration** dialog.

Your configuration changes will not reach the PeerSync machine until they are [distributed](#). The updated profile will become active on the machine after the PeerSync service has been restarted.

- [Import Existing Profile](#)
- [Edit/Configure Jobs](#)
- [Edit Global Settings](#)
- [Distribute Profile](#)


Importing an Existing Profile

In the **Associated Profile** section of the **PeerSync Management Configuration** dialog, you can update the configured profile with one you have saved and configured outside of the Peer Management Center.

Note: If making changes outside of the Peer Management Center, we recommend exporting the profile from the Peer Management Center (by clicking the **Export** button), making necessary changes outside of the Peer Management Center, and finally importing the profile back into the Peer Management Center.

Click the **Import** button on the right of the dialog to import the profile. To propagate this new updated profile, close the **PeerSync Management** dialog, reopen it, and then distribute to the PeerSync host through the [Distribute](#) button.


The screenshot shows a window titled "File Synchronization Configuration [DDWin12R2a]". On the left is a navigation tree with the following items: Monitoring (expanded), Logging and Alerts, Email Alerts, Associated Profile (selected), Jobs, Global Settings, and Associated Installation. The main area is titled "Associated Profile" and contains four text boxes: "Description:" with the value "Backup", "File Name:" with "DDWin12R2a.snc", "Last Updated On:" with "Aug 24, 2015 10:47:38 PM", and "Current State:" with "Active". To the right of these boxes are three buttons: "Export", "Import", and "Distribute". Below the text boxes, it says "Total number of jobs configured in this profile is 1". At the bottom right of the dialog are "OK" and "Cancel" buttons.



Once a job type has been selected, click **Apply** and complete the PeerSync Job Configuration wizard to complete the job configuration and add the job to the profile.

Edit Existing Job

To edit an existing job, select the job in the **Jobs** view, and then click the **Edit** button on the right. The **PeerSync Job Properties** dialog will open with all available settings grouped by category in the navigation tree.



Enable/Disable Job

To enable or disable a job, click the checkbox to the left of the job name in the **Jobs** view.

To save these changes, click **OK** on the bottom right of the **PeerSync Management Configuration** dialog.

Copy Job

You can copy an existing job by selecting the job from the **Jobs** view and clicking the **Copy** button on the right. The **PeerSync Job Properties** dialog will open, allowing you to make changes to the copied job.

Note: You must make at least one change to the job settings. If the job settings remain identical, it will not be saved after the **OK** button is clicked.

Remove Job

To remove jobs from the PeerSync Configuration, select one job from the **Jobs** view, click the **Remove** button on the right. Repeat this for any additional jobs you wish to remove.

Editing Global Settings

In the **Global Settings** of the **PeerSync Management Configuration** dialog, you can make changes to settings that apply to all PeerSync Jobs within the profile.

File Synchronization Configuration [DDWin12R2a]

Monitoring
Logging and Alerts
Email Alerts
Associated Profile
Jobs
Global Settings
Associated Installation

Global Settings

Recovery Options

Retry open/inaccessible files 1 times

Retry Failed Connection every 1 minutes

Performance Options

Maximum number of Job Threads 5

Maximum number of File Threads 10

Use Enhanced Event Processing

Reconnect Options Run a Scan on reconnect

Application Priority Selection Normal

OK Cancel

Recovery Options	These changes will update how we retry failed or inaccessible files as well as the interval in which we retry Failed Connections.
Performance Options	These settings allow you to change the maximum number of job scans that can run parallel to one another and the maximum number of events that can be processed parallel to one another.

Reconnect Options	This setting allows you to choose how PeerSync handles a re-established connection. Options are to Run a Scan on reconnect or Store missed events and process on reconnect .
Application Priority Selection	This setting enables to select the priority level you want PeerSync to have.

Distributing a Profile


This topic covers information on how to distribute changes to the PeerSync profile from the Peer Management Center

To distribute the PeerSync profile changes, right-click the PeerSync Management job from the **Jobs** view, and then click **Edit Configuration**.

In the **PeerSync Management Configuration** screen, click the **Associated Profile** node, and then click the **Distribute** button.

In the event that one or more of your jobs are configured to use a ByteReplicator Relay Server (usually used in NetApp source environments), the Distribute Profile process will also distribute your relay Server configurations by compiling all unique target Hosts and relay servers into a *%profilename%.pls* file. This file will be distributed to the PeerSync machine alongside the profile.

Note: This action will distribute the profile to the machine and attempt to stop and start PeerSync Service to commit those changes. If you do not wish to restart the PeerSync service, wait to distribute the profile until you are ready to have the service restart.



Managing the PeerSync Service

The following PeerSync service management actions are available from the [Synchronization Summary view](#) and the [Summary view](#) for a specific PeerSync Management job.


Starting the PeerSync Service

To start the PeerSync service associated with any PeerSync Management job, right-click the view and choose **Start PeerSync**.

Stopping the PeerSync Service

To stop the PeerSync service associated with any PeerSync Management job, right-click the view and choose **Stop PeerSync**.

Note: The associated PeerSync Management job must be running in order to successfully perform this action.



For information on the additional PeerSync multi-job global actions, see [Synchronization Summary View](#).

Runtime Job Views

Double-clicking on the PeerSync Management job from the [Synchronization Summary view](#) will open the job-specific runtime views.

- [Summary View](#)
- [Failed Events View](#)
- [Monitoring Log View](#)
- [Alerts View](#)
- [Participants View](#)
- [Configuration View](#)

Summary ! Failed Events (2)
Monitoring Log ! Alerts (16)
Participants (1)
Configuration

Summary View

Actions ▼

Monitoring Peerlet Session	Failed	Started: 9/30/15 12:23 PM
Stats Timestamp		9/30/2015 1:56:51 PM
Stats State	Failed	
PeerSync Running Info		Started: 9/30/2015 12:09:46 PM
Mode	Automatic and Real-Ti...	
Status	Target Folders are Not A...	
PeerSync Real Time Stats		
Real Time Events	128	
Real Time Events Peak	53.318 events/minute	
Real Time Events In Process	0	
Real Time Events Average	1.195 events/minute	

Overview
PeerSync Jobs Stats
Added
Updated
Deleted
Messages

PeerSync Overall Status					
Checked	260	Updated	0	Current Event Status	Real-time Monitoring (Failed Scans: 1) (Failed Events...
Excluded	0	Added	0	Pending Event Status	No Pending Items
Messages	11	Deleted	0	Bytes Transferred	0 bytes
					Elapsed Time: 01:47:08 Xfer Rate: N/A

When double-clicking a PeerSync Management job, the default selected tab will be the **Summary** tab. This view will show information received by the PeerSync machine on the status of the PeerSync Management job.

Information found in this view is global to the PeerSync profile. To see PeerSync job-specific statistics, click the [PeerSync Jobs Stats](#) tab.

Information on this view is received whenever the information changes on the PeerSync machine, normally every 1 minute or so. To auto-refresh this view with the latest data, click **Enable Auto-Update** on the top right of the view, and choose a Refresh cycle. The cycle is the

not the cycle for receiving the information, just to refresh the view with the latest information received by PeerSync.

The screenshot displays the PeerSync monitoring interface. At the top, there are navigation tabs: Summary (selected), Failed Events (2), Monitoring Log, Alerts (16), Participants (1), and Configuration. Below the tabs, there is a 'Summary View' section with an 'Actions' dropdown menu. The main content area is divided into several sections:


- Monitoring Peerlet Session:** Shows a 'Failed' status. Stats Timestamp is 9/30/2015 1:56:51 PM, and Stats State is 'Failed'. Started: 9/30/15 12:23 PM.
- PeerSync Running Info:** Shows 'Automatic and Real-Ti...' mode and 'Target Folders are Not A...' status. Started: 9/30/2015 12:09:46 PM.
- PeerSync Real Time Stats:** Shows Real Time Events (128), Real Time Events Peak (53.318 events/minute), Real Time Events In Process (0), and Real Time Events Average (1.195 events/minute).

Below these sections, there are tabs for 'Overview', 'PeerSync Jobs Stats', 'Added', 'Updated', 'Deleted', and 'Messages'. The 'Overview' tab is selected, showing the 'PeerSync Overall Status' table:

Category	Count	Action	Count	Event Status	Details
Checked	260	Updated	0	Current Event Status	Real-time Monitoring (Failed Scans: 1) (Failed Events...
Excluded	0	Added	0	Pending Event Status	No Pending Items
Messages	11	Deleted	0	Bytes Transferred	0 bytes

At the bottom of the overview section, it shows 'Elapsed Time: 01:47:08 Xfer Rate: N/A'.

On this page, you can right-click to display the PeerSync **Actions** menu:



On the bottom half of the page, you will find a set of tabs showing more granular information regarding this PeerSync session.

- [PeerSync Jobs Stats](#)
- [Added Files](#)
- [Updated Files](#)
- [Deleted Files](#)
- [Messages](#)

PeerSync Jobs Stats

When clicking the **PeerSync Jobs Stats** view, a request goes out to the PeerSync machine to request job-specific statistics and return them to the Peer Management Center to be displayed. These statistics can be requested only if PeerSync is running on that machine and only if the PeerSync Management job is started on the Peer Management Center.

When the statistics are received, the view is updated with the job-specific statistics and the caption on the top of the view will show the date and time the list was last updated.

By right-clicking on the info table, you can choose to hide or show columns.

Job Na...	Source	Target	Last Scan (Status: Durati...	Xfer Rate	Event Averages	Upda...	Added	Delet...	Mess...	Fail...	Status
● Data ...	c:\source\	c:\target\	9/30/2015 12:09:47 PM (...)	N/A	0.00 per min (0...	0 (0 ...	0 (0 ...	0 (0 ...	0	0	Normal
● Data2...	c:\source2\	c:\target2\	9/30/2015 12:09:47 PM (...)	N/A	0.00 per min (0...	0 (0 ...	0 (0 ...	0 (0 ...	0	0	Normal
● Data ...	c:\source3\	\\backupserve...	N/A	N/A	0.00 per min (0...	0 (0 ...	0 (0 ...	0 (0 ...	11	3	Target Not Available (Scan on Re...
All Jobs	-----	-----	N/A	N/A	0.00 per min (0...	0 (0 ...	0 (0 ...	0 (0 ...	11	3	Target Folders are Not Available f...

Added Files

When clicking the **Added** tab, a request goes out to the PeerSync machine to request a list of latest added files and return it to the Peer Management Center to be displayed. This list can be requested only if PeerSync is running on that machine and only if the PeerSync Management job is started on the Peer Management Center.

When the list is received, the view is updated with the latest added events processed by PeerSync, and the caption on the top of the view will show the date and time the list was last updated.

By right-clicking on the info table, you can choose to hide or show columns.

This information in this table can be filtered by Path or by Job Name.

Overview | PeerSync Jobs Stats | **Added** | Updated | Deleted | Messages

Added Log

0 errors, 0 warnings, 100 others | Filter by:

Date	Type	Path	Comments	Message	Job Name	File Size	Modified Time
09-15-2015 17:0...	Event	c:\target\FILE42.TXT	Added [Attrib...		Data Backup	2.3 KB	09-15-2015 17:01:27
09-15-2015 17:0...	Event	c:\target\FILE44.TXT	Added [Attrib...		Data Backup	1.9 KB	09-15-2015 17:01:27
09-15-2015 17:0...	Event	c:\target\FILE43.TXT	Added [Attrib...		Data Backup	4.0 KB	09-15-2015 17:01:27
09-15-2015 17:0...	Event	c:\target\FILE45.TXT	Added [Attrib...		Data Backup	4.0 KB	09-15-2015 17:01:27
09-15-2015 17:0...	Event	c:\target\FILE47.TXT	Added [Attrib...		Data Backup	1.7 KB	09-15-2015 17:01:27
09-15-2015 17:0...	Event	c:\target\FILE46.TXT	Added [Attrib...		Data Backup	1.6 KB	09-15-2015 17:01:27
09-15-2015 17:0...	Event	c:\target\FILE48.TXT	Added [Attrib...		Data Backup	3.2 KB	09-15-2015 17:01:27
09-15-2015 17:0...	Event	c:\target\FILE41.TXT	Added [Attrib...		Data Backup	3.3 KB	09-15-2015 17:01:27
09-15-2015 17:0...	Event	c:\target\FILE50.TXT	Added [Attrib...		Data Backup	1.4 KB	09-15-2015 17:01:27
09-15-2015 17:0...	Event	c:\target\FILE49.TXT	Added [Attrib...		Data Backup	2.7 KB	09-15-2015 17:01:27
09-15-2015 17:0...	Event	c:\target\FILE27.TXT	Added [Attrib...		Data Backup	2.1 KB	09-15-2015 17:01:26
09-15-2015 17:0...	Event	c:\target\FILE28.TXT	Added [Attrib...		Data Backup	3.9 KB	09-15-2015 17:01:26
09-15-2015 17:0...	Event	c:\target\FILE29.TXT	Added [Attrib...		Data Backup	2.6 KB	09-15-2015 17:01:26
09-15-2015 17:0...	Event	c:\target\FILE30.TXT	Added [Attrib...		Data Backup	3.9 KB	09-15-2015 17:01:26
09-15-2015 17:0...	Event	c:\target\FILE31.TXT	Added [Attrib...		Data Backup	2.8 KB	09-15-2015 17:01:26
09-15-2015 17:0...	Event	c:\target\FILE32.TXT	Added [Attrib...		Data Backup	1.9 KB	09-15-2015 17:01:26
09-15-2015 17:0...	Event	c:\target\FILE33.TXT	Added [Attrib...		Data Backup	1.9 KB	09-15-2015 17:01:26

Updated Files

When clicking the **Updated** tab, a request goes out to the PeerSync machine to request a list of latest updated files and return it to the Peer Management Center to be displayed. This list can be requested only if PeerSync is running on that machine and only if the PeerSync Management job is started on the Peer Management Center.

When the list is received, the view is updated with the latest updated events processed by PeerSync, and the caption on the top of the view will show the date and time the list was last updated.

By right-clicking on the info table, you can choose to hide or show columns.

This information on this table can be filtered by Path or by Job Name.

Overview PeerSync Jobs Stats Added Updated Deleted Messages							
Updated Log							
0 errors, 0 warnings, 100 others Filter by: <input type="text"/> <input type="text"/>							
Date	Type	Path	Comments	Message	Job Name	File Size	Modified Time
09-15-2015 17:0...	Event	c:\target\FLDR3\FILE33....	Updated [Attri...		Data Backup	2.5 KB	09-15-2015 17:03:50
09-15-2015 17:0...	Event	c:\target\FLDR3\FILE35....	Updated [Attri...		Data Backup	1.9 KB	09-15-2015 17:03:50
09-15-2015 17:0...	Event	c:\target\FLDR3\FILE37....	Updated [Attri...		Data Backup	3.8 KB	09-15-2015 17:03:50
09-15-2015 17:0...	Event	c:\target\FLDR3\FILE36....	Updated [Attri...		Data Backup	1.7 KB	09-15-2015 17:03:50
09-15-2015 17:0...	Event	c:\target\FLDR2\FILE13....	Updated [Attri...		Data Backup	3.6 KB	09-15-2015 17:03:48
09-15-2015 17:0...	Event	c:\target\FLDR2\FILE16....	Updated [Attri...		Data Backup	1.6 KB	09-15-2015 17:03:48
09-15-2015 17:0...	Event	c:\target\FLDR2\FILE12....	Updated [Attri...		Data Backup	1.3 KB	09-15-2015 17:03:48
09-15-2015 17:0...	Event	c:\target\FLDR2\FILE14....	Updated [Attri...		Data Backup	2.9 KB	09-15-2015 17:03:48
09-15-2015 17:0...	Event	c:\target\FLDR2\FILE15....	Updated [Attri...		Data Backup	2.1 KB	09-15-2015 17:03:48
09-15-2015 17:0...	Event	c:\target\FLDR2\FILE10....	Updated [Attri...		Data Backup	3.0 KB	09-15-2015 17:03:48
09-15-2015 17:0...	Event	c:\target\FLDR2\FILE11....	Updated [Attri...		Data Backup	1.4 KB	09-15-2015 17:03:48
09-15-2015 17:0...	Event	c:\target\FLDR2\FILE17....	Updated [Attri...		Data Backup	2.3 KB	09-15-2015 17:03:48
09-15-2015 17:0...	Event	c:\target\FLDR2\FILE18....	Updated [Attri...		Data Backup	1.0 KB	09-15-2015 17:03:48
09-15-2015 17:0...	Event	c:\target\FLDR2\FILE19....	Updated [Attri...		Data Backup	2.3 KB	09-15-2015 17:03:48
09-15-2015 17:0...	Event	c:\target\FLDR2\FILE23....	Updated [Attri...		Data Backup	1.9 KB	09-15-2015 17:03:48
09-15-2015 17:0...	Event	c:\target\FLDR2\FILE21....	Updated [Attri...		Data Backup	1.3 KB	09-15-2015 17:03:48
09-15-2015 17:0...	Event	c:\target\FLDR2\FILE20....	Updated [Attri...		Data Backup	3.0 KB	09-15-2015 17:03:48

Deleted Files

When clicking on the **Deleted** tab, a request goes out to the PeerSync machine to request a list of latest deleted files and return it to the Peer Management Center to be displayed. This list can be requested only if PeerSync is running on that machine and only if the PeerSync Management job is started on the Peer Management Center.

When the list is received, the view is updated with the latest deleted events processed by PeerSync, and the caption on the top of the view will show the date and time the list was last updated.

By right-clicking on the info table, you can choose to hide or show columns.

This information on this table can be filtered by Path or by Job Name.

Overview PeerSync Jobs Stats Added Updated Deleted Messages							
Deleted Log (List Updated on 10-05-2015 11:57:51)							
0 errors, 0 warnings, 10 others Filter by: <input type="text"/> <input type="text"/>							
Date	Type	Path	Comments	Message	Job Name	File Size	Modified Time
10-05-2015 11:5...	Data Bac...	c:\target\FLDR3	Scan		Session	0 bytes	10-05-2015 11:57:49
10-05-2015 11:5...	Data Bac...	c:\target\FILE6.TXT	Scan		Session	1.2 KB	10-05-2015 11:57:49
10-05-2015 11:5...	Data Bac...	c:\target\FILE4.TXT	Scan		Session	1.3 KB	10-05-2015 11:57:49
10-05-2015 11:5...	Data Bac...	c:\target\FILE8.TXT	Scan		Session	1.5 KB	10-05-2015 11:57:49
10-05-2015 11:5...	Data Bac...	c:\target\FILE2.TXT	Scan		Session	3.1 KB	10-05-2015 11:57:49
10-05-2015 11:5...	Data Bac...	c:\target\FILE5.TXT	Scan		Session	0 bytes	10-05-2015 11:57:48
10-05-2015 11:5...	Data Bac...	c:\target\FILE7.TXT	Scan		Session	2.1 KB	10-05-2015 11:57:48
10-05-2015 11:5...	Data Bac...	c:\target\FILE9.TXT	Scan		Session	2.2 KB	10-05-2015 11:57:48
10-05-2015 11:5...	Data Bac...	c:\target\FILE1.TXT	Scan		Session	1.3 KB	10-05-2015 11:57:48
10-05-2015 11:5...	Data Bac...	c:\target\FILE3.TXT	Scan		Session	1.4 KB	10-05-2015 11:57:48

Messages

When clicking on the **Messages** tab, a request goes out to the PeerSync machine to request a list of messages/errors logged and return it to the Peer Management Center to be displayed. This list can be requested only if PeerSync is running on that machine and only if the File Synchronization job is started on the Peer Management Center.

When the info list is received the view is updated with the messages logged by PeerSync, and the caption on the top of the view will show the date and time the list was last updated.

By right-clicking on the info table, you can choose to hide or show columns.

This information on this table can be filtered by Path, Job Name, or Message.

Overview	PeerSync Jobs Stats	Added	Updated	Deleted	Messages
Message Log (List Updated on 09-30-2015 13:53:45)					
0 errors, 0 warnings, 13 others Filter by: <input type="text"/> <input type="text"/>					
Date	Path	Message	Job Name		
09-30-2015 13:2...	\\backupserver\da...	Failed Event - Add...	Data 3 Backup		
09-30-2015 13:2...	\\backupserver\da...	Failed Event - Add...	Data 3 Backup		
09-30-2015 13:2...	\\backupserver\da...	Failed Event - Add...	Data 3 Backup		
09-30-2015 12:2...	\\backupserver\da...	Failed Event - Add...	Data 3 Backup		
09-30-2015 12:1...	\\backupserver\da...	Failed Event - Add...	Data 3 Backup		
09-30-2015 12:1...	\\backupserver\da...	Failed Event - Add...	Data 3 Backup		
09-30-2015 12:1...	\\backupserver\da...	Failed Event - Add...	Data 3 Backup		
09-30-2015 12:1...	\\backupserver\da...	Failed Event - Add...	Data 3 Backup		
09-30-2015 12:1...	\\backupserver\da...	Failed Event - Add...	Data 3 Backup		
09-30-2015 12:1...	\\backupserver\da...	Failed Event - Add...	Data 3 Backup		
09-30-2015 12:0...	\\backupserver\da...	Connection Failure	Data 3 Backup		
09-30-2015 12:0...	\\backupserver\da...	Cannot create/got...	Data 3 Backup		

The **Failed Events** view allows you to see all those events that have failed to be processed by PeerSync. The list is populated when the PeerSync Management job starts, as well as in real-time as new failures occur. The information can be filtered by File Name.

Summary ! Failed Events (2) Monitoring Log ! Alerts (16) Participants (1) Configuration

Failed Events

2 Files | Filter by File Name:

Date	File	Cause	Status	Message
09-30-2015 13:20:48	\\backupserver\data3\FLDR3\FILE...	ADDFILE	Failed Event	Connection Failure (Target Not A...
09-30-2015 13:20:48	\\backupserver\data3\FILE4 - Co...	ADDFILE	Failed Event	Connection Failure (Target Not A...

You can right-click the info table and choose to **Reprocess Failed Events**. This action will send a request to PeerSync to retry all the failed events in the list.

The **Monitoring Log** view allows you to view recent event history for the currently running PeerSync Management job based on your [Logging and Alerts](#) settings. You can specify the maximum number of events to store in the table by adjusting the **Display Events** spinner located in the top right corner of the panel. The maximum number of events that can be viewed is 3,000.

If you need to view more events or events from a prior session, then you can use the log files saved in the **Hub\logs** directory located in the installation directory. The event log files will start with **fs_event.log** and are written in a tab-delimited format. Microsoft Excel is a good tool to use to view and analyze a log file. See [Logging and Alerts](#) for more information about log files.

You can click on any column header to sort by the column. Warnings are displayed in light gray; errors are displayed in red; fatal errors are displayed in orange. Error records will also contain an error message in the **Message** column.

To change what is being logged, update the selected Event Types in the [Logging and Alerts](#) settings.

Summary ! Failed Events (2) **Monitoring Log** ! Alerts (16) Participants (1) Configuration

Event Log (Auto-Update Disabled)

0 errors, 0 warnings, 4 others | Filter by Severity: Filter by: Actions ▾

Date	Severity	Type	Host	Is Source	File	Comments	Message
09-30-2015 13:2...	INFO	Failed Events Reprocess	DDWin12R2b	true			Failed Event Repro...
09-30-2015 13:2...	INFO	Failed Events Reprocess	DDWin12R2b	true			Failed Event Repro...
09-30-2015 12:2...	INFO	Watch Directory		true			
09-30-2015 12:2...	INFO	Session Started		true			

Clicking the **Actions** table menu provides the following options:

Re fre sh Vi ew	Refresh all information provided in the table.
Cle ar Ev en ts	Remove all items from the table.

The **Alerts** view allows you to view any alerts relevant to the running PeerSync Management job. Items shown here are based on the configured Alerts Severity setting on the Logging and Alerts configuration page. You can specify the maximum number of alerts to store in the table by adjusting the Display Alerts spinner located in the top right corner of the panel.

The alerts are also written to a tab-delimited file named **fs_alert.log** within the subdirectory **Hub/logs** within the installation directory of the Peer Management Center. See the [Logging and Alerts](#) settings for more information about log files.

You can click on any column header to sort by that column. For example, clicking on the **Severity** column will sort by alert severity. Warnings are displayed in light gray; errors and fatal alerts are displayed in red. A common error may be the PeerSync service is not running, which will trigger a PeerSync Quorum lost alert.

Summary ! Failed Events (2) Monitoring Log ! Alerts (16) Participants (1) Configuration

Alert Log

16 errors, 0 warnings, 0 others | Filter by Severity: ▼

Received Date	Severity	Type	Host	Message
09-30-2015 12:09:30	FATAL	Application		PeerSync Quorum lost for job DDWin12R2b[WestCo...
09-30-2015 12:09:30	ERROR	Application	DDWin12R2b	Service Not Running
09-30-2015 12:09:30	FATAL	Application		PeerSync Quorum lost for job DDWin12R2b[WestCo...
09-30-2015 12:09:30	ERROR	Application	DDWin12R2b	Service Not Running
09-30-2015 12:07:30	FATAL	Application		PeerSync Quorum lost for job DDWin12R2b[WestCo...
09-30-2015 12:07:30	ERROR	Application	DDWin12R2b	Service Not Running
09-30-2015 12:07:30	FATAL	Application		PeerSync Quorum lost for job DDWin12R2b[WestCo...
09-30-2015 12:07:30	ERROR	Application	DDWin12R2b	Service Not Running
09-30-2015 11:53:59	FATAL	Application		Quorum lost for job DDWin12R2b[WestCoast]. Sessi...
09-30-2015 11:53:59	ERROR	Application	DDWin12R2b	Agent on host DDWin12R2b was restarted while job ...
09-30-2015 11:52:41	FATAL	Application		PeerSync Quorum lost for job DDWin12R2b[WestCo...
09-30-2015 11:52:41	ERROR	Application	DDWin12R2b	Service Not Running
09-30-2015 11:51:11	FATAL	Application		PeerSync Quorum lost for job DDWin12R2b[WestCo...
09-30-2015 11:51:11	ERROR	Application	DDWin12R2b	Service Not Running
09-30-2015 11:50:54	FATAL	Application		PeerSync Quorum lost for job DDWin12R2b[WestCo...
09-30-2015 11:50:54	ERROR	Application	DDWin12R2b	Service Not Running

The following right-click menu items are unique to this table:

Ref res h Vie w	Refresh all information provided in the table. This can also be done from the right-click context menu of the table.
Cle ar Ev ent s	Remove all items from the table. This can also be done from the right-click context menu of the table.

The **Participants** view shows the currently configured host participant for the selected PeerSync Management job and contains a column used to display activity status occurring on the hosts. If a host has become unavailable or the PeerSync service stopped, an error message will be displayed in red next to the failed host.

Summary Failed Events (2) Monitoring Log Alerts (16) **Participants (1)** Configuration

Host Participants

Host	Root Path	Status	State	Message
DDWin12R...	C:\Program Files (x86)\P...	Participating	Active	

Host Participant State Change Log

Filter by: Host: Status: State:

Date	Host	Status	State	Message
09-30-2015 ...	DDWin12R...	Participating	Active	
09-30-2015 ...	DDWin12R...	Not Participating	Inactive	Job Stopped
09-30-2015 ...	DDWin12R...	Participating	Active	
09-30-2015 ...	DDWin12R...	Not Participating	Inactive	Job Stopped
09-30-2015 ...	DDWin12R...	Participating	Active	
09-30-2015 ...	DDWin12R...	Not Participating	Inactive	Job Stopped
09-30-2015 ...	DDWin12R...	Participating	Active	
09-30-2015 ...	DDWin12R...	Host Resource Av...	Active	PeerSync Service is running
09-30-2015 ...	DDWin12R...	Host Resource Av...	Active	PeerSync Service Available
09-30-2015 ...	DDWin12R...	Host Resource Un...	Inactive	PeerSync Service Not Running
09-30-2015 ...	DDWin12R...	Host Resource Av...	Active	PeerSync Service is running
09-30-2015 ...	DDWin12R...	Host Resource Av...	Active	PeerSync Service Available
09-30-2015 ...	DDWin12R...	Host Resource Un...	Inactive	PeerSync Service Not Running
09-30-2015 ...	DDWin12R...	Participating	Active	
09-30-2015 ...	DDWin12R...	Not Participating	Inactive	Job Stopped
09-30-2015 ...	DDWin12R...	Participating	Active	
09-30-2015 ...	DDWin12R...	Participating	Active	
09-30-2015 ...	DDWin12R...	Host Unavailable	Inactive	Agent on host DDWin12R2b was restarted while jo

The **Participants** view also contains a table that displays the most recent host participant state changes, for example, when a host was removed from synchronization session, when a host came back online, or when the PeerSync service was stopped or started. This functionality is broken down into two parts: right-click context menu items and the **Host Participant State Change Log** view.

The **Host Participant State Change Log** is a log of all host participant status changes (e.g., Collaborating, Not Collaborating) and/or state changes (e.g., Active, Pending Restart) of a host participant. This table is currently limited to 250 rows and can be filtered by host, by status, and by state.

The following items are available in the right-click context menu for this table:

Refresh View	Refresh all information provided in the table.
Clear Events	Remove all items from the table.

The **Configuration** view displays a quick summary of all configurable items for the selected PeerSync Management job. Each page of the **File Synchronization Configuration** dialog is represented in its own part of the view and can be collapsed if desired.

Clicking **Edit this Configuration** will immediately bring you to the **PeerSync Management Configuration** dialog where you can edit the current monitoring configuration or the associated PeerSync profile.

Summary ! Failed Events (2) Monitoring Log ! Alerts (16) Participants (1) Configuration

[Edit this Configuration](#)

Configuration Summary

General Settings

Host Name: DDWin12R2b
 Session Name: DDWin12R2b[WestCoast]
 Session ID: 101
 Alert Severity: WARNING

Configured PeerSync Jobs


Filter by: Include Disabled Jobs

Name	#	Source	Target	Type
<input checked="" type="checkbox"/> Data 3 Backup	3	c:\source3	\\backupserver\data3	Real Time Backup
<input checked="" type="checkbox"/> Data Backup	1	c:\source	c:\target	Real Time Backup
<input checked="" type="checkbox"/> Data2 Backup	2	c:\source2	c:\target2	Real Time Backup


Monitoring Settings

Upgrade/Reprocess Installation

From the [Synchronization Summary view](#), you can click on one or more PeerSync Management jobs and choose **Reprocess/Upgrade Installation**. This option sends a request to the selected PeerSync instances to install/upgrade given the configured settings.



The installation settings should be common for ALL the PeerSync Management PeerSync instances in order to successfully install PeerSync.



The screenshot shows a window titled "File Synchronization Configuration" with a blue header bar. The "Installation Settings" tab is active, displaying "Remote Installation Settings". The form includes the following fields and controls:

- Pre-Defined Settings:** A dropdown menu set to "EastCoast" and a text box containing "EastCoast".
- Installation Path:** A text box containing the path "%ProgramFiles%\Peer Software\PeerSync".
- Existing Exe:** A dropdown menu and a "Browse" button.
- Imported Exe Version:** A text box containing "v9.3.1.1007 [C:\Program Files (x86)\Peer Software\Peer Management Hub\Hub\workspace\peersync\templates\exes\peersync93-9_3_1_1007.exe]".
- License Section:**
 - User Name:** Text box containing "Peer Software".
 - Company:** Text box containing "Peer Software".
 - Options:** Text box with a yellow highlight.
 - Password:** Text box with a yellow highlight.
- Service Section:**
 - Logon User:** Text box containing "bytemetrics\adminidanielad".
 - Password:** Text box filled with 12 dots.

At the bottom right, there are "Finish" and "Cancel" buttons.

See [Installation Settings](#) for information on the settings on this page.

Index

- A -

- Access, PeerGFS API 174
- Active Directory authentication 373
- Active Directory groups 370
- Active Directory users 110, 370
- Admin user 111
- Advanced configuration options, Amazon FSxN 324
- Advanced configuration options, Dell EMC Isilon 329
- Advanced configuration options, Dell EMC Unity 334
- Advanced configuration options, Dell EMC VNX 339
- Advanced configuration options, Dell PowerScale 329
- Advanced configuration options, NetApp 7-Mode 346
- Advanced configuration options, NetApp cDOT 353
- Advanced configuration options, Nutanix Files 358
- Agent availability 300
- Agent configuration 159
- Agent configuration, Broker 162
- Agent configuration, General 164
- Agent configuration, Logging 166
- Agent configuration, Performance 167
- Agent connectivity, preferences 300
- Agent properties, editing 172
- Agent properties, viewing 170
- Agent Summary view 60
- Agent, disabled 158
- Agent, disconnected 300
- Agent, installation 18
- Agent, re-enabling 158
- Agent, updating 25, 174
- Agent, VM options 169
- Agents view 33
- Alerts 98, 105
- Alerts view 35
- Amazon FSxN configuration 319
- Amazon FSxN credentials 319
- Amazon FSxN prerequisites 9
- Amazon FSxN, advanced configuration options 324
- Amazon S3 416, 423
- API 174
- API access 174
- API categories 176
- API integration 175
- API reference 176
- API status codes 177
- Application support, File Collaboration job 577, 613
- Application support, File Synchronization job 742
- Auto match root 519
- Auto-restarting, File Collaboration job 626
- Auto-restarting, File Synchronization job 755
- Azure Blob Storage 414
- Azure Storage 421

- B -

- Bash 175
- Basic concepts 78
- Batched emails 259
- Batched real-time 433
- Broker configuration, preferences 302
- Broker statistics 70, 71, 72, 74
- Broker, Agent configuration 162
- Browsing files and folders 298
- Bucket 420
- Bucket details, Amazon S3 423
- Bucket details, NetApp StorageGRID 425
- Bucket details, Nutanix Objects 427

- C -

- CDP 434
- Cloud Backup and Replication job, creating 383
- Cloud Backup and Replication job, proxy configuration 388
- Cloud Backup and Replication jobs 382
- Cloud Backup and Replication jobs, overview 383
- Cloud Backup and Replication jobs, preferences 196
- Collab and Sync Summary view, Reports tab 66
- Collab and Sync Summary view, Summary tab 63
- Complex regular expressions 88
- Concepts 78
- Configuration 8

Configuration, Agent 159
 Configuration, Preferences 193
 Conflict resolution, File Collaboration job 602
 Conflict resolution, File Synchronization job 734
 Conflict resolution, metadata 606, 738
 Conflicts 146
 Connection statuses 157
 Container 420
 Container details, Azure Storage 421
 Continuous data protection 434
 Create File Collaboration job 519
 Create File Synchronization job 519
 Credentials 202
 Credentials, Amazon FSxN 319
 Credentials, Dell EMC Isilon 328
 Credentials, Dell EMC Unity 333
 Credentials, Dell EMC VNX/Celerra 338
 Credentials, Dell PowerScale 328
 Credentials, NetApp 7-Mode 342
 Credentials, NetApp cDOT 349
 Credentials, Nutanix Files 354
 Custom web roles 116

- D -

Dashboard view 37
 Data recovery 451
 Database compression 70, 71, 72, 74
 Database connections 198
 Delayed replication 177
 Dell EMC configuration 325
 Delta-level replication 437
 Delta-level replication, File Collaboration job 604
 Delta-level replication, File Synchronization job 736
 Destination credentials 414, 416, 418, 419
 Destination snapshot report 205
 Destination storage credentials 202
 Detector settings 519
 DFS 149
 DFS namespace 519
 DFS namespace folder, adding 507
 DFS namespace root path 285, 471, 501, 519
 DFS namespace server, adding 501
 DFS Namespace, elements 147
 DFS namespace, failover and failback 230
 DFS Namespaces service 471, 501
 DFS namespaces, connecting to jobs 518

DFS namespaces, managing 501
 DFS-N Link, File Collaboration job 619
 DFS-N Link, File Synchronization job 748
 DFS-N Management job, creating 465
 DFS-N Management job, folder targets 475
 DFS-N Management job, importing existing namespace 490
 DFS-N Management job, Management Agent 467
 DFS-N Management job, namespace folders 475
 DFS-N Management job, namespace name 470
 DFS-N Management job, namespace server 471
 DFS-N Management job, namespace settings 474
 DFS-N Management job, running 499
 DFS-N Management job, starting 499
 DFS-N Management job, stopping 501
 DFS-N Management job, verifying Agent 468
 DFS-N Management jobs, preferences 285
 Disabled agent 158
 Disconnected agent 300
 DSU, master-edge assignment 572, 597, 701

- E -

Editing multiple File Collaboration jobs 620, 749
 Email alerts, Cloud Backup and Replication job 440
 Email alerts, concepts 78
 Email alerts, DFS-N Management job 481
 Email alerts, File Collaboration job 577, 615
 Email alerts, File Replication job 658
 Email alerts, File Synchronization job 706, 744
 Email alerts, preferences 205, 259, 303
 EMC Isilon environment prerequisites 9
 EMC VNX/Celerra environment prerequisites 9
 Enhanced metadata conflict resolution 606, 738
 Environmental requirements 9
 Event detection 360
 Event detection analytics 70, 71, 72, 74
 Expedited Sync Queue 227

- F -

File and folder filters, preferences 211, 266
 File Collaboration job, application support 577, 613
 File Collaboration job, auto-restarting 626
 File Collaboration job, conflict resolution 602

- File Collaboration job, create job from namespace folder 519
- File Collaboration job, creating 531
- File Collaboration job, delta-level replication 604
- File Collaboration job, DFS-N Link 619
- File Collaboration job, editing 585
- File Collaboration job, editing participants 595
- File Collaboration job, email alerts 577, 615
- File Collaboration job, file filters 601
- File Collaboration job, file locking 608, 740
- File Collaboration job, file metadata 575, 606
- File Collaboration job, general 599
- File Collaboration job, host connectivity issues 628
- File Collaboration job, Management Agent 535
- File Collaboration job, participants 533, 587
- File Collaboration job, running 622
- File Collaboration job, runtime view 45
- File Collaboration job, runtime view, Alerts tab 53
- File Collaboration job, runtime view, Configuration tab 56
- File Collaboration job, runtime view, Event Log tab 50
- File Collaboration job, runtime view, Participants tab 54
- File Collaboration job, runtime view, Quarantines tab 52
- File Collaboration job, runtime view, Retries tab 52
- File Collaboration job, runtime view, Session tab 48
- File Collaboration job, runtime view, Summary tab 46
- File Collaboration job, SNMP notifications 617
- File Collaboration job, starting 624
- File Collaboration job, stopping 626
- File Collaboration job, tags 618
- File Collaboration job, target protection 613
- File Collaboration jobs 530
- File Collaboration jobs, editing multiple 620, 749
- File Collaboration jobs, overview 530
- File Collaboration jobs, preferences 225
- File conflicts 146
- File filters 79
- File filters, Cloud Backup and Replication job 411
- File filters, creating 80
- File filters, File Collaboration job 601
- File filters, File Synchronization job 731
- File filters, predefined 81
- File filters, usage notes 95
- File locking 269
- File locking, File Collaboration job 608, 740
- File menu 70, 71, 72, 74
- File metadata 153, 437
- File metadata, File Collaboration job 575, 606
- File metadata, File Synchronization job 704, 738
- File quarantine 146
- File Replication job, email alerts 658
- File Replication job, runtime view 57
- File Replication jobs 630
- File Replication jobs, preferences 225
- File retries 146, 265
- File Retries and Source Snapshots, preferences 208
- File Synchronization job, application support 742
- File Synchronization job, auto-restarting 755
- File Synchronization job, conflict resolution 734
- File Synchronization job, create job from namespace folder 519
- File Synchronization job, creating 661
- File Synchronization job, delta-level replication 736
- File Synchronization job, DFS-N Link 748
- File Synchronization job, editing 713
- File Synchronization job, editing participants 723
- File Synchronization job, email alerts 706, 744
- File Synchronization job, file filters 731
- File Synchronization job, file metadata 704, 738
- File Synchronization job, General 729
- File Synchronization job, host connectivity issues 756
- File Synchronization job, Management Agent 665
- File Synchronization job, participants 663, 716
- File Synchronization job, running 751
- File Synchronization job, runtime view 58
- File Synchronization job, SNMP notifications 746
- File Synchronization job, starting 753
- File Synchronization job, stopping 755
- File Synchronization job, tags 747
- File Synchronization job, target protection 742
- File Synchronization jobs 660
- File Synchronization jobs, preferences 225
- Files and folders, browsing 298
- Filter expressions 97
- Filter patterns 84
- Filter patterns, complex regular expressions 88
- Filter patterns, excluding temporary files 86
- Filter patterns, using wildcards 85

Filter, scheduled replication 177
 Filtering by date 88
 Filtering by file size 91
 Filtering folders 93
 Filters, file 95
 Filters, folders 93
 Filters, list 96
 Folder filters 79
 Folder filters, creating 80
 Folder target, adding 513
 Folders, filtering 93

- G -

General Configuration, preferences 297, 298
 General, Agent configuration 164
 General, File Collaboration job 599
 General, File Synchronization job 729

- H -

Heartbeats 300
 Help menu 70, 71, 72, 74
 Hidden items 298

- I -

Importing existing namespace 490
 Initial synchronization process 623, 752
 Initialization process 623, 752
 Installation 8
 Installation, Peer Agent 18
 Internal users 110, 111, 112, 364, 366
 Isilon credentials 328
 Isilon, advanced configuration options 329

- J -

Job alerts 105
 Job Alerts view 38
 Job initialization process 623, 752
 Job logs 105
 Job, manual retries 630, 758
 Jobs views 39
 Jobs, Cloud Backup and Replication 382
 Jobs, File Collaboration 530
 Jobs, File Replication 630

Jobs, File Synchronization 660
 Jobs, PeerSync Management 759

- K -

Keytool certificate management utility 180

- L -

Last modified date 88
 LDAP administrator 373
 LDAP settings 364
 License 180
 License file 311
 Licensed storage capacity 180
 Licensing 311
 Link namespace folder to job 525
 Link namespace to job 518
 List filter expressions 97
 List filters, concepts 96
 List filters, examples 97
 List filters, managing 98
 List filters, removing 98
 Locking 269
 Log files 100
 Logging 98
 Logging, Agent configuration 166
 Logs 105

- M -

Malicious Event Detection 313
 Management Agent 387
 Management Agent, DFS-N Management job 467
 Management Agent, File Collaboration job 535
 Management Agent, File Synchronization job 665
 Master-edge assignment, DSU 572, 597, 701
 MED configuration, preferences 313
 Memory dump file 70, 71, 72, 74
 Menus 70, 71, 72, 74
 Metadata 153
 Metadata conflict resolution 606, 738
 Miscellaneous options 437

- N -

Namespace elements 147

- Namespace failback 149
- Namespace failover 149
- Namespace folder 519
- Namespace folder target, adding 513
- Namespace folder target, disable 230
- Namespace folder target, renewable 230
- Namespace folder, adding 507
- Namespace folder, linking to job 525
- Namespace server 471
- Namespace server, adding 501
- Namespace, linked to job 518
- NAS configuration, Amazon FSxN 319
- NAS configuration, Dell EMC 325
- NAS configuration, NetApp 7-Mode 342
- NAS configuration, NetApp cDOT 349
- NAS configuration, Nutanix Files 354
- NAS configuration, preferences 319
- NetApp 7-Mode configuration 342
- NetApp 7-Mode credentials 342
- NetApp 7-Mode environment prerequisites 9
- NetApp 7-Mode, advanced configuration options 346
- NetApp cDOT configuration 349
- NetApp cDOT credentials 349
- NetApp cDOT, advanced configuration options 353
- NetApp cDOT/ONTAP9+ environment prerequisites 9
- NetAPP prerequisites 10
- NetApp StorageGRID 418, 425
- NTFS permissions 437, 575, 606, 704, 738
- Nutanix Files configuration 354
- Nutanix Files credentials 354
- Nutanix Files, advanced configuration options 358
- Nutanix Objects 419, 427
- Nutanix prerequisites 10
- Participants, adding to File Collaboration job 588
- Participants, adding to File Synchronization job 717
- Participants, editing 595, 723
- Participants, File Collaboration job 533, 587
- Participants, File Synchronization job 663, 716
- Participants, removing from File Collaboration job 588
- Participants, removing from File Synchronization job 717
- Peer Agent, installation 18
- Peer Agent, updating 25
- Peer Agents, managing 154
- Peer Global File Service license 180, 311
- Peer Management Broker 587, 716
- Peer Management Center, updating 23
- PeerGFS API 174
- PeerGFS license 180, 311
- PeerGFS preferences 192
- PeerSync Management jobs 759
- Performance, Agent configuration 167
- Performance, preferences 214, 270
- Permissions 112
- Permissions, PeerSync Management jobs 113
- Permissions, web roles 113
- PMC user interface 26
- PMC user interface, views 32
- PMC, updating 23
- PMC/Agent logs 70, 71, 72, 74
- PowerScale advanced configuration options 329
- PowerScale credentials 328
- Powershell 175
- Predefined file filters 81
- Preferences 192
- Preferences, Agent connectivity 300
- Preferences, Broker configuration 302
- Preferences, Cloud Backup and Replication 196
- Preferences, configuring 193
- Preferences, database connections 198
- Preferences, email alerts 205, 259
- Preferences, file and folder filters 211, 266
- Preferences, File Collaboration jobs 225
- Preferences, File Replication jobs 225
- Preferences, File Retries and Source Snapshots 208
- Preferences, File Synchronization jobs 225
- Preferences, General configuration 297, 298
- Preferences, MED configuration 313
- Preferences, NAS configuration 319
- Preferences, performance 214, 270
- Preferences, real-time event detection 227, 272
- Preferences, replication and retention policies 219
- Preferences, Scan Manager 223, 278
- Preferences, SNMP Notifications 221, 243, 274
- Preferences, Software updates 306

Preferences, system alerts 303
 Preferences, tags 308
 Prerequisites, Amazon FSxN 9
 Prerequisites, NetAPP 10
 Prerequisites, Nutanix 10
 Pre-Seeding 178
 Properties, Agent 170, 172
 Proxy configuration 388

- Q -

Quarantined file 259, 629, 757
 Quarantines 146

- R -

Real-time event detection 272, 360
 Real-time event detection, preferences 227, 272
 Real-time replication 177
 Reconnect attempts 300
 Recovering data 451
 Re-enable agent 158
 Rehydrated data 437
 Removing file from quarantine 629, 757
 Replication and Retention Policies, preferences 219
 Replication and Retention policy 429
 Replication schedule 430, 431, 433, 434
 Reports tab, Collab and Sync Summary view 66
 Reports, destination snapshot 205
 Reports, scan 205
 Requirements, environment 9
 Retention 435
 Retries 146
 Retrying a job 630, 758
 REVIT 227
 Rich client interface 110
 Rich client users 110
 Roles 364
 Runtime views 42

- S -

Scan Manager, preferences 223, 278
 Scan report 205
 Scheduled replication 177
 Scheduled replication filter 177

Scheduled scans 431
 Security 180
 Seeding Target 587, 716
 Smart Data Seeding 177, 178
 Snapshots, source 436
 SNMP notifications, Cloud Backup and Replication job 442
 SNMP notifications, DFS-N Management job 484
 SNMP notifications, File Collaboration job 617
 SNMP notifications, File Synchronization job 746
 SNMP notifications, overview 106
 SNMP Notifications, preferences 221, 243, 274
 Software updates, preferences 306
 Source paths 409
 Source snapshots 436
 Source storage platform 386
 Standard web roles 113
 Starting, DFS-N Management job 499
 Starting, File Collaboration job 624
 Starting, File Synchronization job 753
 Status codes, API 177
 Stopping, DFS-N Management job 501
 Stopping, File Collaboration job 626
 Stopping, File Synchronization job 755
 Storage capacity 180
 Storage information 394
 Storage platform credentials 202
 Storage tiering options 437
 Summary tab, Collab and Sync Summary view 63
 Summary views 59
 System alerts 298, 303
 System folders 298

- T -

Tables 77
 Tag categories 107
 Tags overview 107
 Tags, assigning 107
 Tags, File Collaboration job 618
 Tags, File Synchronization job 747
 Tags, filtering resources 110
 Tags, preferences 308
 Target protection, File Collaboration job 613
 Target protection, File Synchronization job 742
 Temporary files 86
 Terminology 1
 Testing API access 175

Thread dump file 70, 71, 72, 74
TLS certificates 180
TLS certificates, existing 187
TLS certificates, new 180
Toolbar 75

- U -

Unity credentials 333
Unity, advanced configuration options 334
Updating software 306
Updating, Agent 174
Updating, Peer Agent 25
Updating, PMC 23
Upgrade 311
User interface 26, 110
User management 364
Users, internal 111, 112, 366

- V -

Views 32
Views, Agent Summary 60
Views, Agents 33
Views, Alerts 35
Views, dashboard 37
Views, Job Alerts 38
Views, Jobs 39
Views, runtime 42
Views, summary 59
VM options 169
VNX, advanced configuration options 339
VNX/Celerra credentials 338

- W -

Web client interface 110
Web client user 110, 112, 113
Web client, accessing 29, 31
Web client, configuration 16
Web role 110
Web role, Administrator 113
Web role, custom 112
Web role, Help Desk 113
Web role, Power User 113
Web role, standard 112
Web roles 111, 112

Web roles, custom 116
Web roles, permissions 113, 117
Web roles, standard 113
Wildcards, filter patterns 85
Window menu 70, 71, 72, 74

- Y -

YAML file 175